

01 July 2025

QUANTUM SECURITY MANAGEMENT

R82

Administration Guide



Check Point Copyright Notice

© 2024 - 2025 Check Point Software Technologies Ltd.

All rights reserved. This product and related documentation are protected by copyright and distributed under licensing restricting their use, copying, distribution, and decompilation. No part of this product or related documentation may be reproduced in any form or by any means without prior written authorization of Check Point. While every precaution has been taken in the preparation of this book, Check Point assumes no responsibility for errors or omissions. This publication and features described herein are subject to change without notice.

RESTRICTED RIGHTS LEGEND:

Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.227-7013 and FAR 52.227-19.

TRADEMARKS:

Refer to the Copyright page for a list of our trademarks.

Refer to the <u>Third Party copyright notices</u> for a list of relevant copyrights and third-party licenses.

Important Information



Latest Software

We recommend that you install the most recent software release to stay up-todate with the latest functional improvements, stability fixes, security enhancements and protection against new and evolving attacks.



Certifications

For third party independent certification of Check Point products, see the <u>Check</u> <u>Point Certifications page</u>.



Check Point R82 For more about this release, see the R82 home page.



Latest Version of this Document in English Open the latest version of this document in a Web browser.

Download the latest version of this <u>document in a Web browser</u>.



Feedback

Check Point is engaged in a continuous effort to improve its documentation. Please help us by sending your comments.

Patent Notice

Check Point Quantum Security Management is protected by the following patents in the United States and elsewhere.



This page is intended to serve as notice under 35 U.S.C. § 287(a): US7,647,492, US7,769,862, US7,797,566, US7,950,059, US8,051,187, US8,146,159, US8,161,188, US8,176,539, US8,200,818, US8,254,698, US8,406,233, US8,533,808, US8,615,655, US8,644,328, US8,726,008, US8,776,017, US8,843,993, US8,844,019, US8,850,576, US8,902,900, US8,948,193, US8,959,047, US9,137,204, US9,208,317, US9,210,128, US9,356,945, US9,483,583, US9,537,756, US9,569,265, US9,647,985, US9,672,189, US9,832,215, US9,935,903, US10,057,390, US10,382,493, US10,467,407, US10,567,395, US10,567,468, US10,645,074, US10,728,266, US10,728,274, US11,075,882, US11,165,820, US11,321,453, US11,323,426, US11,411,924, US11,606,375

Revision History

Date	Description
25 June 2025	Updated "Working with Manual NAT Rules" on page 425
16 June 2025	Updated "The Columns of the Access Control Rule Base" on page 328
28 May 2025	Updated "Connecting On-Premises Management Servers and Security Gateways to the Infinity Portal" on page 537
27 April 2025	Updated "HTTPS Inspection" on page 541
6 April 2025	Added "Blocking TLS Connections" on page 576
23 March 2025	Added "Policy Insights " on page 397 Updated "Creating an Administrator Account with SAML Authentication Login" on page 101
14 March 2025	Updated the chapter "UserCheck in the Access Control Policy" on page 516
25 February 2025	Updated "Central Deployment of Hotfixes and Version Upgrades" on page 244 - in the section "Limitations" added Security Group in Maestro and ElasticXL Cluster
06 February 2025	Updated:
	 "SmartConsole Window" on page 36 "SmartConsole Toolbars" on page 37
05 January	Added:
2025	 "SmartConsole Packages" on page 32 "Analyzing Threats" on page 515 "Testing New SmartConsole Features" on page 667
	Updated:
	 "Access, Custom and HTTPS Inspection Tools" on page 44 "Keyboard Shortcuts for SmartConsole" on page 48 "Updatable Objects" on page 295 "Managing Administrator Accounts" on page 74 "Managing User Accounts" on page 135

Date	Description
01 January 2025	Updated "Security Zones" on page 305
29 December 2024	Updated: "Security Management behind NAT" on page 477 "HTTPS Inspection" on page 541
15 December 2024	Updated "HTTPS Inspection" on page 541
01 December 2024	Updated "SmartTasks" on page 599
04 November 2024	Updated "The HealthCheck Point Tool" on page 276
21 October 2024	First release of this document

Table of Contents

Introduction to Quantum Security Management	
Workflow for Configuring Security Management	
SmartConsole Packages	
Connecting to the Security Management Server with SmartConsole	
Understanding SmartConsole	
SmartConsole Window	
SmartConsole Toolbars	
Search Engine	41
IP Search	41
General IP Search	41
Packet Search	42
Rule Base Results	
Access, Custom and HTTPS Inspection Tools	44
"Access Tools" in the Security Policies "Access Control" view	44
"Custom Policy Tools" in the Security Policies "Threat Prevention" view	44
HTTPS Inspection Tools in the Security Policies HTTPS Inspection View	
Shared Policies	
API Command Line Interface	47
Keyboard Shortcuts for SmartConsole	
Using Infinity AI Copilot in SmartConsole	
Prerequisites	
Planning Security Management	
Sizing the Security Management Server	
Define your Organization's Topology	53
Define Access Rules for Protection of your Organization's Resources	53
Enforce Access Policies	53
Configuring the Security Management Server and Security Gateways	

Managing Security through API	
API	56
API Tools	
Configuring the API Server	
Self-Managed Security Gateways	60
Introduction	
Requirements	
Limitations	
Notes	63
Configuration	
Resetting a Dynamic Layer	
Creating an Administrator Account with API Key Authentication	71
Managing Administrator Accounts	74
Creating an Administrator Account	
Editing an Administrator Account	77
Deleting an Administrator Account	78
Default Expiration for Administrators	
Configuring SmartConsole Session Timeout	79
Revoking an Administrator Certificate	
Restricting Administrator Login Attempts	
Unlocking Administrator Accounts	
Multiple Administrators	80
Creating an Administrator Account with Check Point Password Authentication	81
Creating an Administrator Account with OS Password Authentication	
Creating an Administrator Account with RADIUS Server Authentication	87
Creating an Administrator Account with TACACS Server Authentication	92
Creating an Administrator Account with SecurID Authentication	97
Creating an Administrator Account with SAML Authentication Login	101
Use Case	
SAML Authentication Login	

	Creating an Administrator Account with API Key Authentication	
	Assigning Permission Profiles to Administrators	
	Changing and Creating Permission Profiles	
	Configuring Customized Permissions	
	Configuring Permissions for Access Control Layers	
	Configuring Permissions for Access Control and Threat Prevention	
	Configuring Permissions for Monitoring, Logging, Events, and Reports	
	Defining Trusted Clients	
	Session Flow for Administrators	
	Publishing a Session	
	Working in SmartConsole Session View	
	Viewing Changes Made in Private Sessions	
	Taking over locked objects from administrators with inactive sessions	
	Administrators Working with Multiple Sessions	
	Approval Cycle for Sessions (SmartWorkflow and Identity Provider)	
	Use Case	
	Configuration	
	Setting up for Team Work	
١	Ianaging User Accounts	
	Creating a User Account	
	Changing an Existing User	
	Deleting a User	
	Managing User Groups	
	Configuring Default Expiration Settings for Users	
	Managing Users	141
	Creating a New User Template	141
	Creating a New User	
	Editing an Existing User	
	Deleting a User	
	Configuring Default Expiration Settings for Users	

Creating a User Account with Check Point Password Authentication	
Creating a User Account with OS Password Authentication	
Creating a User Account with RADIUS Server Authentication	
Configuring RADIUS Authentication for a User	
Granting User Access Using RADIUS Server Groups	
Creating a User Account with TACACS Server Authentication	
Creating a User Account with SecurID Authentication	
Access Roles	
Adding Access Roles	
User Directory	
User Directory Considerations	
Deploying User Directory	
Enabling User Directory	
User Directory Schema for LDAP	
Schema Checking	
OID Proprietary Attributes	
User Directory Schema Attributes	
Fetch User Information Effectively	
Setting User-to-Group Membership Mode	
Profile Attributes	
Managing Users on a User Directory Server	
Distributing Users in Multiple Servers	
Managing LDAP Information	
LDAP Groups for the User Directory	
Retrieving Information from a User Directory Server	
Running User Directory Queries	
Querying Multiple LDAP Servers	
Account Units	
Working with LDAP Account Units	
Configuring LDAP query parameters	

214
214
215
215
217
217
217
217
217
218
218
218
219
220
221
221
222
223
224
224
224
226
228
229
230
230
231

Managing Server and Gateway Licenses	
Viewing Licenses in SmartConsole	234
Viewing license information for VSX	
Monitoring Licenses in SmartConsole	
License or Quota Changes	
Security Gateway Indicators	240
Installing the Recommended Take on the Security Gateway	241
Central Deployment of Hotfixes and Version Upgrades	
Introduction	
Prerequisites	245
Limitations	246
Installation	246
Uninstalling a Hotfix or a Jumbo Hotfix Accumulator	250
How the Central Deployment Upgrades a Cluster	
Configuring a Security Gateway to Access the Management Server or Log Server its NATed IP Address	
Configuring Implied Rules or Kernel Tables for Security Gateways	254
Introduction	
Configuration files	
Configuration Procedure	
Location of 'user.def' Files on the Management Server	
Location of 'implied_rules.def' Files on the Management Server	
Location of 'table.def' Files on the Management Server	
Location of 'crypt.def' Files on the Management Server	
Location of 'vpn_table.def' Files on the Management Server	
Location of 'vpn_route.conf' Files on the Management Server	
Location of 'communities.def' Files on the Management Server	
Location of 'base.def' Files on the Management Server	
Location of 'dhcp.def' Files on the Management Server	
Location of 'gtp.def' Files on the Management Server	274

The HealthCheck Point Tool	
Statuses in SmartConsole	
Limitations	
Managing Objects	
Object Categories	
Actions with Objects	
Object Tags	
Adding a Tag to an Object	
Network Object Types	
Networks	
Network Groups	
Grouping Network Objects	
Check Point Hosts	
Gateway Cluster	
Address Ranges	
Wildcard Objects	
Understanding Wildcard Objects	
IPv6	
Domains	
Updatable Objects	
Introduction to Updatable Objects	
Adding an Updatable Object to the Access Control Policy	
Adding an Updatable Object to the Custom Threat Prevention Policy	
Adding an Updatable Object to the HTTPS Inspection Policy	
Monitoring Updatable Objects	
Updating the Updatable Objects through the Management Server	
Dynamic Objects	
Generic Data Center Objects	
Limitations	
Security Zones	

Processing Flow for Rule Base Execution when using Security Zones and NAT Rules	306
Creating and Assigning Security Zones	306
Predefined Security Zones	307
Limitations	308
Externally Managed Gateways and Hosts	309
Interoperable Devices	310
VoIP Domains	311
Logical Servers	312
Balance Method	312
Open Security Extension (OSE) Devices	313
Defining OSE Device Interfaces	313
OSE Device Properties Window - "General" Tab	314
Anti-Spoofing Parameters and OSE Devices Setup (Cisco)	314
Managing Policies	316
Working with Policy Packages	316
Viewing Rule Logs	323
Policy Installation History	324
Concurrent Install Policy	325
Accelerated Install Policy	326
Creating an Access Control Policy	327
Introducing the Unified Access Control Policy	327
The Columns of the Access Control Rule Base	328
Source and Destination Column	329
To Learn More About Network Objects	329
VPN Column	329
IPsec VPN	
Mobile Access to the Network	330
To Learn More About VPN	330
Services & Applications Column	330

Service Matching	
Application Matching	
Content Column	
Actions	
Tracking Column	
To Learn More About Tracking	
Rule Matching in the Access Control Policy	
The matching examples show that:	
Creating a Basic Access Control Policy	
Basic Rules	
Use Case - Basic Access Control	
Use Case - Inline Layer for Each Department	
Default Cell Values	
Enforcement of Rules with the Value "None"	
Upgrading of a Management Server from R81 and Lower Versions	
Creating Application Control and URL Filtering Rules	
Blocking URL Categories	
Ordered Layers and Inline Layers	
The Need for Ordered Layers and Inline Layers	
Order of Rule Enforcement in Inline Layers	
Order of Rule Enforcement in Ordered Layers	
Creating an Inline Layer	
Creating an Ordered Layer	
Enabling Access Control Features	
Types of Rules in the Rule Base	
Administrators for Access Control Layers	
Sharing Layers	
Visual Division of the Rule Base with Sections	
Managing Policies and Layers	
Best Practices for Access Control Rules	

Use Cases for the Unified Rule Base	
Self-Managed Security Gateways	
Introduction	
Requirements	
Limitations	
Notes	
Configuration	
Resetting a Dynamic Layer	
Installing the Access Control Policy	
Policy Insights	
Supported Objects	
Prerequisites	
Working with Policy Insights	
Components of the Policy Insights Window	
Analyzing the Rule Base Hit Count	
Enabling or Disabling Hit Count	
Hit Count Display	
Preventing IP Spoofing	
Anti-Spoofing Options	
Configuring the NAT Policy	
Getting Started with NAT	
Introduction	
Types of NAT Rules	
Types of NAT Methods	
NAT Rules in SmartConsole	
Order of NAT Rule Enforcement	414
Working with Automatic NAT Rules	
Example of Automatic NAT Rules	
Configuring Automatic NAT	
Example Deployment	

Automatic Hide NAT to External Networks	.423
Working with Manual NAT Rules	.425
Example of a Manual NAT Rule	.425
Configuring Manual NAT	.426
Example Deployment	. 426
Working with NAT46 Rules	432
Overview	.432
Known Limitations for NAT46	. 434
Configuring NAT46	. 434
Logging of NAT46 Traffic	.446
Working with NAT64 Rules	. 447
Overview	.447
Known Limitations for NAT64	. 448
Example of NAT64 Translation Flow	.448
Configuring NAT64	. 451
Logging of NAT64 traffic	.467
Advanced NAT Settings	468
Automatic and Proxy ARP	.468
NAT and Anti-Spoofing	.469
Disabling NAT in a VPN Tunnel	.470
Internal Communication with Overlapping Addresses	. 471
Example Network Configuration	.471
Communication Examples	.472
Routing Considerations	.473
Object Database Configuration	.473
Multicast Access Control	.475
Security Management behind NAT	. 477
Overview	.477
Configuring NAT for Control Connections on the Security Management Server	. 477
Configuration on the Security Gateway	.478

Overview	
NAT Priorities	
IP Pool per Interface	
Reusing IP Pool Addresses for Different Destinations	
IP Pool Configuration Procedure	
Mobile Access to the Network	
Check Point Mobile Access Solutions	
Client-Based vs. Clientless	
Mobile Access Clients	
Mobile Access Web Portal	
SSL Network Extender	
Configuring Mobile Access to Network Resources	
Sample Mobile Access Workflow	
Sample Mobile Access Deployment	
Using the Mobile Access Configuration Wizard	
Allowing Mobile Connections	
Defining Access to Applications	
Activating Single Sign-On	
Connecting to a Citrix Server	
Sample Deployment with Citrix Server	
Configuring Citrix Services for Mobile Access	
Compliance Check	
Compliance Policy Rules	
Creating a Compliance Policy	
Configuring Compliance Settings for a Security Gateway	
Secure Workspace	
Secure Workspace	
To Learn More About Mobile Access	
Site-to-Site VPN	

Sample Site-to-Site VPN Deployment	505
VPN Communities	505
Sample Combination VPN Community	508
Allowing VPN Connections	508
Sample VPN Access Control Rules	509
To Learn More About Site-to-Site VPN	509
Remote Access VPN	510
VPN Connectivity Modes	510
Sample Remote Access VPN Workflow	510
Configuring the Security Gateway for a Remote Access Community	512
To Learn More About Remote Access VPN	512
Implied Rules	513
Creating a New Threat Prevention Policy	514
Installing the Threat Prevention Policy	514
Analyzing Threats	515
UserCheck in the Access Control Policy	516
Configuring UserCheck	518
UserCheck Interaction Objects for Access Control Software Blades	522
UserCheck Interaction Action Types	522
Default UserCheck Interaction Objects for Access Control	523
Creating New UserCheck Interaction Objects for Access Control	523
Send Email Notifications in Plain Text	528
Localizing and Customizing the UserCheck Portal	530
External Network Feeds	531
Use Case	531
Monitoring	534
Troubleshooting	535
Connecting On-Premises Management Servers and Security Gateways to the Infinity Portal	
Prerequisites	

	Troubleshooting	
H	TTPS Inspection	
	Intercepting HTTPS Connections	
	Outbound HTTPS Inspection	
	Inbound HTTPS Inspection	
	Getting Started with HTTPS Inspection	
	HTTPS Inspection Policy	
	Configuring HTTPS Inspection Policy	
	HTTPS Inspection Policy Enforcement	
	Working with Inbound CA Certificates	
	Assigning a Server Certificate for Inbound HTTPS Inspection	
	Configuring HTTPS Inspection on the Security Gateway	
	HTTPS Inspection Deployment View	
	Working with Outbound CA Certificates	
	Creating an Outbound CA Certificate	
	Importing an Outbound CA Certificate	
	Exporting and Deploying the Generated CA Certificate	
	Deploying Certificates using Group Policy	
	Exporting a Certificate from one Security Management Server to Another	
	Working with Trusted CAs for Outbound HTTPS Inspection	
	HTTPS Inspection Global Settings	
	Fail Mode	
	Categorization Mode	
	Server Validations	
	Certificate Blocking	
	Bypass Allow Lists	
	Session Logs	
	Other	
	Intermediate CA	
	Bypass Under Load Logging	

HTTPS Inspection Statistics View	
Configuration	
Viewing HTTPS Inspection Statistics	
SNI support for Site Categorization	
HTTPS Inspection on Non-Standard Ports	
Inspection of TLS v1.3 Traffic	
Inspection of HTTP/3 protocol (RFC 9114)	
Using HTTPS/3 the in a Rule Base	
Monitoring the HTTP/3 inspection	
Limitations	
Blocking TLS Connections	
Prerequisites	
Procedure	
Client Certificates for Smartphones and Tablets	
Managing Client Certificates	
Creating Client Certificates	
Revoking Certificates	
Creating Templates for Certificate Distribution	
Cloning a Template	
Giving Permissions for Client Certificates	
Preferences and Management Settings	
Database Revisions	
Setting IP Address Versions of the Environment	
Restoring Window Default	
Configuring the Login Window	
Synchronization with UserCenter	
Inspection Settings	
Configuring Inspection Settings	
SmartTasks	
Available Triggers	

Available Actions	
Configuring SmartTask Properties	
SmartTask Advanced Properties	
Send Web Request	
Run script	
Send Email	
Network Security for IoT Devices	
Introduction	
Prerequisites	
Network Overview	
Network Diagram	
Configuring the IoT Third Party Discovery Service	
Adding IoT Assets to the Policy	
Infinity for IoT Logs	
Management High Availability	
Overview of Management High Availability	
The High Availability Environment	
Configuring a Secondary Security Management Server in SmartConsole	
Synchronizing Active and Standby Servers	
Monitoring High Availability	
Monitoring Synchronization Status and Actions	
Changing a Server to Active or Standby	
Working in Collision Mode	
Changeover Between Active and Standby	
High Availability Troubleshooting	
Not Communicating	
Collision or HA Conflict	
Sync Error	
Unlocking the Administrator	
Environments with Endpoint Security	

High Availability Disaster Recovery	
Compliance	
The Compliance View	
The Compliance Scoring System	
The Security Best Practices Compliance View	
Creating User-Defined Best Practices	
Activating and Deactivating Best Practice Tests	
The Gateways View	
The Blades View	
The Action Items and Messages View	
The Regulatory Compliance View	
Creating Reports	
The ICA Management Tool	
Overview	
Connecting to the ICA Management Tool	
The ICA Management Tool Portal	
User Certificate Management	
Modifying the Key Size for User Certificates	
Performing Multiple Simultaneous Operations	
ICA Administrators with Reduced Privileges	
Operations with Certificates	
Management of SIC Certificates	
Management of Security Gateway VPN Certificates	
Management of User Certificates in SmartConsole	
Notifying Users about Certificate Initialization	
Retrieving the ICA Certificate Files	
Searching for a Certificate	
Basic Search Parameters	
Advanced Search Attributes	
The Search Results	

Viewing and Saving Certificate Details	
Removing and Revoking Certificates and Sending Email Notifications	
Submitting a Certificate Request to the CA	
Initializing Multiple Certificates Simultaneously	
CRL	
CRL Management	
CRL Operations	
CA Procedures	
CA Cleanup	
Configuring the CA	
CA Data Types and Attributes	
Certificate Longevity and Statuses	
Gaia API Proxy	
Testing New SmartConsole Features	
Command Line Reference	
Syntax Legend for CLI Commands	
contract_util	
contract_util check	
contract_util cpmacro	
contract_util download	
contract_util mgmt	
contract_util print	
contract_util summary	
contract_util update	
contract_util verify	
cp_conf	
cp_conf admin	
cp_conf auto	
cp_conf ca	
cp_conf client	

cp_conf finger	
cp_conf lic	
cp_log_export	
cpca_client	
cpca_client create_cert	
cpca_client double_sign	
cpca_client get_crldp	
cpca_client get_pubkey	
cpca_client init_certs	
cpca_client lscert	
cpca_client revoke_cert	
cpca_client revoke_non_exist_cert	
cpca_client search	
cpca_client set_ca_services	
cpca_client set_cert_validity	
cpca_client set_mgmt_tool	741
cpca_client set_sign_hash	
cpca_create	
cpconfig	
cpinfo	
cplic	
cplic check	
cplic contract	
cplic db_add	
cplic db_print	
cplic db_rm	
cplic del	
cplic del <object name=""></object>	
cplic get	
cplic print	

cplic put	
cplic put <object name=""></object>	774
cplic upgrade	777
cppkg	
cppkg add	
ppkg delete	
cppkg get	
cppkg getroot	
cppkg print	
cppkg setroot	
cpprod_util	
cprid	
cprinstall	
cprinstall boot	
cprinstall cprestart	
cprinstall cpstart	
cprinstall cpstop	
cprinstall delete	
cprinstall get	
cprinstall install	
cprinstall revert	
cprinstall show	
cprinstall snapshot	
cprinstall transfer	
cprinstall uninstall	
cprinstall verify	
cpstart	
cpstat	
cpstop	
cpview	

Overview of CPView	
CPView User Interface	
Using CPView	
cpwd_admin	
cpwd_admin config	
cpwd_admin del	
cpwd_admin detach	
cpwd_admin exist	
cpwd_admin flist	
cpwd_admin getpid	
cpwd_admin kill	
cpwd_admin list	
cpwd_admin monitor_list	
cpwd_admin start	
cpwd_admin start_monitor	
cpwd_admin stop	
cpwd_admin stop_monitor	
dbedit	
fw	
fw fetchlogs	
fw hastat	
fw kill	
fw log	
fw logswitch	
fw Islogs	
fw mergefiles	
fw repairlog	
fw sam	
fw sam_policy	
fw sam_policy add	


fw sam_policy batch	
fw sam_policy del	
fw sam_policy get	
fwm	
fwm dbload	
fwm exportcert	
fwm fetchfile	
fwm fingerprint	
fwm getpcap	
fwm ikecrypt	
fwm load	
fwm logexport	
fwm mds	
fwm printcert	
fwm sic_reset	
fwm snmp_trap	
fwm unload	
fwm ver	
fwm verify	
inet_alert	
Idapcmd	
Idapcompare	
Idapmemberconvert	
Idapmodify	
Idapsearch	
mgmt_cli	
migrate	
migrate_server	
queryDB_util	
rs_db_tool	

sam_alert	
stattest	
threshold_config	
Glossary	

Introduction to Quantum Security Management

Check Point offers effective Security Management solutions to help you keep up with constantly growing needs and challenges of your organizational network. This Administration Guide focuses on the basic Security Management Server deployment.

If you are interested in deployments for organizations with multiple sites, refer to the <u>*R82 Multi-Domain Security Management Administration Guide.*</sub></u>



These are the basic components of Check Point security architecture.

Item	Description
1	SmartConsole - Check Point Graphical User Interface for connection to and management of Security Management Servers.
2	Security Management Server - Manages Security Gateways with defined security policies and monitors security events on the network.
3	Security Gateway - Placed at the perimeter of the network topology, to protect your environment through enforcement of the security policies.
4	Your environment to protect.

Workflow for Configuring Security Management

1. Connect with SmartConsole to the Security Management Server.

See "Connecting to the Security Management Server with SmartConsole" on page 33.

2. Configure the Security Management Server and Security Gateways in your environment.

See "Configuring the Security Management Server and Security Gateways" on page 54.

- Define the administrators of your environment.
 See "Managing Administrator Accounts" on page 74.
- Assign permissions to the administrators of your environment.
 See "Assigning Permission Profiles to Administrators" on page 115
- Define users and user groups that your security environment protects.
 See "Managing User Accounts" on page 135.
- Configure the physical and virtual network components in your environment.
 See "Managing Objects" on page 279
- Configure access rules that govern the protection of your organization's resources.
 See "Creating an Access Control Policy" on page 327.
- 8. Install the Security Policy.

See "Installing the Access Control Policy" on page 396. See "Installing the Threat Prevention Policy" on page 514.

SmartConsole Packages

SmartConsole is the main GUI client you use to connect to the Check Point Management Server to configure the required objects and policies in a Check Point environment.

Check Point provides these SmartConsole Packages:

SmartConsole Package	Where to Get It	Description	
Desktop SmartConsole	<u>sk181127</u> .	A standlone SmartConsole application you install or a Windows OS-based computer. For information about the updatable SmartConsole, see <u>sk171315</u> .	
Web SmartConsole	This package is built-in to the Management Server. This package is self-updatable, if the Management Server is connected to the Internet. Get the latest offline package from <u>sk170314</u> .	 Web SmartConsole provides the SmartConsole GUI functionality in a web browser. Best Practice - We recommend to use the Google Chrome web browser to connect to the Web SmartConsole. To connect to the Web SmartConsole: In a web browser, connect to: https://<ip address="" management="" of="" server="" the="">/smartconsole</ip> Example: https://192.168.3.57/smartconsole Log in with the credentials of the Management Server administrator. 	
Portable SmartConsole	<u>sk116158</u> .	Portable SmartConsole is a version of the SmartConsole client which is deployed without the installer of SmartConsole. This package encapsulates all content into the directory where it is deployed, so that it can be carried around in a portable device. Another advantage of this version is that it allows side by side versions of the SmartConsole of the same release on the same computer.	

Connecting to the Security Management Server with SmartConsole

To log in to a Security Management Server / Domain Management Server with SmartConsole, you must have an administrator account configured on the Security Management Server / Domain Management Server.

When installing the Security Management Server / Multi-Domain Security Management Server, you create one administrator in the First Time Configuration Wizard. After that, you can create additional administrators accounts in SmartConsole.

To log in to the Security Management Server / Domain Management Server with SmartConsole

1. Launch the SmartConsole application.

See "SmartConsole Packages" on page 32.

2. Enter your administrator authentication credentials.

These can be a *username*, or a *certificate file*, or a *CAPI certificate*.

• Logging in with a username:

Enter the Username and Password.

- Logging in with a certificate file:
 - a. From the drop-down list, select Certificate File.
 - b. Browse to the file.

This is the certificate file you created in the administrator object.

See "Managing Administrator Accounts" on page 74.

c. Enter the password of the certificate file.

• Logging in with a certificate in the CAPI repository:

Prerequisite - You must create a certificate file in the administrator object in SmartConsole, save it, and import it into the Windows Certificate Store on the SmartConsole client computer. See "*Managing Administrator Accounts*" on page 74.

- a. From the drop-down list, select CAPI Certificate.
- b. From the drop-down list, select the administrator.
- Logging in with Identity Provider:

From the drop-down list, select Identity Provider

- Note No need to enter credentials. The third party Identity Provider you are connected to already recognizes and authenticates you. For instructions on how to configure the Identity Provider, see "Creating an Administrator Account with SAML Authentication Login" on page 101.
- 3. Enter the name or the IP address of the Security Management Server / Domain Management Server.
- 4. To connect in read-only mode, select the **Read Only** checkbox.
- 5. Click Login.

The SmartConsole authenticates the Security Management Server / Domain Management Server. The first time you connect, SmartConsole shows the fingerprint.

6. Confirm the fingerprint.

The fingerprint and the IP address of the Security Management Server / Domain Management Server are saved to the user settings in Windows.

Understanding SmartConsole

Check Point SmartConsole makes it easy to manage security for complex networks. Before you configure your cyber security environment and policies, become familiar with Check Point's SmartConsole.

You can get the SmartConsole package in the Home Page SK article - sk181127.

You must install the SmartConsole package in a folder, whose full path includes only English characters.

SmartConsole Window

	1			2 🛱 Discard	Session 🔹 🖹 Ch	anges 🏐 Publish				🗢 Al Copilot	SmartConsole	_ 6
Access Control			+=	+≡ × Ξ ÷ ≡ - Ø Insta	all Policy 🚺 🗂 Act	ons •	ction,		Q, V ^ Y			4
/	No.	Name	Source * Any	Destination	VPN * Any	Services & Applications 部 dns	Action	Track None	Install On * Policy Targets			5
HE NAT	2		* Any	↔ All_Internet	* Any	器 AOL_Messenger	Drop	- None	* Policy Targets			0
RITY Intreat Prevention	3		* Any	間 DMZZone	* Any	😵 http	Accept	- None	* Policy Targets			0
Custom Policy Marca Autonomous Policy	4	cleanup rule	* Any	* Any	* Any	* Any	Orop	- None	* Policy Targets			-6
112 Constant												
• HTTPS Inspection												
Inbound Policy											· ·	
U Outbound Policy												
Shared Policies												
Access Trads	Summary	y Details Logs	History									Ŧ
Access Tools	Summary	/ Details Logs	History									-
Access Tools & VPN Communities @ VPN Network Probes	Summary		History	Created by: 23		Addi	tional Rule Info:					
🕸 VPN Communities	()	Accept	History	Created by: aa	11:27 AM	_						
 VPN Communities VPN Network Probes Updates 	nule	Accept	History	_	11:27 AM	Ticke	t Number:					
 VPN Communities VPN Network Probes Updates 	()	Accept	History	Date created: 2/4/2025	11:27 AM 0(0%, Zero)	Ticke						
 ✤ VPN Communities ♥ VPN Network Probes ♥ Updates 	nule	Accept	History	Date created: 2/4/2025		Ticke	t Number:					
 VPN Communities VPN Network Probes Updates 	nule	Accept	History	Date created: 2/4/2025		Ticke	t Number:					

ltem	Description	Item	Description
1	Global Toolbar	5	Validations pane
2	Session Management Toolbar	6	Al Copilot. For complete description and minimum requirements, see <u>sk182844</u> .
3	Navigation Toolbar	7	Command line interface button
4	Objects Bar (F11)		

Note - In SmartConsole > Gateways & Servers view, after you click the Filter (funnel) button on the top toolbar, you can select only one facet in each category ("Version", "Hardware", and so on).

SmartConsole Toolbars

Global Toolbar (top of SmartConsole)

lcon	Description
	 The main SmartConsole Menu. When SmartConsole is connected to a Security Management Server, this includes: Manage policies and layers Open Object Explorer New object (opens a menu to create a new object) Publish session Discard session Dession details Install policy Verify Access Control Policy Install Database Uninstall Threat Prevention policy Manage Licenses and Packages Endpoint (opens a menu to SmartEndpoint and Harmony Endpoint Web UI) Global Properties View (opens a menu to select a View to open)
ŵ	Create new objects or open the Object Explorer
•	Install policy on managed Security Gateways

Session Management Toolbar (top of SmartConsole)

lcon	Description
₪	Discard changes made during the session
Session 🝷	Enter session details to view the number of changes made in the session.
٩	Publish the SmartConsole session, to make the changes visible to other administrators, and ready to install on Security Gateways. Note - When the policy is installed, published changes are installed on the Security Gateways and enforced.

Icon	Keyboard Shortcut	Description
	Ctrl+1	Gateways & Servers configuration view:
		 Manage Security Gateways Activate Software Blades Add, edit, or delete Security Gateways and clusters (including virtual clusters) Run scripts Backup and restore Security Gateways Open a command line interface on the Security Gateway View Security Gateway status
556	Ctrl+2	Security Policies Access Control view:
		 Manage Access Control: Content Awareness, VPN, Application & URL Filtering, and Mobile Access Edit multiple policies at the same time Add, edit, or delete NAT rules Use the Access Tools
		Security Policies Threat Prevention view:
		 Manage Threat Prevention: IPS, Anti-Bot, Anti-Virus, Threat Emulation Edit the unified threat Rule Base Configure threat profiles Add, edit, or delete exceptions and exception groups Use the Custom Policy Tools
		Shared Policies Views:
		Manage Mobile Access, DLP, and inspection Settings
^	Ctrl+3	Logs & Events view: View high level graphs and plots Search through logs Schedule customized reports Monitor Security Gateways View compliance information

Navigation Toolbar (left side of SmartConsole)

Icon	Keyboard Shortcut	Description
Ø	Ctrl+4	 Infinity Services view: Connect from you on-premises Management Server to the Infinity Portal Run services that are managed in the Infinity Portal on your Management Server objects. See a unified log view of all your Check Point products, both in cloud and on-premises. Use new administrator capabilities on the on-premises Management Server
	Ctrl+5	 Manage & Settings view - review and configure the Security Management Server settings: Administrators Permissions profiles Trusted clients Administrator sessions, and session settings Blades Revisions Preferences Sync with User Center

Command Line Interface Button (left bottom corner of SmartConsole)

lcon	Keyboard Shortcut	Description
	F9	Open a command line interface for management scripting and API

For more SmartConsole shortcuts, see "Keyboard Shortcuts for SmartConsole" on page 48.

Objects Bar (right side of SmartConsole)

ltem	Keyboard Shortcut	Description
Objects	F11	Manage security and network objects

Al Copilot Pane (right side of SmartConsole

Item	Description
AI Copilot	The Infinity AI Copilot is an intelligent assistant integrated into SmartConsole, designed to streamline tasks and deliver actionable insights for efficient Security Management. For complete description and minimum requirements, see <u>sk182844</u> .

Validations Pane (right side of SmartConsole)

Item	Description
Validations	View validation errors

System Information Area (bottom of SmartConsole)

Item	Description
Task List	Management tasks in progress. Expand to view recent tasks
Server Details	The IP address of the server to which SmartConsole is connected. If Management High Availability is configured, click to view the details.
Session Status	The number of changes made in the session and the session status.
Connected administrators	Connected administrators: Yourself and others.

Search Engine

In each view you can search the Security Management Server database for information relevant to the view. For example:

- Gateway, by name or IP address
- Access Control rule
- NAT rule
- Threat Prevention profile
- Specific threat or a threat category
- Object tags

You can search for an object in the Security Management Server database in two ways:

- Enter the prefix of the object's name. For example, to find USGlobalHost, you can enter USG in the search box.
- Enter any sequence of characters in the object's name and add an asterisk (*) before such sequence.

For example, to find *USGlobalHost*, you can enter **oba*, **host*, **SG* and so on in the search box.

IP Search

You can run an advanced search for an IP address, network, or port. It returns direct and indirect matches for your search criteria.

- IP address: xxx.xxx.xxx.xxx
- Network: xxx.xxx.0.0/16 or xxx.xxx
- Port: svc:<xxx>

These are the different IP search modes:

- General (Default). Returns direct matched results and indirect results in IP ranges, networks, groups, groups with exclusion, and rules that contain these objects.
- Packet Matches rules as if a packet with your IP address arrives at the Security Gateway.

General IP Search

This is the default search mode. Use it to search in Rule Bases and in objects. If you enter a string that is not a valid IP or network, the search engine treats it as text.

When you enter a valid IP address or network, an advanced search is done and on these objects and rules:

- Objects that have the IP address as a text value for example, in a comment
- Objects that have an IP address property (direct results)
- Groups, networks, and address ranges that contain objects with the text value or address value
- Rules that contain those objects

Packet Search

A Packet Search matches rules as if a packet with your IP address arrives at the Security Gateway.

It matches rules that have:

- The IP address in a column of the rule
- "Any"
- A Group-with-exclusion or negated field with the IP address in its declaration

To run a Packet Search:

1. Click the search box.

The search window opens.

- 2. Click Packet or enter: "mode:Packet"
- 3. To search a specific rule column, enter: ColumnName:Criteria

Rule Base Results

When you enter search criteria and view the matched results, the value that matched the criteria in a rule is highlighted.

If there is	This is highlighted
A direct match on an object name or on textual columns	Only the specific matched characters
A direct match on object properties	The entire object name
A negated column	The negated label
A match on "Any"	"Any"

Known Limitation:

Packet search does not support IPv6.

Access, Custom and HTTPS Inspection Tools

The Access Tools section in the Security Policies Access Control view and the Custom Policy Tools section in the Security Policies Threat Prevention view give you more management and data collection tools.

"Access Tools" in the Security Policies "Access Control" view

Tool	Description
VPN Communities	Create, edit, or delete VPN Communities.
VPN Network Probes	Monitor the status and availability of Site to Site VPN tunnels.
Updates	Update the Application & URL Filtering database, schedule updates, and configure updates.
UserCheck	Configure UserCheck Interaction objects for Access Control policy actions.
Client Certificates	Create and distribute client certificates that allow users to authenticate to the Security Gateway from handheld devices.
IoT Protect	Configure network security for IoT devices.
Application Wiki	Browse to the Check Point AppWiki. Search and filter the Web 2.0 Applications Database, to use Check Point security research in your policy rules for actions on applications, apps, and widgets.
Installation History	See the Policy installation history for each Security Gateway, and who made the changes. See the revisions that were made during each installation, and who made them. Install a specific version of the Policy.

"Custom Policy Tools" in the Security Policies "Threat Prevention" view

ΤοοΙ	Description
Profiles	Create, edit, or delete profiles.
IPS Protections	Edit IPS protections per profile.

ΤοοΙ	Description	
Protections	See statistics on different protections. Configure Whitelist Files list.	
Allow List Files		
Indicators	Configure indicators of malicious activity and how to handle it.	
Updates	Configure updates to the Malware database, Threat Emulation engine and images, and the IPS database.	
UserCheck	Configure UserCheck Interaction objects for Threat Prevention policy actions.	
Threat Wiki	Browse to the Check Point ThreatWiki. Search and filter Check Point's Malware Database, to use Check Point security research to block malware before it enters your environment, and to best respond if it does get in.	
Installation History	See the Policy installation history for each Security Gateway, and who made the changes. See the revisions that were made during each installation, and who made them. Install a specific version of the Policy.	

HTTPS Inspection Tools in the Security Policies HTTPS Inspection View

ΤοοΙ	Description	
Deployment	See the statuses and recommendations for Security Gateways with HTTPS Inspection enabled in Learning Mode. See the inspection status of each Security Gateway. Manage inbound and outbound certificates for the Security Gateways.	
Advanced Settings	sted Manage trusted CAs and custom trusted certificates.	
Trusted Certificates		

Shared Policies

The **Shared Policies** section in the **Security Policies** shows the policies that are not in a Policy package. They are shared between all Policy packages.

Shared policies are installed with the Access Control Policy.

Software Blade	Description	
Mobile Access	Launch Mobile Access policy in a SmartConsole. Configure how your remote users access internal resources, such as their email accounts, when they are mobile.	
DLP	Launch Data Loss Prevention policy in a SmartConsole. Configure advanced tools to automatically identify data that must not go outside the network, to block the leak, and to educate users.	
Inspection Settings	You can configure Inspection Settings for the Security Gateway (see "Preferences and Management Settings" on page 589): Deep packet inspection settings Protocol parsing inspection settings VoIP packet inspection settings	

API Command Line Interface

You can also configure objects and rules through the API command line interface, which you can access from SmartConsole.

	Click to open the command line interface.	
0	In the command line interface, this button opens the Check Point Management API Reference. The Check Point Management API Reference is a comprehensive guide that provides detailed information on how to use the Check Point Management APIs.	
In addition to the command line interface, you can create and run API scripts to manage		

In addition to the command line interface, you can create and run API scripts to manage configuration and operations on the Security Management Server (see "Managing Security through API" on page 56).

Keyboard Shortcuts for SmartConsole

These are additional keyboard shortcuts that you can use to navigate between the different SmartConsole fields:

Keyboard shortcut	Description
Ctrl+S	Publish the SmartConsole session.
Ctrl+Alt+S	Discard the SmartConsole session.
Shift+Alt+Enter	Install policy.
F10	Show/hide task details.
F11	Show/hide Object Explorer.
Ctrl+O	Manage policies and layers
Ctrl+E	Open Object Explorer
Ctrl+F3	Switch to high-contrast theme
Alt+Space	System menu
F1	Open the relevant online help
Alt+F4	Close SmartConsole

Shortcuts for the specific views that support them:

Keyboard shortcut	Description
Ctrl+T	Open new tab
Ctrl+W or Ctrl+F4	Close current tab
Ctrl+Tab	Move to the next tab
Ctrl+Shift+Tab	Move to the previous tab
Delete	Delete the currently selected item
Ctrl+A	Select all elements
Esc	Cancel operation to close window
Enter or mouse double-click	Edit item

In the Security Policies view, these are the shortcuts for pages that contain policies:

Keyboard shortcut	Description
Ctrl+G	Go to rule (in the Access Control Rule Base)
Ctrl+X	Cut rule
Ctrl+C	Copy rule
Ctrl+V	Paste rule below the selected rule
Delete	Remove a used item from a rule cell
Ctrl+F	Open Rule Base search
F3	Navigate to the next Rule Base search result
Ctrl+arrow up	Go to the first rule in the Rule Base
Ctrl+arrow down	Go to the last rule in the Rule Base
Space or +	Open drop-down menu for the current cell in the Rule Base
Shift+arrow up/down	Move between objects in the Rule Base

Shortcuts for the Logs & Events view:

Keyboard shortcut	Description
Ctrl+G	Switch to grid view (in the Logs and Audit Logs views)
Ctrl+L	Switch to table view (in the Logs and Audit Logs views)
Ctrl+R	Resolve objects
F5	Refresh query
F6	Enable auto-refresh
Ctrl+D	Add to favorites
Ctrl+S	Organize favorites

Using Infinity AI Copilot in SmartConsole

The Infinity AI Copilot is an intelligent assistant integrated into SmartConsole, designed to streamline tasks and deliver actionable insights for efficient security management.

The Infinity AI Copilot was trained to understand and read Check Point Security Policies, how ordered layers and Inline Layers work, how Security Gateways match traffic to rules, how to query logs, and so on. The Infinity AI Copilot was also trained based on the content of Administration Guides and Knowledge base SK articles. As a result, the Infinity AI Copilot can provide precise answers about your Check Point environment.

After you connect your Security Management Server to the Infinity Portal, the Infinity AI Copilot can read the configured objects, Security Policies, and logs (if you enable "Log Sharing") on your Security Management Server and answer questions about your environment.

Prerequisites

Requirements for Desktop SmartConsole	Requirements for Web SmartConsole
To use the Infinity AI Copilot in Desktop SmartConsole, you must install these two packages:	To use the Infinity AI Copilot in Web SmartConsole, you must install this package:
 Desktop SmartConsole Build 1027 or higher. <u>Web SmartConsole Take 125 or higher</u>. 	Web SmartConsole Take 125 or higher

Note - We recommend to always install the latest Take of Web SmartConsole.

To Enable the Infinity AI Copilot

1. Connect your Security Management Server to the Infinity Portal.

See "To connect your Security Management Server and Security Gateway objects from SmartConsole to the Infinity Portal" on page 538.

- 2. Enable the Infinity AI Copilot:
 - a. In the Infinity Services page, in the Infinity AI Copilot widget, change the toggle to **ON**.

b. Follow the on-screen instructions.

The Infinity AI Copilot tab appears in SmartConsole on the right panel (and in the top right).

3. Optional: To ask questions about logs, it is necessary to share logs.

See "To share your on-premises Management Server log information with the Infinity Portal" on page 539.

Planning Security Management

Sizing the Security Management Server

This section provides information to help you size a Security Management Server and validate the sizing of an existing environment.

The data required for accurate sizing of the Security Management Server:

- Number of Security Gateways managed by the Security Management Server.
- Sustained logs per second.
- Large-scale deployments:
 - Number of Domains
 - Size of Rule Base
 - Number of concurrent administrators
 - Security Management limitations

You can find guidelines on how to collect the data and identify the appropriate size for your Management Server in $\frac{sk181782}{sk181782}$.

For Multi-Domain / Large-scale deployments, refer to sk178325.

We recommend:

- To use dedicated Management Servers.
- To use dedicated Log Servers.
- Configure Management High Availability. You can use standby Management Servers as Log Servers for your gateways
- Use dedicated SmartEvent Servers.
- You can define the SmartEvent Server as the Primary Log Server for your gateways (does not apply to Multi-Domain Security Management configurations).

After installing the Security Management Server and Security Gateway, you can continue with cyber security configuration for your environment.

Define your Organization's Topology

Network topology consists of network components, both physical and logical, such as physical and virtual Security Gateways, hosts, hand-held devices, CA servers, third-party servers, services, resources, networks, address ranges, and groups. Each of these components corresponds to an object in your Check Point security management configuration. Configure those objects in SmartConsole. See "Network Object Types" on page 284.

Define users and user groups that your security environment protects

You can add users and groups to the database manually, through LDAP and User Directory, or with the help of Active Directory.

To add users and user groups, see "Managing User Accounts" on page 135

To use LDAP and User Directory, see "*Configuring Users on an External LDAP Server*" on page 217.

To use Active Directory, see "Microsoft Active Directory" on page 217.

Define Access Rules for Protection of your Organization's Resources

Configure access rules and group them in policies that are enforced on the Security Gateways. You can define access policies based on traffic, applications, Web sites, and data (see *"Managing Policies" on page 316*). Set up preventative actions against known threats with Check Point Anti-Virus and Anti-Malware. Educate users about the validity and security of the operations they attempt with the help of UserCheck. Track network traffic and events through logging and monitoring.

Enforce Access Policies

Configure the Security Gateways. Make sure to activate the appropriate Software Blades. Then, install your policies on the Security Gateways.

Configuring the Security Management Server and Security Gateways

To start setting up your security environment, configure the Security Management Server and the Security Gateways. The Security Gateways enforce the security policy that you define on the Security Management Server.

To configure the Security Management Server in SmartConsole

1. In the Gateways & Servers view, find the Security Management Server object.

In the **Search** box at the top of the view, you can search for it by object name or object IP address.

When you select the Security Management Server object, the **Summary** tab in the lower pane shows the Software Blades that are enabled on it.

2. Double-click the object to open its properties.

On the **Management** tab, enable the Software Blades, as necessary:

- Network Policy Management Manage a comprehensive security policy, unified for all security functionalities. This is automatically enabled.
- Endpoint Policy Management Manage Endpoint Security Clients on end-user computers and hand-held devices.
 - Important It is not supported to disable this Software Blade after you enable it.
- Logging & Status Monitor security events and status of Security Gateways, VPNs, users, and more, with advanced visuals and data management features.
- Identity Logging Add user identities, and data of their computers and devices, from Active Directory domains, to log entries.
- User Directory Populate your security scope with user accounts from the LDAP servers in your environment.
- Provisioning Manage Security Gateway configuration and policies for multiple appliances and open servers in one central SmartConsole.
- Compliance Optimize your security settings and comply with regulatory requirements

- SmartEvent Server Manage security events in real-time.
- SmartEvent Correlation Unit Correlate security events in real-time.

To configure the Security Gateways in SmartConsole

- 1. From the navigation toolbar, select Gateways & Servers.
- 2. Click New, and select Gateway.
- 3. In the **Check Point Security Gateway Creation** window that opens, select a configuration mode:
 - Wizard Mode Run the configuration wizard.
 - Classic Mode Configure the Security Gateway settings in the classic mode (see "Managing Gateways" on page 221).

Managing Security through API

This section describes the API Server on a Management Server and the applicable API Tools.

API

You can configure and control the Management Server through API Requests you send to the API Server that runs on the Management Server.

The API Server runs scripts that automate daily tasks and integrate the Check Point solutions with 3rd-party systems, such as virtualization servers, ticketing systems, and change management systems.

To learn more about the management APIs, to see code samples, and to take advantage of user forums, see:

- The API Documentation:
 - Online <u>Check Point Management API Reference</u>
 - Local-https://<Server IP Address>/api_docs

By default, access to the local API Documentation is disabled. Follow the instructions in sk174606.

Note - On a Standalone server (a server which runs both a Security Management Server and a Security Gateway), the API Documentation web portal (https://<Server IP Address>/api_docs) stops working when you open SmartView Web Application (https://<Server IP Address>/smartview).

The Developers Network section of <u>Check Point CheckMates Community</u>.

API Tools

You can use these tools to work with the API Server on the Management Server:

Standalone management tool, included with Gaia operating system:

mgmt_cli

Standalone management tool, included with SmartConsole:

mgmt_cli.exe

You can copy this tool from the SmartConsole installation folder to other computers that run Windows operating system.

 Web Services APIs that allow communication and data exchange between the clients and the Management Server over the HTTP protocol.

These APIs also let other Check Point processes communicate with the Management Server over the HTTPS protocol.

https://<IP Address of Management Server>/web_api/<command>

Configuring the API Server

To configure the API Server:

- 1. Connect with SmartConsole to the Security Management Server or applicable Domain Management Server.
- 2. From the left navigation panel, click Manage & Settings.
- 3. In the upper left section, click **Blades**.
- 4. In the Management API section, click Advanced Settings.

The Management API Settings window opens.

5. Configure the **Startup Settings** and the **Access Settings**.

Configuring Startup Settings

Select **Automatic start** to automatically start the API server when you start or reboot the Management Server.

Notes:

- If the Management Server has more than 4GB of RAM installed, the Automatic start option is activated by default during the Management Server installation.
- If the Management Server has less than 4GB of RAM, the Automatic start option is deactivated.

Configuring Access Settings

Select one of these options to configure which clients can connect to the API Server:

Management server only

Only the Management Server itself can connect to the API Server.

This option only lets you use the $mgmt_cli$ utility on the Management Server command line to send API requests.

You cannot use SmartConsole or Web services to send API requests.

All IP addresses that can be used for GUI clients

You can send API requests from all IP addresses that are defined in SmartConsole > **Permissions & Administrators** > **Trusted Clients**.

This includes requests from SmartConsole, Web services, and the mgmt_cli utility on the Management Server.

All IP addresses

You can send API requests from all IP addresses.

This includes requests from SmartConsole, Web services, and the mgmt_cli utility on the Management Server.

- 6. Click OK.
- 7. In the upper left section, click **Permissions & Administrators**.
- 8. In the object of each applicable Administrator, make sure the assigned Permission Profile allows access to Management API.

Instructions

- a. Edit the Administrator object.
- b. In the left panel, click General.

c. In the **Permissions** section, on the right side of the selected Permission Profile, click the eye icon.


The Permission Profile object opens in the read-only view.

- d. In the left panel, click Management.
- e. The permission Management API Login has to be selected.

If it is not selected, then close this window and edit this Permission Profile object.

For more information, see "Assigning Permission Profiles to Administrators" on page 115.

- f. Click Close.
- 9. Publish the SmartConsole session.
- 10. Restart the API Server on the Management Server with this command:



 On a Multi-Domain Server, you must run this command in the context of the applicable Domain Management Server:

```
mdsenv <IP Address or Name of Domain Management
Server>
```

The output of this command must show:

```
API started successfully
```

11. Examine the status of the API server on the Management Server with this command:

api status

Notes:

• The output of this command must show:

```
Overall API Status: Started
API readiness test SUCCESSFUL. The server is up and ready
to receive connections
```

The output this command may show the state of the "API" process as "Stopped" when the API access is set to "All IP addresses that can be used for GUI clients", and more than 200 Trusted Clients are configured:

```
Processes:

Name State PID More Information

API Stopped ...
```

Self-Managed Security Gateways

Introduction

R82 introduced a new Dynamic Layer in the Access Control policy to assist customers with highly automated network environments.

This Policy Layer serves as a container for rules created directly on the Security Gateway using the Gaia API call "set-dynamic-content", catering to environments where provisioning, configuration, and other IT processes are regularly managed through the distribution of JSON files.

Workflow:

- 1. On the Management Server, in the Access Control, you create a new Policy Layer and configure it as a Dynamic Layer.
- 2. On the Security Gateway, you configure the required Access Control rules in this Dynamic Layer with the Gaia API call "set-dynamic-content" (in the JSON format).

The Dynamic Layer works only as a container for rules that you configure on the Security Gateway. After you run the Gaia API command on the Security Gateway, it ignores all rules in this Dynamic Layer that were configured in SmartConsole. If permanent rules are needed (for example, to allow access from a remote API client), you must configure them in the main policy on the Management Server and not in Dynamic Layers.

For additional information, refer to sk182252.

Requirements

- 1. Management Server R82 and higher:
 - Security Management Server
 - Multi-Domain Security Management Server
- 2. Security Gateway R82 and higher:
 - Single Security Gateway
 - ElasticXL Cluster
 - ClusterXL
 - Security Group in Maestro or Scalable Chassis
- 3. On the Security Gateway, the user that runs the Gaia API must have this configuration in Gaia OS:
 - a. **Role**: adminRole.
 - b. Access Mechanism: Gaia API.
 - c. Shell:/etc/cli.sh or /bin/bash

See the <u>Gaia Administration Guide</u> for your version > User Management chapter> Users and Roles sections.

Limitations

• This feature was designed for the JSON format.

Use a 3rd-party REST API client that allows you to paste the required API body in the JSON format.

Do not use the Check Point CLI API client "mgmt_cli".

- It is not supported to edit or delete individual dynamic rules on the Security Gateway after you add them.
 - To change an individual dynamic rule, you must run the Gaia API call "setdynamic-content" with the updated API body that contains the complete Access Control rules and the updated parameters and values for that individual rule.
 - To delete an individual dynamic rule, you must run the Gaia API call "setdynamic-content" with the updated API body that contains the complete Access Control rules without that individual rule.



- To see the current rules and to copy the current complete JSON, run the Gaia API call "show-dynamic-layer" on the Security Gateway.
- If necessary, you can delete all rules in the Dynamic Layer on the Security Gateway. See "*Resetting a Dynamic Layer*" on page 69.
- VSNext Virtual Gateway is not supported.
- Traditional VSX Virtual System (on a VSX Gateway or VSX Cluster) is not supported.
- Traditional VSX Virtual Router (on a VSX Gateway or VSX Cluster) is not supported.

Notes

- Each Policy Package supports more than one Dynamic Layer as an Inline Layer or as an Ordered Layer. For example, different administrators can use different Policy Layers.
- The Security Gateway applies the Access Control rules in the order of the Policy Layers in the Policy Package.
- Rules that you configure in the Dynamic Layer apply until you run the Gaia API call "set-dynamic-content" for the first time on the Security Gateway.
- If you delete the Dynamic Layer from the Policy Package (or clear the checkbox Set as a Dynamic Layer in the Dynamic Layer) and install the Access Control policy, then the Security Gateway removes all dynamic rules and applies only the static rules configured in SmartConsole.
- SmartConsole does not show rules in the Dynamic Layer that you configure on the Security Gateway.
- To see the list of the supported objects in the Dynamic Layer, refer to the API call "setdynamic-content" > section "Request Body" > parameter "objects".

Configuration

- 1. Connect with SmartConsole to the Security Management Server / Domain Management Server.
- 2. Add a new Policy Layer and configure it as a Dynamic Layer.

Notes:

- You can configure a new Policy Layer directly in a specific policy, or as a shared Policy Layer for several policies.
- You can configure an Inline Layer (within a specific rule), or an Ordered Layer (a separate set of rules in a dedicated Policy Layer).

See "Ordered Layers and Inline Layers" on page 359.

You can add a new Policy Layer and configure it as a Dynamic Layer either in SmartConsole (described below) or with the Management API call "add-accesslayer dynamic-layer true" (see <u>Check Point Management API Reference</u> v1.8 and higher).

Procedure in SmartConsole:

To configure an Ordered Layer in a specific Access Control policy

- a. In the top left corner, click Menu > Manage policies and layers.
- b. In the left panel, click **Policies**.

- c. Right-click the applicable Policy Package and click Edit.
- d. In the Access Control section, click the + icon.
- e. In the top right corner, click New Layer.
- f. Enter the name for this Policy Layer.
- g. On the General page:

In the Blades section, select the supported blades:

- i. Mandatory: Firewall
- ii. Optional: Application & URL Filtering
- h. On the Advanced page:
 - i. In the Implicit Cleanup Action section, select the option Drop (default).

This Drop rules makes sure to drop all traffic that matches this Ordered Layer until you run the Gaia API call "set-dynamic-content" on the Security Gateway.

You can change it later in SmartConsole.

- ii. In the Dynamic Layer section, select Set as a Dynamic Layer.
- On the Permissions page, select the permission profiles that can edit the Dynamic Layer. This is essential when multiple Dynamic Layers are used, each configured by different users. Only the profiles shown here can edit the Layer. To add additional profiles that can edit the Layer, go to the bottom of the Permissions page.

To create a new permission profile, in SmartConsole, go to the Manage & Settings view > Permissions & Administrators > Permission Profiles. In the profile editor, go to Access Control > Policy, and make sure Edit layers by the selected profile in a layer editor is selected.

- j. Click **OK** to close the Layer Editor window.
- k. In the policy, to the right of the Access Control section, you now see the Layer called **Network** (default name) and the new Dynamic Layer.

Important - You can change the order of these Policy Layers.

I. Click OK to close the Policy window.

To configure an Inline Layer in a specific Access Control policy in a specific rule

- a. From the left navigation panel, click Security Policies.
- b. If you need to open a different Security Policy:
 - i. At the top, click the [+] tab.
 - ii. Click the required policy.
- c. In the Access Control section, click Policy.
- d. Locate the applicable rule.
- e. In the rule, click in the Action cell > click Inline Layer > click New Layer.
- f. Enter the name for this **Policy Layer**.
- g. On the General page, in the Blades section, select the supported blades:
 - Mandatory: Firewall
 - Optional: Application & URL Filtering
 - Optional: In the Sharing section, select Multiple policies and rules can use this layer.
- h. On the Advanced page:
 - i. In the Implicit Cleanup Action section, select the option Accept.

This makes sure to accept traffic that matches this Inline Layer until you run the Gaia API call "set-dynamic-content" on the Security Gateway.

You can change it later in SmartConsole.

- ii. In the Dynamic Layer section, select Set as a Dynamic Layer.
- On the Permissions page, select the permission profiles that can edit the Dynamic Layer. This is essential when multiple Dynamic Layers are used, each configured by different users. Only the profiles shown here can edit the Layer. To add additional profiles that can edit the Layer, go to the bottom of the Permissions page.

To create a new permission profile, in SmartConsole, go to the Manage & Settings view > Permissions & Administrators > Permission Profiles. In the profile editor, go to Access Control > Policy, and make sure Edit layers by the selected profile in a layer editor is selected.

- j. Click **OK** to close the **Layer Editor** window.
- k. In the rule, you now see the new Inline Layer.

To configure a shared Ordered Layer to use in several Access Control Policies

- a. In the top left corner, click **Menu > Manage policies and layers**.
- b. In the left panel, click Layers > Access Control.
- c. From the top tool bar, click New.
- d. Enter the name for this Policy Layer.
- e. On the General page, in the Blades section, select the supported blades:
 - Mandatory: Firewall
 - Optional: Application & URL Filtering
 - Optional: In the Sharing section, select Multiple policies and rules can use this layer.
- f. On the Advanced page:
 - i. In the Implicit Cleanup Action section, select the option Drop.

This **Drop** rules makes sure to drop all traffic that matches this Ordered Layer until you run the Gaia API call "set-dynamic-content" on the Security Gateway.

You can change it later in SmartConsole.

- ii. In the Dynamic Layer section, select Set as a Dynamic Layer.
- g. On the **Permissions** page, select the permission profiles that can edit the Dynamic Layer. This is essential when multiple Dynamic Layers are used, each configured by different users. Only the profiles shown here can edit the Layer. To add additional profiles that can edit the Layer, go to the bottom of the **Permissions** page.

To create a new permission profile, in SmartConsole, go to the **Manage &** Settings view > Permissions & Administrators > Permission Profiles. In the profile editor, go to Access Control > Policy, and make sure Edit layers by the selected profile in a layer editor is selected.

- h. Click OK to close the Layer Editor window.
- i. In the left panel, click **Policies**.
- j. Right-click the applicable Policy Package and click Edit.
- k. In the Access Control section, click the + icon.
- I. Click the new Dynamic Layer.

m. In the policy, to the right of the Access Control section, you now see the Layer called Network (default name) and the new Dynamic Layer.

8 Important - You can change the order of these Policy Layers.

- n. Click **OK** to close the **Policy** window.
- o. Click Close to close the Manage policies and layers window.
- 3. If you run Gaia API calls on the Security Gateway from a remote API client (and not locally on the Security Gateway), make sure your Access Control policy allows such connection to the Security Gateway.



Best Practice - To avoid losing connectivity loss for the API client, add the applicable rule only in a static Policy Layer (that is not configured as a Dynamic Layer).

- 4. Install this Access Control Policy on the Security Gateway / Cluster object.
- 5. Run the Gaia API call "set-dynamic-content" on the Security Gateway / each Cluster Member / Security Group to configure the required dynamic Access Control rules.



Marning - Pay close attention to the rules you configure on the Security Gateway.

There is **no** verification of possible conflicts between the rules configured on the Security Gateway and the rules configured in SmartConsole.

Notes:

Refer to the online Check Point Gaia API Reference (v1.8 and higher) > section System > sub-section Dynamic Content.

To see the local Gaia API Reference, go to this URL on a Management Server or Security Gateway (R82 or higher):

```
https://<IP Address of Gaia Management
Interface>/gaia docs/#web/set-dynamic-content
```

At the top of the Gaia API Reference, click the Web Services tab.

- Because you run Gaia API calls from a remote API client, make sure your Access Control policy allows such connection to the Security Gateway.
 - Best Practice To avoid losing connectivity loss for the API client, add the applicable rule only in a static Policy Layer (that is not configured as a Dynamic Layer).

Workflow for a remote REST API client (based on the Postman application)

- a. Install the Postman application.
- b. Get the Gaia REST API collection from sk143612.

- c. Import the Gaia REST API collection into the Postman application (first, you must create a Postman account). Refer to the Postman documentation about the import methods.
- d. Configure the required API variables:
 - i. In the left panel, in the Gaia REST API collection, click the top folder Gaia API.
 - ii. Add these variables:

Variable Name	Variable Value	Comment
username	Username of the applicable user in the Gaia OS on the Security Gateway.	The default user is admin. You can create other users (see the Requirements section).
password	Password of the applicable user in the Gaia OS on the Security Gateway.	You configure this password.
ip	IP Address of the Gaia Management Interface on the Security Gateway / each Cluster Member / Security Group.	This is the IP address on the Security Gateway / each Cluster Member / Security Group, to which the API client connects.
sid	Initially, empty.	Use this variable to contain the required SID after running the Gaia API call "login".

- e. Get the Login Session ID (SID):
 - i. In the left pane, open the folder Session Management.
 - ii. Click the API call "login".
 - iii. In the top right corner, click Send.
 - iv. In the bottom panel, copy the value of the parameter "sid".

- f. Configure the SID variable:
 - i. In the left panel, click the top folder Gaia API.
 - ii. In the sid variable, enter the copied value in the column Current Value.
 - iii. In the top right corner, click Save.
- g. Run the API call "set-dynamic-content" on the Security Gateway / each Cluster Member / Scalable Platform Security Group:
 - i. In the left panel, click the API "set-dynamic-content".
 - ii. At the top, click the Body tab.
 - iii. Configure the required parameters and values in the JSON format.
 - iv. In the top right corner, click **Send**.
 - v. In the bottom panel, copy the entire response with a Task ID.
 - vi. In the left panel, open the Misc folder, and click the API call "show task".
 - vii. At the top, click the **Body** tab and click the **raw** option.
 - viii. Paste the entire response with the Task ID.
 - ix. In the top right corner, click **Send**.
 - x. In the bottom panel, see the API response for the API call "set-dynamic-content".
- 6. **Optional**: Examine the configured dynamic Access Control rules.
 - To see the configured dynamic Access Control rules in a specific Dynamic Layer, run the Gaia API call "show-dynamic-layer" on the Security Gateway / each Cluster Member / Security Group.
 - To see the configured dynamic Access Control rules in all configured Dynamic Layers, run the Gaia API call "show-dynamic-layers" on the Security Gateway / each Cluster Member / Security Group.

Resetting a Dynamic Layer

To remove all dynamic rules, you must reset the Dynamic Layer that contains these rules on the Security Gateway.]

Procedure

Run the Gaia API call "set-dynamic-content" on the Security Gateway and use "operation": "reset".

Syntax part for a remote REST API client


```
f'access-layers-content": [f'
    {f'
        "name": "<Name_of_Dynamic_Layer>",f'
        "operation": "reset",f'
        "rulebase": []f'
    }f'
    [f'
```

Creating an Administrator Account with API Key Authentication

An API key is a token that a client provides when making API calls.

API key authentication provides an administrator the ability to use a token for authenticating to the API interface instead of the usual administrator name / password.

You can use SmartConsole to configure an API key for administrators to use the management API.



Prerequiste:

Make sure you configured the required Permission Profile. See "Assigning Permission Profiles to Administrators" on page 115.

To configure API authentication for an Administrator using SmartConsole

- 1. From the left navigation panel, click Manage & Settings...
- 2. Expand **Permissions & Administrators** > click **Administrators**.
- 3. From the top toolbar, click the * icon (New) > click New Administrator.

The New Administrator window opens and shows the General page.

- 4. In the top field, enter the applicable object name.
- 5. Optional: Enter the comment.
- 6. In the Authentication Method field, select API Key.
- 7. Click Generate API key:
 - a. Click Copy Key to Clipboard
 - b. Save the key for a later use (provide it to the relevant administrator).
 - c. Click OK.
- 8. In the **Permission Profile** field, select the applicable profile.
- 9. In the **Expiration** section, configure the required valid expiration date.
- 10. Optional: On the Additional Info page, configure:

- Phone Number
- Contact Details
- Email
- 11. Click **OK**.
- 12. Publish the SmartConsole session.

Example

This example demonstrates how to use the API Key for the API command "login" and the API command "add simple-gateway".

- 1. Connect to the command line on the Security Management Server.
- 2. Log in to the Expert mode.
- 3. Run the API command "login", use the previously generated API key, and save the output to a file:

Syntax:

mgmt_cli login api-key <api-key> > /<path_to>/<filename>

Example:

```
mgmt_cli login api-key mvYSiHVmlJM+J0tu2FqGag12 >
/var/tmp/token.txt
```

4. Run the API command "add simple-gateway".

Run the mgmt cli command with the "-s" flag and specify the token file.

Syntax:

```
mgmt_cli -s /<path_to>/<filename> add simple-gateway name
<gateway name> ip-address <ip address> one-time-password
<password> blade <true>
```

Example:

```
mgmt_cli -s /var/tmp/token.txt add simple-gateway name "gw1"
ip-address 192.168.3.181 one-time-password "aaaa" firewall
true vpn true
```

For more details, see the <u>Check Point Management API Reference</u>.

After you configure API authentication, you can, in addition, configure authentication with a certificate file. The administrator can then authenticate to the Security Management Server with either an API Key or a certificate file.

You create the certificate file in SmartConsole. The administrator can use the certificate to log in to SmartConsole in two ways:

- Log in to SmartConsole with the Certificate File option. The administrator must provide the password to use the certificate file.
- You can import the certificate file to the Windows Certificate Store on the Microsoft Windows SmartConsole computer. The administrator can use this stored certificate to log in to SmartConsole with the CAPI Certificate option. The administrator does not need to provide a password to log in.

The administrator can also give the certificate to other administrators to log in to SmartConsole with no administrator account of their own.

Managing Administrator Accounts

A Check Point administrator is an IT professional who manages and maintains a Check Point security environment with SmartConsole, CLI, or the API. Check Point administrators configure and manage Check Point's security products to protect their organizations' networks from cyber attacks, malware, and other security threats. A Check Point administrator typically installs, configures, and maintains the Check Point software, manages network traffic and security policies, monitors system performance, and troubleshoots security issues. Administrators also ensure that the Check Point security environment is up to date with the latest Hotfixes and updates to maintain optimal security.

You can store administrator accounts in the Check Point management database or on an external LDAP server. The Security Management Server authenticates administrators. Check Point supports different authentication methods for administrators.

As an administrator, you can delegate tasks, such as defining objects and users, to other administrators. Make sure to create administrator accounts with the privileges that are required to accomplish those tasks. If you are the only administrator, we recommend that you create a second administrator account with Read Only permissions, which is useful for troubleshooting, consultation, or auditing.

Creating an Administrator Account

To successfully manage security for a large network, we recommend that you first set up your administrative team, and delegate tasks.

We recommend that you create administrator accounts in SmartConsole, with the procedure below or with the First Time Configuration Wizard.

When you create an administrator account through SmartConsole, you can select one of these authentication methods:

Authentication Method	Description
Check Point Password	Check Point password is a static password that is configured in SmartConsole. The local database on the Security Management Server stores the password. No additional software is required. See "Creating an Administrator Account with Check Point Password Authentication" on page 81.

Authentication Method	Description
OS Password	OS password is kept on the operating system of the computer on which the Security Management Server is installed. You can also use passwords that are stored in Windows domain. No additional software is required. See "Creating an Administrator Account with OS Password Authentication " on page 84
RADIUS	Remote Authentication Dial-In User Service (RADIUS) is an external authentication method that provides security and scalability by separating the authentication function from the access server. With RADIUS, the Security Management Server forwards the authentication requests to the RADIUS server. The RADIUS server, which stores administrator account information, does the authentication. The RADIUS protocol uses UDP to communicate with the Security Gateway or the Security Management Server. See "Creating an Administrator Account with RADIUS Server Authentication" on page 87
TACACS	Terminal Access Controller Access Control System (TACACS) provides access control for routers, network access servers and other networked devices through one or more centralized servers. TACACS is an external authentication method that provides verification services. With TACACS, the Security Management Server forwards authentication requests by remote administrators to the TACACS server. The TACACS server, which stores administrator account information, authenticates administrators. The system supports physical card key devices or token cards and Kerberos secret key authentication. TACACS encrypts the administrator name, password, authentication services and accounting information of all authentication requests to secure communication. See "Creating an Administrator Account with TACACS Server Authentication" on page 92

Authentication Method	Description
SecurID	SecurID requires administrators to possess a token authenticator and to supply a PIN or password. Token authenticators generate one-time passwords that are synchronized to an RSA Authentication Manager (AM) and may come in the form of hardware or software. Hardware tokens are key-ring or credit card-sized devices. Software tokens reside on the PC or device from which the administrator wants to authenticate. All tokens generate a random, one-time use access code that changes approximately every minute. When an administrator attempts to authenticate to a protected resource, the AM must validate the one-time use code. The Security Management Server forwards SecurID authentication requests by remote administrators to the AM. The AM manages the database of the RSA users and their assigned hard or soft tokens. The Security Management Server act as an AM Agent and directs all access requests to the RSA AM for authentication. For additional information on agent configuration, refer to the RSA Authentication Manager documentation. There are no specific parameters required for the SecurID authentication method. Authentication requests can be sent over SDK- supported API or through REST API. See "Creating an Administrator Account with SecurID Authentication" on page 97.
API Key	You can use SmartConsole to configure an API key for administrators to use the management API. You can only use the API to execute API commands and not for SmartConsole authentication. For more information, see "Creating an Administrator Account with API Key Authentication" on page 112
SAML	An administrators can log in to SmartConsole through a central 3rd party Identity Provider with the SAML protocol. The Identity Provider holds the information about the administrators, including the ability to authenticate the administrators. Check Point supports these Identity Providers: Okta, Ping Identity, Azure. For more information, see "Creating an Administrator Account with SAML Authentication Login" on page 101.

Alternatively, or in addition to one of the above authentication methods, you can configure certificate file authentication. The administrator can then authenticate to SmartConsole with one of the Check Point authentication methods or with a certificate file.

You create the certificate file in SmartConsole. The administrator can use the certificate to log in to SmartConsole in two ways:

- Log in to SmartConsole with the Certificate File option. The administrator must provide the password to use the certificate file.
- You can import the certificate file to the Windows Certificate Store on the Microsoft Windows SmartConsole computer. The administrator can use this stored certificate to log in to SmartConsole with the CAPI Certificate option. The administrator does not need to provide a password to log in.

The administrator can also give the certificate to other administrators to log in to SmartConsole with no administrator account of their own.

To create an Administrator Account with the "Check Point Configuration Tool" tool (cpconfig)

We do not recommend to create an administrator with <code>cpconfig</code>, the Check Point Configuration Tool.

Use it only if there is no access to SmartConsole or the Gaia Portal.

If you use cpconfig to create an administrator:

You must restart Check Point Services to activate the administrator with these commands:

cpstop ; cpstart

- It does not show the other administrators.
- Check Point Password is automatically configured as the authentication method.

Editing an Administrator Account

- 1. From the left navigation panel, click Manage & Settings.
- 2. Click Permissions & Administrators.
- 3. Double-click an administrator account.

The Administrators properties window opens.

Deleting an Administrator Account

To make sure your environment is secure, the best practice is to delete administrator accounts when personnel leave or transfer.

To delete an administrator account

- 1. From the left navigation panel, click Manage & Settings.
- 2. Click Permissions & Administrators.
- 3. Select an administrator account and click Delete.
- 4. Click **Yes** in the confirmation window that opens.

Default Expiration for Administrators

If you want to use the same expiration settings for multiple accounts, you can set the default expiration for administrator accounts. You can also select to show notifications about the approaching expiration date when an administrator logs into SmartConsole or one of the SmartConsole clients. The remaining number of days, during which the account is alive, shows in the status bar.

To configure the default expiration settings

- 1. From the left navigation panel, click Manage & Settings.
- 2. Click Permissions & Administrators > Advanced.
- 3. Click Advanced.
- 4. In the **Default Expiration Date** section, select a setting:
 - Never expires
 - Expire at Select the expiration date from the calendar control
 - Expire after Enter the number of days, months, or years (from the day the account is made) before administrator accounts expire
- 5. In the **Expiration notifications** section, select **Show 'about to expire' indication in administrators view** and select the number of **days in advance** to show the message about the approaching expiration date.
- 6. Publish the SmartConsole session.
- Note If you configure an expiration date for an administrator, then the administrator is not logged out automatically. Only a new login is blocked.
 To improve security, configure the idle timeout. Go to SmartConsole > Manage & Settings > Permissions & Administrators > Advanced > Idle Timeout.

Configuring SmartConsole Session Timeout

Use the SmartConsole in a secure manner, and enforce secure usage for all administrators. Configuring a SmartConsole timeout is a basic requirement for secure usage. When an administrator does not use the SmartConsole, it logs out.

To set the SmartConsole session timeout

- 1. From the left navigation panel, click Manage & Settings.
- 2. Click Permissions & Administrators > Advanced.
- 3. In the Idle Timeout area, select Perform logout after being idle.
- 4. Enter a number of minutes.

When a SmartConsole is idle after this number of minutes, the SmartConsole automatically logs out the connected administrator, but all changes are preserved.

Revoking an Administrator Certificate

If an administrator that authenticates through a certificate cannot temporarily fulfill administrator duties, you can revoke the certificate for the account. The administrator account remains, but no one can authenticate to the Security Management Server with the certificate. However, if the account has an additional authentication method (a password, for example), the administrator can use this method to authenticate to the account.

To revoke an administrator certificate

- 1. From the left navigation panel, click Manage & Settings.
- 2. Click Permissions & Administrators.
- 3. Select an administrator account and click Edit.
- 4. In General > Authentication, click Revoke.

Restricting Administrator Login Attempts

You can configure these login restrictions for administrators who log in to the Security Management Server with a Check Point password:

- The number of login attempts before SmartConsole automatically locks an administrator account.
- The number of minutes before SmartConsole unlocks the administrator's account after it was locked.

To configure login restrictions

- 1. Go to the Manage & Settings view or to the Multi-Domain view.
- 2. Go to Permissions & Administrators > Advanced > Login Restrictions.
- Note These restrictions apply only to administrators who authenticate to the Security Management Server with a Check Point password.

Unlocking Administrator Accounts

An administrator with the **Manage Administrators** permission can unlock another administrator if the locked administrator authenticates to the Security Management Server with a Check Point password.

To unlock an administrator:

- 1. Go to the Manage & Settings view or to the Multi-Domain view.
- 2. Right-click the locked administrator and select Unlock Administrator.

Or:

Use the API command "unlock-administrator".

Note - The Unlock Administrator feature does not apply to administrators who use other authentication methods.

Multiple Administrators

If two administrators create an administrator account with the same name, after the first administrator publishes a session, the second administrator will not be able to publish their session. If the second administrator tries to change the name in the administrator account, they will not be able to do so. To resolve this issue, the second administrator must discard the session changes and reconnect.

Creating an Administrator Account with Check Point Password Authentication

Check Point password is a static password that is configured in SmartConsole. The local database on the Security Management Server stores the password. No additional software is required.

After you configure authentication with a Check Point password, you can, in addition, configure certificate file authentication. The administrator can then authenticate to SmartConsole with the Check Point password or the certificate file.

You create the certificate file in SmartConsole. The administrator can use the certificate to log in to SmartConsole in two ways:

- Log in to SmartConsole with the **Certificate File** option. The administrator must provide the password to use the certificate file.
- You can import the certificate file to the Windows Certificate Store on the Microsoft Windows SmartConsole computer. The administrator can use this stored certificate to log in to SmartConsole with the CAPI Certificate option. The administrator does not need to provide a password to log in.

The administrator can also give the certificate to other administrators to log in to SmartConsole with no administrator account of their own.

Prerequiste:

Make sure you configured the required Permission Profile. See "Assigning Permission Profiles to Administrators" on page 115.

To create a new administrator with Check Point password authentication

- 1. Create a new administrator and define Check Point password as the authentication method
 - a. From the left navigation panel, click Manage & Settings...
 - b. Expand **Permissions & Administrators** > click **Administrators**.
 - c. From the top toolbar, click the * icon (New) > click New Administrator.

The New Administrator window opens and shows the General page.

- d. In the top field, enter the applicable object name.
- e. **Optional:** Enter the comment.
- f. In Authentication Method field, select Check Point Password.

Creating an Administrator Account with Check Point Password Authentication

- g. Click Set New Password:
 - i. In the **Password** field, enter the password.
 - ii. In the Confirm field, enter the same password.
 - iii. Optional: Select User must change password on next login.
 - iv. Click OK.
- h. Optional: Create a certificate for this administrator:
 - i. In the Certificate Information field, click Create.
 - ii. In the **Password** field, enter the password.

A password is required to protect the sensitive data in the certificate file.

- iii. In the **Confirm** field, enter the same password.
- iv. Click OK.
- v. Wait for the Save As window to open.
- vi. In the File name field, make sure to include the username.
- vii. In the Save as type field, select Certificate Files (*p12).

The certificate file is in the PKCS #12 format, and has a .p12 extension.

- viii. Browse to a secure location on the SmartConsole computer.
- ix. Click Save.

Notes:

After you save the certificate file, give the administrator this file and password.

The administrator can then authenticate with the certificate when they log in with SmartConsole to the Security Management Server.

- You can revoke this certificate at any time. Select the certificate and click Revoke.
- i. In the **Permission Profile** field, select the applicable profile.
- j. In the **Expiration** section, configure the required valid expiration date.

Creating an Administrator Account with Check Point Password Authentication

- k. Optional: On the Additional Info page, configure:
 - Phone Number
 - Contact Details
 - Email
- I. Click OK.
- m. Publish the SmartConsole session.
- 2. Optional: Import the certificate file into the Windows Certificate Store
 - Note This procedure applies if you create a certificate authentication in the administrator object, and you log in to SmartConsole with the CAPI Certificate option.
 - a. Right-click the *.p12 file you saved when you created the required administrator, and click **Install PFX**.

The Certificate Import Wizard opens.

- b. In the Store Location section, select the applicable option:
 - Current User (this is the default)
 - Local Machine
- c. Click Next.
- d. Enter the same certificate password you used when you created the required administrator certificate.
- e. Clear Enable strong private key protection.
- f. Select Mark this key as exportable.
- g. Click Next.
- h. Select Place all certificates in the following store, click Browse > Personal > OK.
- i. Click Next.
- j. Click Finish.

Creating an Administrator Account with OS Password Authentication

OS password is kept on the operating system of the computer on which the Security Management Server is installed. You can also use passwords that are stored in Windows domain. No additional software is required.

After you configure authentication with an OS password, you can, in addition, configure authentication with a certificate file. The administrator can then authenticate to SmartConsole with either the OS password or the certificate file.

You create the certificate file in SmartConsole. The administrator can use the certificate to log in to SmartConsole in two ways:

- Log in to SmartConsole with the **Certificate File** option. The administrator must provide the password to use the certificate file.
- You can import the certificate file to the Windows Certificate Store on the Microsoft Windows SmartConsole computer. The administrator can use this stored certificate to log in to SmartConsole with the CAPI Certificate option. The administrator does not need to provide a password to log in.

The administrator can also give the certificate to other administrators to log in to SmartConsole with no administrator account of their own.

Prerequiste:

Make sure you configured the required Permission Profile. See "Assigning Permission Profiles to Administrators" on page 115.

To configure Check Point password authentication for an administrator

- 1. Create a new administrator and define OS password as the authentication method
 - a. From the left navigation panel, click Manage & Settings..
 - b. Expand **Permissions & Administrators** > click **Administrators**.
 - c. From the top toolbar, click the * icon (New) > click New Administrator.

The New Administrator window opens and shows the General page.

- d. In the top field, enter the applicable object name.
- e. **Optional:** Enter the comment.
- f. In Authentication Method field, select OS Password.

- g. Optional: Create a certificate for this administrator:
 - i. In the Certificate Information field, click Create.
 - ii. In the **Password** field, enter the password.

A password is required to protect the sensitive data in the certificate file.

- iii. In the **Confirm** field, enter the same password.
- iv. Click OK.
- v. Wait for the Save As window to open.
- vi. In the File name field, make sure to include the username.
- vii. In the Save as type field, select Certificate Files (*p12).

The certificate file is in the PKCS #12 format, and has a .p12 extension.

- viii. Browse to a secure location on the SmartConsole computer.
- ix. Click Save.

Notes:

 After you save the certificate file, give the administrator this file and password.

The administrator can then authenticate with the certificate when they log in with SmartConsole to the Security Management Server.

- You can revoke this certificate at any time. Select the certificate and click Revoke.
- h. In the **Permission Profile** field, select the applicable profile.
- i. In the **Expiration** section, configure the required valid expiration date.
- j. Optional: On the Additional Info page, configure:
 - Phone Number
 - Contact Details
 - Email
- k. Click OK.
- I. Publish the SmartConsole session.
- 2. Optional: Import the certificate file into the Windows Certificate Store
 - Note This procedure applies if you create a certificate authentication in the administrator object, and you log in to SmartConsole with the CAPI Certificate option.

a. Right-click the *.p12 file you saved when you created the required administrator, and click **Install PFX**.

The Certificate Import Wizard opens.

- b. In the Store Location section, select the applicable option:
 - Current User (this is the default)
 - Local Machine
- c. Click Next.
- d. Enter the same certificate password you used when you created the required administrator certificate.
- e. Clear Enable strong private key protection.
- f. Select Mark this key as exportable.
- g. Click Next.
- h. Select Place all certificates in the following store, click Browse > Personal > OK.
- i. Click Next.
- j. Click Finish.

Creating an Administrator Account with RADIUS Server Authentication

Remote Authentication Dial-In User Service (RADIUS) is an external authentication method that provides security and scalability by separating the authentication function from the access server. With RADIUS, the Security Management Server forwards the authentication requests to the RADIUS server. The RADIUS server, which stores administrator account information, does the authentication. The RADIUS protocol uses UDP to communicate with the Security Gateway or the Security Management Server.

You can perform RADIUS authentication for SmartConsole administrators through a RADIUS server or a RADIUS server group. You define RADIUS servers and RADIUS server group objects in SmartConsole. A RADIUS server group is a high availability group of identical RADIUS servers which includes any or all the RADIUS servers in the system. When you create the group, you define a priority for each server in the group. If the server with the highest priority fails, the one with the next highest priority in the group takes over, and so on. If you assign the same priority to all RADIUS servers, the Security Gateway will randomly select one of them for authentication. When you define a group of RADIUS servers, all members of the group must use the same protocol.

To learn how to configure a RADIUS server, refer to the vendor documentation.

After you configure RADIUS server authentication, you can, in addition, configure authentication with a certificate file. The administrator can then authenticate to SmartConsole with the RADIUS server or the certificate file.

You create the certificate file in SmartConsole. The administrator can use the certificate to log in to SmartConsole in two ways:

- Log in to SmartConsole with the **Certificate File** option. The administrator must provide the password to use the certificate file.
- You can import the certificate file to the Windows Certificate Store on the Microsoft Windows SmartConsole computer. The administrator can use this stored certificate to log in to SmartConsole with the CAPI Certificate option. The administrator does not need to provide a password to log in.

The administrator can also give the certificate to other administrators to log in to SmartConsole with no administrator account of their own.

Prerequisite:

Make sure you configured the required Permission Profile. See "Assigning Permission Profiles to Administrators" on page 115.

To configure RADIUS server authentication for an administrator

- 1. In SmartConsole, configure a new RADIUS server object
 - a. Go to the Object Explorer and select New > More > Server > RADIUS.
 - b. Give the server a Name. It can be any name.
 - c. In the **Host** field, click the drop-down arrow, click **New** and create a **New Host** with the **IP address** of the RADIUS server.
 - d. Click OK.

This host now appears in the Host field of the New RADIUS window.

- e. In the **Shared Secret** field, type the secret key that you defined previously on the RADIUS server.
- f. Click OK.
- g. Publish the SmartConsole session.

2. Create a new administrator and define RADIUS as the authentication method

- a. From the left navigation panel, click Manage & Settings..
- b. Expand **Permissions & Administrators** > click **Administrators**.
- c. From the top toolbar, click the * icon (New) > click New Administrator.

The New Administrator window opens and shows the General page.

- d. In the top field, enter the username that you configured on the RADIUS server.
- e. Optional: Enter the comment.
- f. In Authentication Method field, select RADIUS.
- g. In the **RADIUS Server** field, select the RADIUS server object you configured earlier.

- h. Optional: Create a certificate for this administrator:
 - i. In the Certificate Information field, click Create.
 - ii. In the **Password** field, enter the password.

A password is required to protect the sensitive data in the certificate file.

- iii. In the **Confirm** field, enter the same password.
- iv. Click OK.
- v. Wait for the Save As window to open.
- vi. In the File name field, make sure to include the username.
- vii. In the Save as type field, select Certificate Files (*p12).

The certificate file is in the PKCS #12 format, and has a .p12 extension.

- viii. Browse to a secure location on the SmartConsole computer.
- ix. Click Save.

Notes:

 After you save the certificate file, give the administrator this file and password.

The administrator can then authenticate with the certificate when they log in with SmartConsole to the Security Management Server.

- You can revoke this certificate at any time. Select the certificate and click **Revoke**.
- i. In the **Permission Profile** field, select the applicable profile.
- j. In the **Expiration** section, configure the required valid expiration date.
- k. Optional: On the Additional Info page, configure:
 - Phone Number
 - Contact Details
 - Email
- I. Click OK.
- m. Publish the SmartConsole session.

3. Optional: Configure a RADIUS server group for SmartConsole administrator authentication

a. In SmartConsole, configure all the servers that you want to include in the server group, as explained in *"To configure RADIUS server authentication for an administrator" on page 88*.

For each server, enter its priority in the group. The lower the number is, the higher the priority.

For example, if you create a group with 3 servers, with priorities 1,2 and 3, the server with number 1 is approached first, the server with number 2 second, and the server with number 3, third.

b. Create the server group:

In SmartConsole, go to **Object Explorer** and click **New > Server > More > RADIUS Group**.

- c. Configure the group properties and add servers to the group:
 - i. Give the group a Name. It can be any name.
 - ii. Click the + icon for each server you want to add, and select the server from the drop-down list.
 - iii. Click OK.
 - iv. Publish the SmartConsole session.
- 4. Optional: Import the certificate file into the Windows Certificate Store
 - Note This procedure applies if you create a certificate authentication in the administrator object, and you log in to SmartConsole with the CAPI Certificate option.
 - a. Right-click the *.p12 file you saved when you created the required administrator, and click **Install PFX**.

The Certificate Import Wizard opens.

- b. In the Store Location section, select the applicable option:
 - Current User (this is the default)
 - Local Machine
- c. Click **Next**.
- d. Enter the same certificate password you used when you created the required administrator certificate.
- e. Clear Enable strong private key protection.
- f. Select Mark this key as exportable.
- g. Click Next.

- h. Select Place all certificates in the following store, click Browse > Personal > OK.
- i. Click Next.
- j. Click Finish.

Creating an Administrator Account with TACACS Server Authentication

Terminal Access Controller Access Control System (TACACS) provides access control for routers, network access servers and other networked devices through one or more centralized servers.

TACACS is an external authentication method that provides verification services. With TACACS, the Security Management Server forwards authentication requests by remote administrators to the TACACS server. The TACACS server, which stores administrator account information, authenticates administrators. The system supports physical card key devices or token cards and Kerberos secret key authentication. TACACS encrypts the administrator name, password, authentication services and accounting information of all authentication requests to secure communication.

You can perform TACACS authentication for SmartConsole administrators through a TACACS server or a TACACS server group. A TACACS server group is a High Availability group of identical TACACS servers in the system. When you create the group, you define a priority for each server. If the server with the highest priority fails, the one with the next highest priority in the group takes over, and so on. If you assign the same priority to all TACACS servers, the Security Gateway will randomly select one of them for authentication. All TACACS servers in the group must use the same protocol.

To learn how to configure a TACACS server, refer to the vendor documentation.

After you configure TACACS server authentication, you can, in addition, configure authentication with a certificate file. The administrator can then authenticate to SmartConsole with the TACACS server or the certificate file.

You create the certificate file in SmartConsole. The administrator can use the certificate to log in to SmartConsole in two ways:

- Log in to SmartConsole with the **Certificate File** option. The administrator must provide the password to use the certificate file.
- You can import the certificate file to the Windows Certificate Store on the Microsoft Windows SmartConsole computer. The administrator can use this stored certificate to log in to SmartConsole with the CAPI Certificate option. The administrator does not need to provide a password to log in.

The administrator can also give the certificate to other administrators to log in to SmartConsole with no administrator account of their own.

Prerequisite:

Make sure you configured the required Permission Profile. See "Assigning Permission Profiles to Administrators" on page 115.

To configure TACACS server authentication for an administrator

- 1. In SmartConsole, add a new TACACS server object
 - a. Go to **Object Explorer** and click **New > More > Server > TACACS**.
 - b. Enter the server Name.
 - c. In the Host field, click the drop-down arrow, click New, and create a New Host with the IP address of the TACACS server.
 - d. Click OK.

This host now appears in the Host field of the New TACACS window.

- e. Select a Server type.
- f. If your server type is TACACS+, type the **Secret key** that you defined previously on the TACACS+ server.
- g. Click OK.
- h. Publish the SmartConsole session.

2. Add a new administrator and define as the authentication method

- a. From the left navigation panel, click Manage & Settings...
- b. Expand **Permissions & Administrators** > click **Administrators**.
- c. From the top toolbar, click the * icon (New) > click New Administrator.

The New Administrator window opens and shows the General page.

- d. In the top field, enter the username that you configured on the TACACS server.
- e. Optional: Enter the comment.
- f. In Authentication Method field, select TACACS.
- g. In the **TACACS Server** field, select the TACACS server object you configured earlier.

- h. Optional: Create a certificate for this administrator:
 - i. In the Certificate Information field, click Create.
 - ii. In the **Password** field, enter the password.

A password is required to protect the sensitive data in the certificate file.

- iii. In the **Confirm** field, enter the same password.
- iv. Click OK.
- v. Wait for the Save As window to open.
- vi. In the File name field, make sure to include the username.
- vii. In the Save as type field, select Certificate Files (*p12).

The certificate file is in the PKCS #12 format, and has a .p12 extension.

- viii. Browse to a secure location on the SmartConsole computer.
- ix. Click Save.

Notes:

 After you save the certificate file, give the administrator this file and password.

The administrator can then authenticate with the certificate when they log in with SmartConsole to the Security Management Server.

- You can revoke this certificate at any time. Select the certificate and click Revoke.
- i. In the **Permission Profile** field, select the applicable profile.
- j. In the **Expiration** section, configure the required valid expiration date.
- k. Optional: On the Additional Info page, configure:
 - Phone Number
 - Contact Details
 - Email
- I. Click OK.
- m. Publish the SmartConsole session.
- 3. Optional: Configure a TACACS Server group for SmartConsole administrator authentication

a. In SmartConsole, configure all the servers that you want to include in the server group, as explained in *"To configure TACACS server authentication for an administrator" on page 93*.

For each server, enter its priority in the group. The lower the number is, the higher the priority.

For example, if you create a group with 3 servers, with priorities 1,2 and 3, the server with number 1 is approached first, the server with number 2 second, and the server with number 3, third.

b. Create the server group:

In SmartConsole, go to **Object Explorer** and click **New > Server > More > TACACS Group**.

- c. Configure the group properties and add servers to the group:
 - i. Enter the group Name.
 - ii. Click the + icon for each server you want to add, and select the server from the drop-down list.
 - iii. Click OK.
 - iv. Publish the SmartConsole session.
- 4. Optional: Import the certificate file into the Windows Certificate Store
 - Note This procedure applies if you create a certificate authentication in the administrator object, and you log in to SmartConsole with the CAPI Certificate option.
 - a. Right-click the *.p12 file you saved when you created the required administrator, and click **Install PFX**.

The Certificate Import Wizard opens.

- b. In the Store Location section, select the applicable option:
 - Current User (this is the default)
 - Local Machine
- c. Click Next.
- d. Enter the same certificate password you used when you created the required administrator certificate.
- e. Clear Enable strong private key protection.
- f. Select Mark this key as exportable.
- g. Click Next.

- h. Select Place all certificates in the following store, click Browse > Personal > OK.
- i. Click Next.
- j. Click Finish.

Creating an Administrator Account with SecurID Authentication

SecurID requires administrators to possess a token authenticator and to supply a PIN or password. Token authenticators generate one-time passwords that are synchronized to an RSA Authentication Manager (AM) and may come in the form of hardware or software. Hardware tokens are key-ring or credit card-sized devices. Software tokens reside on the PC or device from which the administrator wants to authenticate. All tokens generate a random, one-time use access code that changes approximately every minute. When an administrator attempts to authenticate to a protected resource, the AM must validate the one-time use code.

The Security Management Server forwards SecurID authentication requests by remote administrators to the AM. The AM manages the database of the RSA users and their assigned hard or soft tokens. The Security Management Server act as an AM Agent and directs all access requests to the RSA AM for authentication. For additional information on agent configuration, refer to the RSA Authentication Manager documentation.

There are no specific parameters required for the SecurID authentication method. Authentication requests can be sent over SDK-supported API or through REST API.

To learn how to configure a SecurID server, refer to the vendor documentation.

After you configure SecurID authentication, you can, in addition, configure authentication with a certificate file. The administrator can then authenticate to SmartConsole with SecurID authentication or the certificate file.

You create the certificate file in SmartConsole. The administrator can use the certificate to log in to SmartConsole in two ways:

- Log in to SmartConsole with the **Certificate File** option. The administrator must provide the password to use the certificate file.
- You can import the certificate file to the Windows Certificate Store on the Microsoft Windows SmartConsole computer. The administrator can use this stored certificate to log in to SmartConsole with the CAPI Certificate option. The administrator does not need to provide a password to log in.

The administrator can also give the certificate to other administrators to log in to SmartConsole with no administrator account of their own.

Prerequiste:

Make sure you configured the required Permission Profile. See "Assigning Permission Profiles to Administrators" on page 115.

To configure SecurID authentication for an administrator

- 1. Configure the Security Management Server to use SecurID (this procedure is only relevant if you use an SDK-supported API)
 - a. Connect to the command line on the Security Management Server.
 - b. Log in to the Expert mode.
 - c. Copy the sdconf.rec file to the /var/ace/ directory.

If the /var/ace/ directory does not exist, create it with this command:

```
mkdir -v /var/ace/
```

d. Assign all permissions to the sdconf.rec file:

```
chmod -v 777 /var/ace/sdconf.rec
```

- 2. Configure the SecurID Server object
 - a. Add a new SecurID server object:

Go to the Object Explorer and select New > More > Server > New SecurID.

- b. In the top field, enter the applicable object name.
- c. Optional: Enter the comment.
- d. This step applies only to SDK-supported API:

Click Browse and select the sdconf.rec file.

This must be a copy of the file that is located on the Security Management Server.

- e. Click OK.
- 3. Add a new administrator and define SecurID as the authentication method
 - a. From the left navigation panel, click Manage & Settings...
 - b. Expand **Permissions & Administrators** > click **Administrators**.
 - c. From the top toolbar, click the * icon (New) > click New Administrator.

The New Administrator window opens and shows the General page.

- d. In the top field, enter the applicable object name.
- e. Optional: Enter the comment.
- f. In Authentication method, select SecurID.

- g. Optional: Create a certificate for this administrator:
 - i. In the Certificate Information field, click Create.
 - ii. In the **Password** field, enter the password.

A password is required to protect the sensitive data in the certificate file.

- iii. In the **Confirm** field, enter the same password.
- iv. Click OK.
- v. Wait for the Save As window to open.
- vi. In the File name field, make sure to include the username.
- vii. In the Save as type field, select Certificate Files (*p12).

The certificate file is in the PKCS #12 format, and has a .p12 extension.

- viii. Browse to a secure location on the SmartConsole computer.
- ix. Click Save.

Notes:

 After you save the certificate file, give the administrator this file and password.

The administrator can then authenticate with the certificate when they log in with SmartConsole to the Security Management Server.

- You can revoke this certificate at any time. Select the certificate and click Revoke.
- h. In the **Permission Profile** field, select the applicable profile.
- i. In the **Expiration** section, configure the required valid expiration date.
- j. Optional: On the Additional Info page, configure:
 - Phone Number
 - Contact Details
 - Email
- k. Click OK.
- I. Publish the SmartConsole session.
- 4. Optional: Import the certificate file into the Windows Certificate Store
 - Note This procedure applies if you create a certificate authentication in the administrator object, and you log in to SmartConsole with the CAPI Certificate option.

a. Right-click the *.p12 file you saved when you created the required administrator, and click **Install PFX**.

The Certificate Import Wizard opens.

- b. In the Store Location section, select the applicable option:
 - Current User (this is the default)
 - Local Machine
- c. Click Next.
- d. Enter the same certificate password you used when you created the required administrator certificate.
- e. Clear Enable strong private key protection.
- f. Select Mark this key as exportable.
- g. Click Next.
- h. Select Place all certificates in the following store, click Browse > Personal > OK.
- i. Click Next.
- j. Click Finish.

Creating an Administrator Account with SAML Authentication Login

With SAML authentication, administrators log in to SmartConsole through a central 3rd party Identity Provider with the SAML protocol. The Identity Provider holds the information about the administrators, including the ability to authenticate the administrators. Check Point supports these Identity Providers: Okta, Ping Identity, Azure.

Use Case

Administrators with accounts in Azure want to work with SmartConsole. If each administrator uses two different administrator names and passwords, one for Azure and one for SmartConsole, this causes a number of issues:


- The administrators must handle different password and expiration policies (in addition to other corporate passwords).
- The administrators must remember two different passwords, one for Azure and one for SmartConsole (in addition to other corporate passwords).
- It requires additional maintenance of the administrators. For example, when an administrator leaves, you must remove them from all applications they are registered to. If you use an Identity Provider, you simply need to remove the administrator from the Identity Provider database.

Therefore, the organization prefers that each administrator uses one password for both Azure and SmartConsole. With the Identity Provider, the administrator can authenticate once to Azure, and when the administrator connects to SmartConsole, SmartConsole already recognizes them and they do not have to enter another password. This way, the administrator also does not reveal their password to the Security Management Server.

SAML Authentication Process Flow:

- 1. The administrator tries to log in to SmartConsole.
- 2. SmartConsole redirects the administrator back to the browser to a URL which is preconfigured on the Security Management Server.
- 3. The Security Management Server redirects the browser with a SAML request to the Identity Provider.
- 4. The Identity Provider authenticates the administrator.
- 5. The Identity Provider generates a SAML assertion and sends it back to the Security Management Server through the browser.
- 6. The Security Management Server validates the SAML assertion.

- 7. If the administrator is authenticated, the Security Management Server redirects the browser to SmartConsole with the necessary data required for authentication.
- 8. SmartConsole opens a session to the Security Management Server with this authentication data.



SAML Authentication Login

- Note By default, SAML authentication for SmartConsole login requires Gaia Portal on the Management Server to work on the TCP port 443. If Gaia Portal runs on a different port, then enter this port number in the SmartConsole login window (<IP_ Address>:<Port>). For more information, see sk182032.
 - 1. In your Identity Provider, create the SmartConsole application and configure its settings

See your Identity Provider documentation for instructions.

Notes:

- Make sure the client can connect to the Identity Provider website and that there is no policy rule that blocks it.
- The SmartConsole application integration in your Identity Provider must have attribute mappings for "username", and it must have the "sign assertion and response" option selected.
- The Identity Provider can return response to more than one URL. In a Management High Availability environment, enter the required number of Reply URLs.

When the Identity Provider sends the response, the response must contain the IP address that the response is returned to.

If the required destination is not included in the response, the response is eliminated.

Make sure to disable the use of "Default" for the Reply URLs:

Assertion Consumer Service URL (Set by Application) * Primary Management Reply URL	0	Default* No		+
		Default value: POST		
Assertion Consumer Service URL (Set by Application) * Secondary Management Reply URL	0	Default* No	*	-
		Default value: POST		

- 2. In SmartConsole, create an Identity Provider object and configure its settings
 - a. In the Object Explorer, click **New > More > User/Identity > Identity Provider**.

The New Identity Provider window opens.

- b. Configure these properties for the Identity Provider object:
 - Name (for example: Azure).
 - Use Identity Provider for Select Managing administrator access. This handles the authentication to SmartConsole through an Identity Provider.

Note - To use the SAML authentication for **Security Gateway and logs**, see the *R82 Identity Awareness Administration Guide*.

Data Required by the SAML Identity Provider - SmartConsole creates the Identifier (Entity ID) and the Reply URLs according to the environment.

Take the Identifier (Entity ID) and Reply URL that SmartConsole showed you and enter them in the relevant places in the properties of the SmartConsole application you created in your Identity Provider.

To use a Domain name instead of a URL



Note - For a Security Management Server and Multi-Domain Server behind NAT, these steps must be followed.

In a Management High Availability environment, you must do these steps on each Management Server.

- i. Connect to the command line on the Management Server.
- ii. Log in to the Expert mode.
- iii. Back up the current \$CPDIR/tmp/.CPprofile.sh file:

```
cp -v$CPDIR/tmp/.CPprofile.sh{, BKP}
```

iv. Edit the \$CPDIR/tmp/.CPprofile.sh file:

```
vi $CPDIR/tmp/.CPprofile.sh
```

v. Add this line at the bottom of the file:

```
SAML IP OR NAME = < Your Domain Name >; export
SAML IP OR NAME
```

Example:

```
SAML IP OR NAME=example.com;export SAML IP OR
NAME
```

- vi. Save the changes in the file and exit the editor.
- vii. Restart Check Point services (this action disconnects SmartConsole clients):
 - On a Security Management Server, run: cpstop ; cpstart
 - On a Multi-Domain Server, run: mdsstop ; mdsstart

viii. Connect with SmartConsole to the Management Server.

Creating an Administrator Account with SAML Authentication Login

- ix. Open the Identity Provider Website.
- x. In the **Reply URLs**, replace the IP address with the Domain Name.
- Data received from the SAML Identity Provider:
 - Import metadata file The Identity Provider creates this file. The metadata file has all the information required to establish trust between the Identity Provider and the Management Server.
 - If the Identity Provider has no metadata file, enter this information of the Identity Provider manually:
 - Identifier (Entity ID) Unique identifier of the Identity Provider.
 - Login (URL) This is the endpoint on the Identity Provider side where SAML requests are posted.
 - Certificate file The Management Server takes the certificate file from the Identity Provider to validate the Identity Provider's signature. The certificate is stored on the Management Server and used whenever responses are posted.
- c. Click OK.
- d. Publish the SmartConsole session.
- In SmartConsole, go to the Manage & Settings view > Permissions & Administrators > Advanced > Identity Provider > Identity Provider for Managing Administrator Access > select the Identity Provider object that you created.

Notes

- On a Security Management Server, you can use only one Identity Provider.
- On a Multi-Domain Security Management Server:
 - You can use only one Identity Provider for a Domain.
 - If you configure an Identity Provider for the Multi-Domain Server and do not configure an Identity Provider for a Domain, the Domain Management Server takes the Identity Provider configured for the Multi-Domain Server.
 - Only super user can assign an Identity Provider to a Domain.
 - To access the Domain with the Domain's Identity Provider, open SmartConsole and connect to the Domain's IP address.
 - Domain's Identity Provider can only authenticate for administrators or groups that have a permission profile for the Domain.
- 4. Create the administrator (or group of administrators) that authenticates with an Identity Provider

Prerequiste: Make sure you configured the required Permission Profile. See "Assigning Permission Profiles to Administrators" on page 115.

- a. From the left navigation panel, click Manage & Settings...
- b. Expand **Permissions & Administrators** > click **Administrators**.
- c. From the top toolbar, click the * icon (New) > click New Administrator.

The New Administrator window opens and shows the General page.

d. In the top field, enter the applicable object name.

The object name must be identical to the name defined in the Identity Provider's username attribute.

- e. Optional: Enter the comment.
- f. In Authentication Method field, select Identity Provider.
- g. Optional: Create a certificate for this administrator:
 - i. In the Certificate Information field, click Create.
 - ii. In the **Password** filed, enter the password.

A password is required to protect the sensitive data in the certificate file.

- iii. In the Confirm filed, enter the same password.
- iv. Click OK.
- v. Wait for the Save As window to open.
- vi. In the File name field, make sure to include the username.
- vii. In the Save as type field, select Certificate Files (*p12).

The certificate file is in the PKCS #12 format, and has a .p12 extension.

- viii. Browse to a secure location on the SmartConsole computer.
- ix. Click Save.

Notes:

 After you save the certificate file, give the administrator this file and password.

The administrator can then authenticate with the certificate when they log in with SmartConsole to the Security Management Server.

- You can revoke this certificate at any time. Select the certificate and click **Revoke**.
- h. In the **Permission Profile** field, select the applicable profile.

- i. Optional: On the Additional Info page, configure:
 - Phone Number
 - Contact Details
 - Email
- j. Click OK.
- k. Publish the SmartConsole session.

Notes:

- In the Identity Provider's interface, configure a SAML attribute:
 - i. Define an optional attribute named "groups".
 - ii. Configure the attribute according to the Identity Provider's requirements.
- If you configure an administrator group, configure these settings
 - Name Enter a name for the administrator group object. You can select any name.
 - **Group ID/name** Must be identical to the group attribute defined in the Identity Provider.
- The **Expiration** date is grayed out because it is defined in the Identity Provider's database.
- 5. There are two ways to log in to SmartConsole with Identity Provider.

Logging in through the SmartConsole login window

- a. Open SmartConsole.
- b. From the first drop-down menu, select Identity Provider.

The Security Management Server checks if the administrator exists in the Security Management Server database.

- If the administrator exists, the SmartConsole logs the administrator in.
- If the administrator does not exist, the Security Management Server checks if the administrator is in an administrator group in the Security Management Server database.

If the administrator exists in such a group, SmartConsole logs in the administrator, and the Security Management Server assigns the administrator the permissions of the group.

- c. Enter the IP address or hostname of the Management Server.
- d. Click Login with SSO.

Notes:

- If an administrator has an administrator account and is also part of an administrator group, the Security Management Server assigns to the administrator the administrator account permissions.
- If the administrator belongs to more than one administrator group, the Security Management Server assigns to the administrator the permissions of the administrator group which comes first in alphabetical order in the Security Management Server database.
- The administrator session is not disconnected if you disconnect or edit the administrator object in the Identity Provider while the Security Management Server session is active.

Best Practice - We recommend to use at least one administrator that is not authenticated through the Identity Provider, in case the Identity Provider is not available.

Logging in with a SmartConsole configuration file

CLI Syntax:

To launch SmartConsole with a configuration file for SAML login, use this command in the Windows Command Prompt:

SmartConsole.exe -p "Full Path to the Configuration File"

Example:

```
cd /d "C:\Program Files (x86)\CheckPoint\SmartConsole\R82\"
```

SmartConsole.exe -p "D:\MySAML Configuration.xml"

Required Configuration File:

This is the required configuration file (plain-text XML):

```
<?xml version="1.0" encoding="utf-8"?>
<RemoteLaunchParemeters
xmlns:xsi="http:/www.w3.org/2001/XMLSchema-instance"
xmlns:xsd="http:/www.w3.org/2001/XMLSchema">
<ServerIP>IP Address of the Management Server</ServerIP>
<DomainName>Name of the Domain Management Server</DomainName>
<ReadOnly>False</ReadOnly>
<CloudDemoMode>False</CloudDemoMode>
<IsSamlLogin>1</IsSamlLogin>
</RemoteLaunchParemeters>
```

Parameters:

Parameter	Description
<serverip></serverip>	Specifies the IP Address of the Management Server.
<domainname></domainname>	Specifies the name of the Domain Management Server object when connecting to a Multi-Domain Security Management Server.
<readonly></readonly>	 Specifies if to open SmartConsole in the Read-Only mode. Valid values: False - Opens SmartConsole in the Write mode. True - Opens SmartConsole in the Read-Only mode.
<clouddemomode></clouddemomode>	Specifies if to enable the Demo Mode. Valid values: False - Opens SmartConsole in regular mode. True - Opens SmartConsole in the Demo mode.
<issamllogin></issamllogin>	 Specifies if to enable the SAML login. Valid values: 1 - Enables the SAML login. 0 - Disables the SAML login.

Example of the configuration file for a Security Management Server with the IP address 172.30.44.55:

After you configure SAML authentication, you can, in addition, configure authentication with a certificate file. The administrator can then authenticate to SmartConsole with the SAML Identity Provider or the certificate file.

You create the certificate file in SmartConsole. The administrator can use the certificate to log in to SmartConsole in two ways:

- Log in to SmartConsole with the Certificate File option. The administrator must provide the password to use the certificate file.
- You can import the certificate file to the Windows Certificate Store on the Microsoft Windows SmartConsole computer. The administrator can use this stored certificate to log in to SmartConsole with the CAPI Certificate option. The administrator does not need to provide a password to log in.


The administrator can also give the certificate to other administrators to log in to SmartConsole with no administrator account of their own.

Creating an Administrator Account with API Key Authentication

An API key is a token that a client provides when making API calls.

API key authentication provides an administrator the ability to use a token for authenticating to the API interface instead of the usual administrator name / password.

You can use SmartConsole to configure an API key for administrators to use the management API.



Prerequiste:

Make sure you configured the required Permission Profile. See "Assigning Permission Profiles to Administrators" on page 115.

To configure API authentication for an Administrator using SmartConsole

- 1. From the left navigation panel, click Manage & Settings...
- 2. Expand **Permissions & Administrators** > click **Administrators**.
- 3. From the top toolbar, click the * icon (New) > click New Administrator.

The New Administrator window opens and shows the General page.

- 4. In the top field, enter the applicable object name.
- 5. **Optional:** Enter the comment.
- 6. In the Authentication Method field, select API Key.
- 7. Click Generate API key:
 - a. Click Copy Key to Clipboard
 - b. Save the key for a later use (provide it to the relevant administrator).
 - c. Click OK.
- 8. In the **Permission Profile** field, select the applicable profile.
- 9. In the **Expiration** section, configure the required valid expiration date.
- 10. Optional: On the Additional Info page, configure:

- Phone Number
- Contact Details
- Email
- 11. Click **OK**.
- 12. Publish the SmartConsole session.

Example

This example demonstrates how to use the API Key for the API command "login" and the API command "add simple-gateway".

- 1. Connect to the command line on the Security Management Server.
- 2. Log in to the Expert mode.
- 3. Run the API command "login", use the previously generated API key, and save the output to a file:

Syntax:

mgmt_cli login api-key <api-key> > /<path_to>/<filename>

Example:

```
mgmt_cli login api-key mvYSiHVmlJM+J0tu2FqGag12 >
/var/tmp/token.txt
```

4. Run the API command "add simple-gateway".

Run the mgmt cli command with the "-s" flag and specify the token file.

Syntax:

```
mgmt_cli -s /<path_to>/<filename> add simple-gateway name
<gateway name> ip-address <ip address> one-time-password
<password> blade <true>
```

Example:

```
mgmt_cli -s /var/tmp/token.txt add simple-gateway name "gw1"
ip-address 192.168.3.181 one-time-password "aaaa" firewall
true vpn true
```

For more details, see the <u>Check Point Management API Reference</u>.

After you configure API authentication, you can, in addition, configure authentication with a certificate file. The administrator can then authenticate to the Security Management Server with either an API Key or a certificate file.

You create the certificate file in SmartConsole. The administrator can use the certificate to log in to SmartConsole in two ways:

- Log in to SmartConsole with the **Certificate File** option. The administrator must provide the password to use the certificate file.
- You can import the certificate file to the Windows Certificate Store on the Microsoft Windows SmartConsole computer. The administrator can use this stored certificate to log in to SmartConsole with the CAPI Certificate option. The administrator does not need to provide a password to log in.

The administrator can also give the certificate to other administrators to log in to SmartConsole with no administrator account of their own.

Assigning Permission Profiles to Administrators

A permission profile is a predefined set of Security Management Server and SmartConsole administrative permissions that you can assign to administrators. You can assign a permission profile to more than one administrator. Only Security Management Server administrators with the *Manage Administrators* permission in the profile can create and manage permission profiles.

To learn about permission profiles for Multi-Domain Security Management administrators, see the *R82 Multi-Domain Security Management Administration Guide*.

Changing and Creating Permission Profiles

Administrators with Super User permissions can edit, create, or delete permission profiles.

These are the predefined, default permission profiles. You cannot change or delete the default permission profiles. You can clone them, and change the clones:

- Read Only All Full Read Permissions. No Write permissions.
- Read Write All Full Read and Write Permissions.
- Super User Full Read and Write Permissions, including managing administrators and sessions.
- Note Multiple administrators can log in to SmartConsole with Read-Write All permission at the same time. You cannot switch between the Read Only All and Read-Write All permission profiles. To switch mode, close the session, reconnect to SmartConsole, and in the SmartConsole login screen, select or clear the Read Only checkbox, as needed.

To change the permission profile of an administrator

- 1. Click Manage & Settings > Permissions & Administrators.
- 2. Double-click the administrator account.

The Administrators properties window opens.

- 3. In the **Permissions** section, select another **Permission Profile** from the list.
- 4. Click OK.

To change a permission profile

- 1. In SmartConsole, go to Manage & Settings > Permissions & Administrators > Permission Profiles.
- 2. Double-click the profile to change.
- 3. In the **Profile** configuration window that opens change the settings as needed.
- 4. Click Close.

To create a new permission profile

- 1. In SmartConsole, go to Manage & Settings > Permissions & Administrators > Permission Profiles.
- 2. Click New Profile.

The New Profile window opens.

- 3. Enter a unique name for the profile.
- 4. Select a profile type:
 - Read/Write All Administrators can make changes to all features
 - Auditor (Read Only All) Administrators can see all information but cannot make changes
 - Customized Configure custom settings (see "Configuring Customized Permissions" on the next page).
- 5. Click OK.

To delete a permission profile

- In SmartConsole, go to Manage & Settings > Permissions & Administrators > Permission Profiles.
- 2. Select a profile and click **Delete**.

You cannot delete a profile that is assigned to an administrator. To see which administrators use a profile, in the error message, click **Where Used**.

If the profile is not assigned to administrators, a confirmation window opens.

3. Click **Yes** to confirm.

Configuring Customized Permissions

Configure administrator permissions for Gateways, Access Control, Threat Prevention, Others, Monitoring and Logging, Events and Reports, Management. For each resource, define if administrators that are configured with this profile can configure the feature or only see it.

Permissions:

- Selected The administrator has this feature.
- Not selected The administrator does not have this feature.
 - Note If you cannot clear a feature selection, the administrator access to it is mandatory.

Some features have **Read** and **Write** options. If the feature is selected:

- **Read** The administrator has the feature but cannot make changes.
- Write The administrator has the feature and can make changes.

To configure customized permissions

- 1. In the **Profile** object, in the **Overview > Permissions** section, select **Customized**.
- 2. Configure permissions in these pages of the **Profile** object:
 - Gateways -Configure the Provisioning and the Scripts permissions.
 - Access Control Configure Access Control Policy permissions (see "Configuring Permissions for Access Control and Threat Prevention" on page 120).
 - Threat Prevention Configure Threat Prevention Policy permissions (see "Configuring Permissions for Access Control and Threat Prevention" on page 120).
 - Others Configure permissions for Common Objects, user databases, HTTPS Inspection features, and Client Certificates.
 - Monitoring and Logging Configure permissions to generate and see logs and to use monitoring features (see "Configuring Permissions for Monitoring, Logging, Events, and Reports" on page 121).
 - Events and Reports Configure permissions for SmartEvent features (see "Configuring Permissions for Monitoring, Logging, Events, and Reports" on page 121).
- 3. In the Management section, configure this profile with permissions to:

- Manage Administrators Manage other administrator accounts.
- Manage Sessions Lets you disconnect, discard, publish, or take over other administrator sessions.
- High Availability Operations Configure and work with High Availability.
- Management API Login Permission to log in to the Security Management Server and run API commands using these tools:
 - mgmt cli (Linux and Windows binaries)
 - Gaia CLI (clish)
 - Web Services (REST)

Useful if you want to prevent administrators from running automatic scripts on the Management Server.

- Note This permission is not required to run commands from within the API terminal in SmartConsole.
- Cloud Management Extension (CME) API Permission to read or edit the Cloud Management Extension (CME) configuration.
- Publish sessions without an approval permission to publish without an approval.
- Approve / reject other sessions permission to approve or reject other sessions.
- Manage integration with Infinity Services Permission to connect to the Infinity Portal through the Infinity Services view in SmartConsole.
- 4. Click OK.

Important - In a Permission Profile, if you select the permission VSX Provisioning (in the Gateways tab), you must also select Publish sessions without an approval (in the Management tab), because the Management Server must save changes in VSX objects immediately.

Configuring Permissions for Access Control Layers

You can simplify the management of the Access Control Policy by delegating ownership of different Layers to different administrators.

To do this, assign a permission profile to the Layer. The permission Profile must have this permission: **Edit Layer by the selected profiles in a layer editor**.

An administrator that has a permission profile with this permission can manage the Layer.

Workflow

- 1. Give Layer permissions to an administrator profile.
- 2. Assign the permission profile to the Layer.

To give Layer permissions to an administrator profile

- 1. In the **Profile** object, in the **Access Control > Policy** section, select **Edit Layer by the** selected profiles in a layer editor.
- 2. Click OK.

To assign a permission profile to a Layer

- 1. In SmartConsole, click Menu > Manage policies and layers.
- 2. In the left pane, click Layers.
- 3. Select a Layer.
- 4. Click Edit.
- 5. In the left pane, select **Permissions**.
- 6. Click +
- 7. Select a profile with Layer permissions.
- 8. Click OK.
- 9. Click Close.
- 10. Publish the SmartConsole session.

Configuring Permissions for Access Control and Threat Prevention

In the permission profile object, select the features and the Read or Write administrator permissions for them.

Access Control

To edit a Layer, a user must have permissions for all Software Blades in the Layer.

In the Actions section:

- Install Policy Install the Access Control Policy on Security Gateways.
- Application & URL Filtering Update Download and install new packages of applications and websites, to use in access rules.
- Threat Prevention

In the Actions section:

- Install Policy Install the Threat Prevention Policy on Security Gateways.
- IPS Update -Download and install new packages for IPS protections.

Configuring Permissions for Monitoring, Logging, Events, and Reports

In the **Profile** object, select the features and the Read or Write administrator permissions for them.

Monitoring and Logging Features

These are *some* of the available features:

- Monitoring
- Management Logs
- Track Logs
- Application and URL Filtering Logs
- Events and Reports Features

These are the permissions for SmartEvent:

- SmartEvent
 - Events views in SmartConsole > Logs & Events
 - Policy SmartEvent Policy and Settings on SmartEvent GUI.
 - **Reports** in SmartConsole > **Logs & Events**
- SmartEvent Application & URL Filtering reports only

Defining Trusted Clients

To limit the access to the Security Management Server from a specified list of hosts, you must configure **Trusted Clients**.

You can configure Trusted Clients in these ways:

Trusted Client Definition	Description
Any	All hosts
IPv4 Address	A single host with the specified IPv4 address
IPv4 Address Range	Hosts with IPv4 addresses in the specified range
IPv4 Netmask	Hosts with IPv4 addresses in the subnet defined by the specified IPv4 address and netmask
IPv6 Address	A single host with the specified IPv6 address
IPv6 Address Range	Hosts with IPv6 addresses in the specified range
IPv6 Netmask	Hosts with IPv6 addresses in the subnet defined by the specified IPv6 address and netmask
Name	A host with the specified hostname
Wild cards (IP only)	Hosts with IP addresses described by the specified regular expression

Administrators with Super User permissions can add, edit, or delete trusted clients in SmartConsole.

Adding a new trusted client

- In SmartConsole, go to Manage & Settings > Permissions & Administrators > Trusted Clients.
- 2. Click New.

The New Trusted Client window opens.

- 3. Enter a unique name for the client.
- 4. Select a client type and configure corresponding values:
 - Any No values to configure
 - IPv4 Address Enter an IPv4 address of a host
 - IPv4 Address Range Enter the first and the last address of an IPv4 address range
 - IPv4 Netmask Enter the IPv4 address and the netmask
 - IPv6 Address Enter an IPv6 address of a host
 - IPv6 Address Range Enter the first and the last address of an IPv6 address range
 - IPv6 Netmask Enter the IPv6 address and the netmask
 - Name Enter a host name
 - Wild cards (IP only) Enter a regular expression that describes a set of IP addresses
- 5. Click OK.

Modifying a trusted client settings

- In SmartConsole, go to Manage & Settings > Permissions & Administrators > Trusted Clients.
- 2. Double-click the client you want to edit.
- 3. In the **Trusted Client** configuration window that opens, change the settings as needed.
- 4. Click OK.

Deleting a trusted client

- 1. In SmartConsole, go to Manage & Settings > Permissions & Administrators > Trusted Clients.
- 2. Select a trusted client and click **Delete**.

The confirmation window opens.

- 3. Click **Yes** to confirm.
- Note Administrators can also configure the GUI Clients in the Check Point Configuration Tool on the Security Management Server (see "cpconfig" on page 749).

Session Flow for Administrators

In SmartConsole, administrators work with sessions. A session is created each time an administrator logs into SmartConsole. Changes made in the session are saved automatically. You can generate a changes report to show you all the changes made in a session. These changes are private and available only to the administrator. To avoid configuration conflicts, other administrators see a lock icon on objects and rules that are being edited in other sessions.

Administrators can publish or discard their private changes. To include private changes in the policy installation, you must publish your changes in the session. This is also true if you want to make your private changes available to other administrators. Unpublished changes from other sessions are not included in the policy installation.

Before you publish a session, we recommend that you give the session a name and add a brief description that documents the work process.

Publishing a Session

The validations pane in SmartConsole shows configuration error messages. Examples of errors are object names that are not unique, or the use of objects that are not valid in the Rule Base. Make sure you correct these errors before publishing.

To publish a SmartConsole session

On the **SmartConsole** toolbar, click **Publish**. When a session is published, a new database version is created and shows in the list of database revisions.

To add a name or description to a session

1. In the SmartConsole toolbar, click Session.

The Session Details window opens.

- 2. Enter a name for the database version.
- 3. Enter a description.
- 4. Click OK.

To discard a session

In the SmartConsole toolbar, click Discard.

Working in SmartConsole Session View

The Session view shows all unpublished sessions in the system. The view shows the sessions of the current administrator, sessions of other administrators and sessions from other applications. The columns in the view can be customized and show the session owner, name, description, connection mode, number of private changes, number of locks, application and other values.

To see session information, click Manage & Settings > Sessions > View Sessions.

Actions available to administrators on private sessions are determined by the **Manage Sessions** permission on their profile.

Administrators without the Manage Session permission can:	Administrators with the Manage Session Permission can:
 Publish and discard their own sessions See sessions opened by other administrators, the number the locks they have and number of changes they have made Take over sessions created by applications, for example sessions created by the API command line tool 	 Publish and discard their own sessions See sessions opened by other administrators, the number the locks they have and number changes they have made Publish & Disconnect the private sessions of other administrators Disconnect & Discard the private sessions of other administrators Disconnect another administrator's private session Take over sessions created by applications, for example sessions created by the API command line tool Take over the private sessions of other administrators. Note - If you want to keep changes made in your own private session, publish these changes <i>before</i> you take over the session of another administrator. If you do not publish your changes, you will lose them. When you take over, you disconnect the other administrator's SmartConsole session. Publish & Disconnect the private sessions of other administrators. The action applies to both SmartConsole sessions and command line API sessions. Disconnect the private session of other administrators


Viewing Changes Made in Private Sessions

You can generate a report to show you the changes made in a specific session, it can be your current session or a different one. Tracking the changes made in sessions lets you track and monitor the changes made, and troubleshoot bugs.

The change report only details changes in policy rules and common network objects. For more details, see: sk166435.

To view the changes made in your current session:

Click the Changes button on the toolbar.



A report is generated which shows the changes made in the current private session.

To view the changes made in any session of your choice:

1. In SmartConsole, go to the Manage & Settings view > Sessions > View Sessions.

The list of sessions appears.

- 2. Click on the required session.
- 3. Click the Changes button on the toolbar.

A changes report is generated.

The report shows a comparison between the selected private sessions.

Note - There is inconsistency between the number of changes which appears in the session toolbar and the Revisions view.

Taking over locked objects from administrators with inactive sessions

If there are locked objects in SmartConsole by administrators with inactive sessions, but the relevant administrators are currently unavailable to log back in to SmartConsole and remove the lock, you can take over their sessions.

To take over inactive sessions of other administrators:

- 1. Log in to SmartConsole with a different administrator account.
- 2. Go to Manage & Settings > Sessions > View Sessions.
- 3. Right-click the relevant sessions of the administrator who owns the locked objects and select **Take over**.

You can now open the relevant object and publish or discard changes to remove the lock.

Administrators Working with Multiple Sessions

Administrators working with multiple sessions can open multiple additional private sessions without publishing changes made in the current private session.

Use Case

Suppose you are making changes in a private session and are asked to solve some immediate problem. The task involves making a change and publishing it. You do not wish to publish or discard your current private session.

You open a new private session, make the change required to resolve the issue, publish the change, then return to your previous private session.

To do this, you need to work with multiple sessions. To switch on multiple sessions, you need the **Manage Sessions** permission selected on your administrator profile.

To enable working in multiple sessions

- 1. Open the relevant permission profile.
- 2. Make sure the Manage Sessions permission is selected on the Management page.
- 3. Open SmartConsole > Manage & Settings View > Sessions > Advanced.
- 4. Select Each administrator can manage multiple SmartConsole sessions at the same time.
- 5. Publish the change.

When working with multiple sessions, you can:

- Open and manage multiple sessions to the Security Management Server using the same administrator account
- Switch between the active session and previously saved sessions
- Publish, discard and disconnect other sessions
- Take over other sessions

The SmartConsole Session menu

After multiple sessions are enabled, the SmartConsole Session menu has these new options:

Option	Description
Edit sessions details	Lets you change the session name and description.

Option	Description
Create new session	In the current window Opens a new session in the current SmartConsole In a new window Opens a new session in a new SmartConsole
Recent	Shows a list of recent sessions. Selecting a session opens the session in the current SmartConsole
More	 Opens the Open Session window that shows sessions that you previously created and saved. Sessions shown in this window are owned by the current administrator in the current domain. The Open Session > Actions menu has options to open a saved session in the current SmartConsole or open the session in a new SmartConsole.

The SmartConsole Session View

When multiple sessions are enabled, you can perform these additional actions:

Action	You can:
For sessions that you own	 Discard and Disconnect Publish and Disconnect Disconnect Open an older session
For sessions owned by other administrators that have made private changes	 Publish and Disconnect their changes Discard and Disconnect Disconnect Take over their changes
For sessions owned by other administrators that have not made private sessions	DisconnectTake over



- When you work in single session, you need to publish or discard your changes before you take over another session. In multiple sessions, you do not have to publish or discard your session before you take over the session of another administrator.
- In multiple sessions, an administrator who connects from another desktop to an already connected session can still take over the connected session by default.

Switching between Multiple and Single Session

If the session management settings switch from multiple SmartConsole sessions to allow only a single SmartConsole session at a time:

- Administrators can still publish, discard and open sessions that they own.
- Cannot create new sessions until they have published or discarded all their unpublished sessions with private sessions
- Cannot take over the sessions of other administrators or applications (for example sessions created with API commands in the *mgmt_cli* utility) until they have published or discarded all their previously saved private sessions.

Approval Cycle for Sessions (SmartWorkflow and Identity Provider)

Lets administrators approve changes in sessions made by other administrators.

Use Case

This feature gives you the option to review and approve configuration changes made by other administrators before publishing them. You can define which administrators must submit their changes for approval and which administrators are authorized to approve changes.

Configuration

- 1. Create a new permission profile for the Administrator "A" whose changes require approval
 - a. In SmartConsole, go to Manage & Settings > Permissions & Administrators > Permission Profiles > New Profile.

The New Profile window opens.

- b. In the Overview page ,select Read/Write All or Customized.
- c. In the **Management** page, clear the **Publish sessions without an approval** option.
- d. Configure the rest of the profile settings, and click **OK** and publish the changes.
- 2. Create a new administrator account for the Administrator "A" whose changes require approval:
 - a. In SmartConsole, go to Manage & Settings > Permissions & Administrators > Administrators > New Administrator.

The New Profile window opens.

- b. Configure the Administrator name and other properties, and in the **Permission Profile** field, select the profile you created for this administrator.
- c. Click OK.
- 3. Create a new permission profile for the Administrator "B" who approves the changes"
 - a. In SmartConsole, go to Manage & Settings > Permissions & Administrators > Permission Profiles > New Profile.

The New Profile window opens.

- b. In the Overview page ,select Read/Write All or Customized.
- c. In the Management page, select Approve/reject other sessions.

- d. Configure the rest of the profile settings, and click OK.
- 4. Create a new administrator account for the Administrator "B" who approves the changes:
 - a. In SmartConsole, go to Manage & Settings > Permissions & Administrators > Administrators > New Administrator.

The New Profile window opens.

- b. Configure the Administrator name and other properties, and in the **Permission Profile** field, select the profile you created for this administrator.
- c. Click **OK** and publish your changes.
- 5. To submit your changes for approval, in SmartConsole's top toolbar, click Submit Request
 - Note If Administrator "A" tries to install policy before his changes are approved, a message shows up indicating the changes must be submitted for approval first.

Each time Administrator "A" makes changes in the SmartConsole configuration:

After Administrator "A" modifies a rule in the Rule Base and clicks **Submit**, SmartConsole locks this rule for further changes and shows a padlock icon.

After Administrator "A" modifies an object and clicks **Submit**, SmartConsole locks this object for further changes. You can only view the object properties (right-click the object > **View**).

Note - To see the status of all sessions, go to Manage & Settings > Sessions > View Sessions.

6. Administrator "B" to reviews and approves the changes

- Note If you have sessions which are pending approval, a notification with the number of sessions pending approval appears next to the Manage & Settings tab and next to the View Sessions tab.
 - a. In SmartConsole, go to Manage & Settings > Sessions > View Sessions.
 - b. Right-click a session that is pending approval.
 - c. To review the changes, select **Review change report** from the drop-down menu.

- d. After you reviewed the changes, right-click the sessions and select one of these options from the drop-down menu:
 - To publish the session, select **Approve**. After the session is published, Administrator "A" can install policy.
 - To return the session to the submitter to fix, select Reject. If you select this option, you return the session to Administrator "A". A window opens and you must provide the return justification.
- 7. Administrator "A" sees the notifications of the reviewed sessions in the Manage & Settings tab and the View Sessions tab.

To fix a session, click a session and select **open session** from the drop-down menu.

Notes:

- To get email notifications about session updates, go to Manage & Settings > SmartTasks, and configure the applicable SmartTask (see "SmartTasks" on page 599).
- To be able to save changes in the Database Tool or in SmartProvisioning, you
 must have permission to publish your changes without an approval. If the
 Publish sessions without an approval, option is cleared, you cannot save
 changes in the Database Tool or in SmartProvisioning.

Setting up for Team Work

As an administrator, you can delegate tasks, such as defining objects and users, to other administrators. Make sure to create administrator accounts (see *"Managing Administrator Accounts" on page 74*) with the privileges that are required to accomplish those tasks.

If you are the only administrator, we recommend that you create a second administrator account with Read Only permissions, which is useful for troubleshooting, consultation, or auditing.

Managing User Accounts

A user account is an object that represents a user that generates traffic in a Check Point environment. The Management Server administrators create, manage and monitor user accounts. The Security Gateway lets you control access privileges for authenticated users. The administrator uses the Security Rule Base to restrict or give users access to specified resources. Users are unaware of the groups to which they belong. Limitation of access to sensitive information and resources only to authorized users ensures the security of the organization's network and data.

Users authenticate to Security Gateways. Check Point supports different Authentication Methods for users.

All users are configured directly in SmartConsole (in contrast to users configured on external servers, such as Active Directory), and are stored on the Management Server in the management database.

When an administrator installs a policy, the Management Server copies the applicable user data to the managed Security Gateway.

When an administrator installs a database (**Menu** > **Install Database**), the Management Server copies the applicable user data to the managed servers (for example, the Log Server).

Creating a User Account

When you create a user account through SmartConsole, you can select one of these authentication methods:

Authentication Method	Description
Check Point Password	Check Point password is a static password that is configured in SmartConsole. The local database on the Security Gateway stores the password. No additional software is required. See "Creating a User Account with Check Point Password Authentication" on page 145.
OS Password	OS Password is stored on the operating system of the computer on which the Security Gateway is installed. You can also use passwords that are stored in a Windows domain. No additional software is required. See "Creating a User Account with OS Password Authentication" on page 149

Authentication Method	Description
RADIUS	Remote Authentication Dial-In User Service (RADIUS) is an external authentication method that provides security and scalability by separating the authentication function from the access server. With RADIUS, the Security Gateway lets you control access privileges for authenticated RADIUS users, based on the administrator's assignment of users to RADIUS groups. These groups are used in the Security Rule Base to restrict or give users access to specified resources. Users are unaware of the groups to which they belong. The Security Gateway forwards authentication requests by remote users to the RADIUS server. The RADIUS server, which stores user account information, does the authentication. The RADIUS protocol uses UDP to communicate with the Security Gateway. To use RADIUS groups, you must define a return attribute in the RADIUS user profile of the RADIUS server. This attribute is returned to the Security Gateway and contains the group name (for example, RAD_<group belong="" radius="" the="" to="" users="" which=""></group>) to which the users belong. For the Gaia operating system, use the attribute "Vendor-Specific" (26) - refer to RFC 2865. See "Creating a User Account with RADIUS Server Authentication" on page 153.
TACACS	Terminal Access Controller Access Control System (TACACS) provides access control for routers, network access servers and other networked devices through one or more centralized servers. TACACS is an external authentication method that provides verification services. With TACACS, the forwards authentication requests by remote users to the TACACS server. The TACACS server, which stores user account information, authenticates users. The system supports physical card key devices or token cards and Kerberos secret key authentication. TACACS encrypts the user name, password, authentication services and accounting information of all authentication requests to make sure communication is secure. See "Creating a User Account with TACACS Server Authentication" on page 160

Authentication Method	Description
SecurID	SecurID requires users to both possess a token authenticator and to supply a PIN or password. Token authenticators generate one-time passwords that are synchronized to an RSA Authentication Manager (AM) and may come in the form of hardware or software. Hardware tokens are key-ring or credit card-sized devices. Software tokens reside on the PC or device from which the user wants to authenticate. All tokens generate a random, one-time use access code that changes approximately every minute. When a user attempts to authenticate to a protected resource, the one-time use code must be validated by the AM. The Security Gateway forwards authentication requests by remote users to the AM. The AM manages the database of RSA users and their assigned hard or soft tokens. The Security Gateway acts as an AM agent and directs all access requests to the AM for authentication. For more information on agent configuration, refer to RSA Authentication Manager documentation. There are no specific parameters required for the SecurID authentication method. Authentication requests can be sent over SDK-supported API or through REST API. See "Creating a User Account with SecurID Authentication" on page 167
	u do not soloct an authoritization mothod, the user cannot leg in or

Important - If you do not select an authentication method, the user cannot log in or use network resources.

After you configure authentication with one of the Check Point authentication methods, you can, in addition, create a certificate file for the user. The user can authenticate to the Security Gateway with one of the Check Point authentication methods or with a certificate file.

You create the certificate file in SmartConsole, and the user can log in to the Security Gateway with the certificate file in two ways:

- Log in to Security Gateway with the Certificate File option. The user must provide the password to use the certificate file.
- You can import the certificate file to the Windows Certificate Store on the Microsoft Windows SmartConsole computer. The user can use this stored certificate to log in to the Security Gateway with the CAPI Certificate option. The user does not need to provide a password to log in.

Changing an Existing User

Procedure

- 1. In the Object Explorer, click User/Identity > Users.
- 2. Double-click a user.

The User window opens.

- 3. Change the properties as necessary.
- 4. Click OK.

Deleting a User

Procedure

- 1. n the Object Explorer, click **User/Identity > Users**.
- Right-click the account and select **Delete**.
 The confirmation window opens.
- 3. Click Yes.

Managing User Groups

User groups are collections of user accounts. Add the user group to the **Source** or **Destination** of a rule. You cannot add individual users to a rule.

You can also edit user groups, and delete user groups that are not used in the Rule Base.

To create a new user group

1. In the Object Explorer (F11), click **New > More > User/Identity > User Group**.

The New User Group window opens.

- 2. Enter a name for the new group.
- 3. For each user or a group of users, click the [+] sign and select the object from the list.
- 4. Configure the optional settings:
 - Mailing List Address
 - Comment
 - Tag
 - Color
- 5. Click OK.

To add new users or other user groups to a group

- In the Object Explorer (F11), select Object Categories > Users/Identities > User Groups
- 2. Right-click the user group and click Edit.

The User Group window opens.

- 3. Click +
- 4. Select users or user groups.
- 5. Click OK.

Configuring Default Expiration Settings for Users

If a user account is about to expire, notifications show when you open the properties of the user in SmartConsole.

Procedure

1. From the main Menu, select Global Properties.

The Global Properties window opens.

- 2. Click User Accounts.
- 3. Select Expire at or Expire after.
 - Expire at Select the expiration date from the calendar control.
 - Expire after Enter the number of days (from the day the account is made) before user accounts expire.
- 4. Select Show accounts expiration indication, and enter the number of days.

Expiration warnings in the SmartConsole user object show this number of days before an account expires. During this time, if the user account is to be active for longer, you can edit the user account expiration configuration. This prevents loss of working time.

Managing Users

All users are configured directly in SmartConsole (in contrast to users configured on external servers, such as Active Directory), and are stored on the Management Server in the management database.

When an administrator installs a policy, the Management Server copies the applicable user data to the managed Security Gateway.

When an administrator installs a database (**Menu** > **Install Database**), the Management Server copies the applicable user data to the managed servers (for example, Log Server).

Creating a New User Template

A user template configures a profile - all new users, for which you select this user template, automatically get these settings. You can override these template settings in each user object.

- 1. In the top right corner, click the **Objects** panel.
- 2. Click New > More > User/Identity > User Template.

The New User Template window opens.

- 3. In the top field, enter the applicable object name.
- 4. Optional: Enter the comment.
- 5. On the **General** page, configure the expiration for this object:
 - According to Global Properties
 - Expire at

This is the date, after which the user is no longer authorized to access network resources and applications.

6. On the **Groups** page, select the applicable user group objects.

All new users, for which you select this user template, are automatically added to these user groups.

- 7. On the Authentication page, select the authentication method:
 - Undefined
 - Check Point Password
 - OS Password
 - SecurID

- RADIUS
- TACACS
- 8. On the **Location** page:
 - a. Configure the allowed sources from which this user can access or send data and traffic.

These objects must already exist before you can select them.

b. Configure the allowed destinations to which this user can access or send data and traffic.

These objects must already exist before you can select them.

- 9. On the **Time** page, configure the applicable working days or hours, when the users can be authenticated for access.
- 10. On the **Encryption** page, configure the IKEv2 authentication and encryption settings for Remote Access VPN.
 - a. Select IKE.
 - b. Click Edit.

The encryption IKE Phase 2 Properties window opens.

- c. On the Authentication page, select the authentication schemes:
 - i. Password The user authenticates with a pre-shared secret password.
 - ii. **Public Key** The user authenticates with a public key contained in a certificate file.
- d. Click OK.
- 11. Click OK.
- 12. Publish the SmartConsole session.

Creating a New User

See:

- Creating a User Account with Check Point Password Authentication" on page 145
- Creating a User Account with OS Password Authentication" on page 149
- Creating a User Account with RADIUS Server Authentication" on page 153
- Creating a User Account with TACACS Server Authentication" on page 160
- "Creating a User Account with SecurID Authentication" on page 167

Editing an Existing User

- 1. In the top right corner, click the **Objects** panel.
- 2. In the list of Object Categories, click Users/Identities.
- 3. Click Users.
- 4. Double-click the applicable user object.

The User window opens.

- 5. Configure the requires settings.
- 6. Click OK.
- 7. Publish the SmartConsole session.
- 8. Install the Access Control Policy.

Deleting a User

- 1. In the top right corner, click the **Objects** panel.
- 2. In the list of Object Categories, click Users/Identities.
- 3. Click Users.
- 4. Right-click the user object and select **Delete**.
- 5. Click Yes to confirm.
- 6. Publish the SmartConsole session.
- 7. Install the Access Control Policy.

Configuring Default Expiration Settings for Users

If a user account is about to expire, notifications show when you open the properties of the user in SmartConsole.

To configure the default expiration settings

1. From the Menu, select Global Properties.

The Global Properties window opens.

- 2. Click User Accounts.
- 3. Select Expire at or Expire after.
 - Expire at Select the expiration date from the calendar control.
 - Expire after Enter the number of days (from the day the account is made) before user accounts expire.
- 4. Select Show accounts expiration indication, and enter the number of days.

Expiration warnings in the SmartConsole User object show this number of days before an account expires. During this time, if the user account is to be active for longer, you can edit the user account expiration configuration. This will avoid loss of working time.

- 5. Click OK.
- 6. Publish the SmartConsole session.

Creating a User Account with Check Point Password Authentication

Check Point password is a static password that is configured in SmartConsole. The local database on the Security Gateway stores the password. No additional software is required.

After you configure authentication with a Check Point password, you can, in addition, configure authentication with a certificate file. The user can then authenticate to the Security Gateway with the Check Point password or the certificate file.

To create a new user with Check Point password authentication

- 1. In the top right corner, click the **Objects** panel.
- 2. Click New > More > User/Identity > User.

The New User window opens.

- 3. Choose the applicable user template and click OK.
- 4. In the top field, enter the applicable object name.

This must be a unique, case sensitive character string.

If you generate a user certificate with a non-Check Point Certificate Authority, enter the Common Name (CN) component of the Distinguished Name (DN).

For example:

If the DN is: CN = James, O = My Organization, C = My Country

then enter James as the user name.

If you use Common Names as user names, they must contain exactly one string with no spaces.

- 5. **Optional:** Enter the comment.
- 6. On the **General** page, configure the applicable settings:
 - Email address (optional)
 - Mobile phone number (optional)

Expire at

This is the date, after which the user is no longer authorized to access network resources and applications.

The default expiration date is configured in **Menu > Global Properties > User** Accounts > Expiration Date.

- 7. On the **Groups** page, you can select the applicable user group objects (in addition or instead those configured in the user template).
- 8. On the Authentication page:
 - a. In the Authentication method field, select Check Point Password.

Important - If you do not select an authentication method, the user cannot log in or use network resources.

- b. Click Set new password.
- 9. On the Location page:
 - a. Configure the allowed sources from which this user can access or send data and traffic.

These objects must already exist before you can select them.

b. Configure the allowed destinations to which this user can access or send data and traffic.

These objects must already exist before you can select them.

10. On the **Time** page:

If the user has specific working days or hours, you can configure when the user can be authenticated for access.

- From and To Enter start time and end time of an expected workday. This user will not be authenticated if a login attempt is made at a time outside the given range.
- Days in week or Daily Select the days on which the user can authenticate and access resources. This user will not be authenticated if a login attempt is made on an unselected day.
- 11. On the Certificates page:

You can configure the applicable certificates for this user for more secured access control.

- a. Click New.
- b. Select the applicable option:
 - Registration Key for certificate enrollment

Sends a registration key that activates the certificate.

- i. Enter the number of days the user has to activate the certificate, before the registration key expires.
- ii. Optional: Enter a comment.
- iii. **Optional:** Click **Template** to preview the email template.
- iv. Click Send.
- v. Click OK to save this key.
- Certificate file (p12)

Creates a *.p12 certificate file with a private password for the user.

i. Enter and confirm the certificate password.

A password is required to protect the sensitive data in the certificate file.

- ii. Optional: Enter a comment.
- iii. Click OK.
- iv. Wait for the Save As window to open.
- v. In the File name field, make sure to include the username.
- vi. In the Save as type field, select Certificate Files (*p12).

The certificate file is in the PKCS #12 format, and has a .p12 extension.

- vii. Browse to a secure location on the SmartConsole computer.
- viii. Click Save.
- ix. Give the user this file and password.
- c. Click OK.

Notes:

- If a user will not be in the system for some time (for example, going on an extended leave), you can revoke the certificate. This leaves the user account in the system, but it cannot be accessed until you renew the certificate.
- To revoke a key / certificate, select the key / certificate and click **Revoke**.
- 12. On the Encryption page:

You can configure the IKEv2 authentication and encryption settings for Remote Access VPN.

- a. Select IKE.
- b. Click Edit.

The encryption IKE Phase 2 Properties window opens.

- c. On the Authentication page, select the authentication schemes:
 - i. **Password** The user authenticates with a pre-shared secret password.
 - ii. **Public Key** The user authenticates with a public key contained in a certificate file.
- d. On the **Encryption** page, there are no settings to configure.

Youy configure these algorithms in SmartConsole > Global Properties > **Remote** Access > VPN - Authentication > section Encryption algorithms.

- e. Click OK.
- 13. Click OK.
- 14. Publish the SmartConsole session.
- 15. Install the Access Control Policy.

Creating a User Account with OS Password Authentication

OS Password is stored on the operating system of the computer on which the Security Gateway is installed. You can also use passwords that are stored in a Windows domain. No additional software is required.

After you configure authentication with an operating system password, you can, in addition, configure authentication with a certificate file. The user can then authenticate to the Security Gateway with the operating system password or the certificate file.

To create a new user with OS password authentication

- 1. In the top right corner, click the **Objects** panel.
- 2. Click New > More > User/Identity > User.

The New User window opens.

- 3. Choose the applicable user template and click OK.
- 4. In the top field, enter the applicable object name.

This must be a unique, case sensitive character string.

If you generate a user certificate with a non-Check Point Certificate Authority, enter the Common Name (CN) component of the Distinguished Name (DN).

For example:

```
If the DN is: CN = James, O = My Organization, C = My Country
```

then enter James as the user name.

If you use Common Names as user names, they must contain exactly one string with no spaces.

- 5. Optional: Enter the comment.
- 6. On the General page, configure the applicable settings:
 - Email address (optional)
 - Mobile phone number (optional)

Expire at

This is the date, after which the user is no longer authorized to access network resources and applications.

The default expiration date is configured in **Menu > Global Properties > User** Accounts > Expiration Date.

- 7. On the **Groups** page, you can select the applicable user group objects (in addition or instead those configured in the user template).
- 8. On the Authentication page:
 - a. In the Authentication method field, select OS Password.
 - Important If you do not select an authentication method, the user cannot log in or use network resources.
 - b. Click Set new password.
- 9. On the Location page:
 - a. Configure the allowed sources from which this user can access or send data and traffic.

These objects must already exist before you can select them.

b. Configure the allowed destinations to which this user can access or send data and traffic.

These objects must already exist before you can select them.

10. On the **Time** page:

If the user has specific working days or hours, you can configure when the user can be authenticated for access.

- From and To Enter start time and end time of an expected workday. This user will not be authenticated if a login attempt is made on a time outside the given range.
- Days in week or Daily Select the days on which the user can authenticate and access resources. This user will not be authenticated if a login attempt is made on an unselected day.
- 11. On the Certificates page:

You can configure the applicable certificates for this user for more secured access control.

- a. Click New.
- b. Select the applicable option:
 - Registration Key for certificate enrollment

Sends a registration key that activates the certificate.

- i. Enter the number of days the user has to activate the certificate, before the registration key expires.
- ii. Optional: Enter a comment.
- iii. **Optional:** Click **Template** to preview the email template.
- iv. Click Send.
- v. Click OK to save this key.
- Certificate file (p12)

Creates a *.p12 certificate file with a private password for the user.

i. Enter and confirm the certificate password.

A password is required to protect the sensitive data in the certificate file.

- ii. Optional: Enter a comment.
- iii. Click OK.
- iv. Wait for the Save As window to open.
- v. In the File name field, make sure to include the username.
- vi. In the Save as type field, select Certificate Files (*p12).

The certificate file is in the PKCS #12 format, and has a .p12 extension.

- vii. Browse to a secure location on the SmartConsole computer.
- viii. Click Save.
- ix. Give the user this file and password.
- c. Click OK.

Notes:

- If a user will not be in the system for some time (for example, going on an extended leave), you can revoke the certificate. This leaves the user account in the system, but it cannot be accessed until you renew the certificate.
- To revoke a key / certificate, select the key / certificate and click **Revoke**.
- 12. On the Encryption page:

You can configure the IKEv2 authentication and encryption settings for Remote Access VPN.

- a. Select IKE.
- b. Click Edit.

The encryption IKE Phase 2 Properties window opens.

- c. On the Authentication page, select the authentication schemes:
 - i. **Password** The user authenticates with a pre-shared secret password.
 - ii. **Public Key** The user authenticates with a public key contained in a certificate file.
- d. On the **Encryption** page, there are no settings to configure.

Youy configure these algorithms in SmartConsole > Global Properties > **Remote** Access > VPN - Authentication > section Encryption algorithms.

- e. Click OK.
- 13. Click **OK**.
- 14. Publish the SmartConsole session.
- 15. Install the Access Control Policy.

Creating a User Account with RADIUS Server Authentication

Remote Authentication Dial-In User Service (RADIUS) is an external authentication method that provides security and scalability by separating the authentication function from the access server.

With RADIUS, the Security Gateway lets you control access privileges for authenticated RADIUS users, based on the administrator's assignment of users to RADIUS groups. These groups are used in the Security Rule Base to restrict or give users access to specified resources. Users are unaware of the groups to which they belong.

The Security Gateway forwards authentication requests by remote users to the RADIUS server. The RADIUS server, which stores user account information, does the authentication.

The RADIUS protocol uses UDP to communicate with the Security Gateway.

To use RADIUS groups, you must define a return attribute in the RADIUS user profile of the RADIUS server. This attribute is returned to the Security Gateway and contains the group name (for example, **RAD_<group to which the RADIUS users belong>**) to which the users belong.

For the Gaia operating system, use the attribute "Vendor-Specific" (26) - refer to RFC 2865.

To learn how to configure a RADIUS server, refer to the vendor documentation.

Users can perform RADIUS authentication through a RADIUS server or a RADIUS server group. A RADIUS server group is a high availability group of identical RADIUS servers which includes any or all the RADIUS servers in the system. When you create the group, you define a priority for each server in the group. If the server with the highest priority fails, the one with the next highest priority in the group takes over, and so on. If you assign the same priority to all RADIUS servers, the Security Gateway will randomly select one of them for authentication.

After you configure authentication with a RADIUS server, you can, in addition, configure authentication with a certificate file. The user can then authenticate to the Security Gateway with the RADIUS server or the certificate file.

Configuring RADIUS Authentication for a User

- 1. In SmartConsole, configure a new RADIUS Server object
 - a. In the top right corner, click the **Objects** panel.
 - b. Click **New > More > Server > RADIUS**.
 - c. In the top field, enter the applicable object name.
 - d. **Optional:** Enter the comment.

- e. In the Host field, click the drop-down arrow, click New.
- f. Create a New Host with the IP address of the RADIUS server. Click OK.
- g. Make sure that this host shows in the Host field of the New RADIUS window.
- h. In the **Service** field, leave the default value **RADIUS**.
- i. In the **Shared Secret** field, enter the secret key that you defined previously on the RADIUS server.
- j. In the Version field, leave the default value RADIUS Ver. 1.0.
- k. In the Protocol field, leave the default value PAP.
- I. In the **Priority** field, leave the default value 1.
- m. Click OK.
- n. Publish the SmartConsole session.

2. Create a new user and select RADIUS as the authentication method

- a. In the top right corner, click the **Objects** panel.
- b. Click New > More > User/Identity > User.

The New User window opens.

- c. Choose the applicable user template and click OK.
- d. In the top field, enter the applicable object name.

This must be a unique, case sensitive character string.

If you generate a user certificate with a non-Check Point Certificate Authority, enter the Common Name (CN) component of the Distinguished Name (DN).

For example:

```
If the DN is: CN = James, O = My Organization, C = My Country
```

then enter James as the user name.

If you use Common Names as user names, they must contain exactly one string with no spaces.

e. Optional: Enter the comment.

- f. On the General page, configure the applicable settings:
 - Email address (optional)
 - Mobile phone number (optional)
 - Expire at

This is the date, after which the user is no longer authorized to access network resources and applications.

The default expiration date is configured in **Menu > Global Properties > User Accounts > Expiration Date**.

- g. On the **Groups** page, you can select the applicable user group objects (in addition or instead those configured in the user template).
- h. On the Authentication page:
 - i. In the Authentication method field, select RADIUS.
 - ii. In the **RADIUS server** field, leave the default value **Any** or select the applicable RADIUS server object.
 - Important If you do not select an authentication method, the user cannot log in or use network resources.
- i. On the Location page:
 - i. Configure the allowed sources from which this user can access or send data and traffic.

These objects must already exist before you can select them.

ii. Configure the allowed destinations to which this user can access or send data and traffic.

These objects must already exist before you can select them.

j. On the **Time** page:

If the user has specific working days or hours, you can configure when the user can be authenticated for access.

- From and To Enter start time and end time of an expected workday. This user will not be authenticated if a login attempt is made on a time outside the given range.
- Days in week or Daily Select the days on which the user can authenticate and access resources. This user will not be authenticated if a login attempt is made on an unselected day.
- k. On the Certificates page:

You can configure the applicable certificates for this user for more secured access control.

- i. Click New.
- ii. Select the applicable option:
 - Registration Key for certificate enrollment

Sends a registration key that activates the certificate.

- i. Enter the number of days the user has to activate the certificate, before the registration key expires.
- ii. Optional: Enter a comment.
- iii. Optional: Click Template to preview the email template.
- iv. Click Send.
- v. Click OK to save this key.
- Certificate file (p12)

Creates a *.p12 certificate file with a private password for the user.

i. Enter and confirm the certificate password.

A password is required to protect the sensitive data in the certificate file.

- ii. Optional: Enter a comment.
- iii. Click OK.
- iv. Wait for the Save As window to open.
- v. In the File name field, make sure to include the username.
- vi. In the Save as type field, select Certificate Files (*p12).

The certificate file is in the PKCS #12 format, and has a .p12 extension.

- vii. Browse to a secure location on the SmartConsole computer.
- viii. Click Save.
- ix. Give the user this file and password.

iii. Click OK.

Notes:

- If a user will not be in the system for some time (for example, going on an extended leave), you can revoke the certificate. This leaves the user account in the system, but it cannot be accessed until you renew the certificate.
- To revoke a key / certificate, select the key / certificate and click Revoke.
- I. On the Encryption page:

You can configure the IKEv2 authentication and encryption settings for Remote Access VPN.

- i. Select IKE.
- ii. Click Edit.

The encryption IKE Phase 2 Properties window opens.

- iii. On the Authentication page, select the authentication schemes:
 - i. **Password -** The user authenticates with a pre-shared secret password.
 - ii. **Public Key** The user authenticates with a public key contained in a certificate file.
- iv. On the Encryption page, there are no settings to configure.

Youy configure these algorithms in SmartConsole > Global Properties > **Remote Access > VPN - Authentication** > section **Encryption algorithms**.

- v. Click OK.
- m. Click OK.
- 3. Optional: Configure a RADIUS server group for SmartConsole user authentication

Note - When defining a group of RADIUS servers, all members of the group must use the same protocol.

- a. In SmartConsole, configure all the servers that you want to include in the server group. For each server, enter its priority in the group. The lower the number is, the higher the priority. For example, if you create a group with 3 servers, with priorities 1,2 and 3, the server with number 1 is approached first, the server with number 2 second, and the server with number 3, third.
- b. Create the server group:

In SmartConsole, go to **Object Explorer** and click **New > Server > More > RADIUS Group**.

- c. Configure the group properties and add servers to the group:
 - i. Give the group a Name. It can be any name.
 - ii. Click the plus (+) for each server you want to add, and select each server from the drop-down list.
 - iii. Click OK.
 - iv. Publish the SmartConsole session.
- d. Add a new user.
- e. Publish the SmartConsole session.
- f. Install the Access Control Policy.

Granting User Access Using RADIUS Server Groups

The Security Gateway lets you control access privileges for authenticated RADIUS users, based on the assignment of users to RADIUS groups. These groups are used in the Security Policy to restrict or give users access to specified resources. Users are unaware of the groups to which they belong.

To use RADIUS groups, you must define a return attribute in the RADIUS user profile of the RADIUS server. This attribute is returned to the Security Gateway and contains the group name (for example, **RAD_<group to which the RADIUS users belong>**) to which the users belong.

Use the RADIUS attribute "Vendor-Specific" (26). Refer to RFC 2865.

Creating a User Account with TACACS Server Authentication

Terminal Access Controller Access Control System (TACACS) provides access control for routers, network access servers and other networked devices through one or more centralized servers.

TACACS is an external authentication method that provides verification services. With TACACS, the forwards authentication requests by remote users to the TACACS server. The TACACS server, which stores user account information, authenticates users. The system supports physical card key devices or token cards and Kerberos secret key authentication. TACACS encrypts the user name, password, authentication services and accounting information of all authentication requests to make sure communication is secure.

To configure a Security Gateway to use TACACS authentication, you must set up the server and enable its use on the Security Gateway.

Users can perform TACACS authentication through a TACACS server or a TACACS server group. A TACACS server group is a high availability group of identical TACACS servers which includes any or all the TACACS servers in the system. When you create the group, you define a priority for each server in the group. If the server with the highest priority fails, the one with the next highest priority in the group takes over, and so on. If you assign the same priority to all TACACS servers, the Security Gateway will randomly select one of them for authentication.

After you configure authentication with a TACACS server, you can, in addition, configure authentication with a certificate file. The user can then authenticate to the Security Gateway with the TACACS server or the certificate file.

To configure TACACS server authentication for a user

- 1. In SmartConsole, configure a new TACACS / TACACS+ server object
 - a. In the top right corner, click the **Objects** panel.
 - b. Click **New > More > Server > TACACS**.
 - c. In the top field, enter the applicable object name.
 - d. Optional: Enter the comment.
 - e. In the Host field, click the drop-down arrow, click New.
 - f. Create a New Host with the IP address of the TACACS server. Click OK.
 - g. Make sure that this host shows in the Host field of the New TACACS window.

h. In the Servers type section, select the applicable value.

Best Practice - The default value is TACACS, but we recommend TACACS+.

- i. If you selected **TACACS+**, then in the a **Secret key** field, enter the secret key that you defined previously on the TACACS+ server.
- j. In the **Priority** field, leave the default value 1.
- k. Click OK.
- I. Publish the SmartConsole session.
- 2. Create a new user and select TACACS as the authentication method
 - a. In the top right corner, click the **Objects** panel.
 - b. Click **New > More > User/Identity > User**.

The New User window opens.

- c. Choose the applicable user template and click OK.
- d. In the top field, enter the applicable object name.

This must be a unique, case sensitive character string.

If you generate a user certificate with a non-Check Point Certificate Authority, enter the Common Name (CN) component of the Distinguished Name (DN).

For example:

If the DN is: CN = James, O = My Organization, C = My Country

then enter James as the user name.

If you use Common Names as user names, they must contain exactly one string with no spaces.

e. Optional: Enter the comment.

- f. On the General page, configure the applicable settings:
 - Email address (optional)
 - Mobile phone number (optional)
 - Expire at

This is the date, after which the user is no longer authorized to access network resources and applications.

The default expiration date is configured in **Menu > Global Properties > User Accounts > Expiration Date**.

- g. On the **Groups** page, you can select the applicable user group objects (in addition or instead those configured in the user template).
- h. On the Authentication page:
 - i. In the Authentication method field, select TACACS.
 - ii. In the **TACACS server** field, leave the default value **Any** or select the applicable TACACS server object.
 - Important If you do not select an authentication method, the user cannot log in or use network resources.
- i. On the Location page:
 - i. Configure the allowed sources from which this user can access or send data and traffic.

These objects must already exist before you can select them.

ii. Configure the allowed destinations to which this user can access or send data and traffic.

These objects must already exist before you can select them.

j. On the **Time** page:

If the user has specific working days or hours, you can configure when the user can be authenticated for access.

- From and To Enter start time and end time of an expected workday. This user will not be authenticated if a login attempt is made on a time outside the given range.
- Days in week or Daily Select the days on which the user can authenticate and access resources. This user will not be authenticated if a login attempt is made on an unselected day.
- k. On the Certificates page:

You can configure the applicable certificates for this user for more secured access control.

- i. Click New.
- ii. Select the applicable option:
 - Registration Key for certificate enrollment

Sends a registration key that activates the certificate.

- i. Enter the number of days the user has to activate the certificate, before the registration key expires.
- ii. Optional: Enter a comment.
- iii. Optional: Click Template to preview the email template.
- iv. Click Send.
- v. Click OK to save this key.
- Certificate file (p12)

Creates a *.p12 certificate file with a private password for the user.

i. Enter and confirm the certificate password.

A password is required to protect the sensitive data in the certificate file.

- ii. Optional: Enter a comment.
- iii. Click OK.
- iv. Wait for the Save As window to open.
- v. In the File name field, make sure to include the username.
- vi. In the Save as type field, select Certificate Files (*p12).

The certificate file is in the PKCS #12 format, and has a .p12 extension.

- vii. Browse to a secure location on the SmartConsole computer.
- viii. Click Save.
- ix. Give the user this file and password.

iii. Click OK.

Notes:

- If a user will not be in the system for some time (for example, going on an extended leave), you can revoke the certificate. This leaves the user account in the system, but it cannot be accessed until you renew the certificate.
- To revoke a key / certificate, select the key / certificate and click Revoke.
- I. On the Encryption page:

You can configure the IKEv2 authentication and encryption settings for Remote Access VPN.

- i. Select IKE.
- ii. Click Edit.

The encryption IKE Phase 2 Properties window opens.

- iii. On the Authentication page, select the authentication schemes:
 - i. **Password -** The user authenticates with a pre-shared secret password.
 - ii. **Public Key** The user authenticates with a public key contained in a certificate file.
- iv. On the Encryption page, there are no settings to configure.

Youy configure these algorithms in SmartConsole > Global Properties > **Remote Access > VPN - Authentication** > section **Encryption algorithms**.

- v. Click OK.
- m. Click OK.
- 3. Optional: Configure a TACACS server group for SmartConsole user authentication

Note - When defining a group of TACACS servers, all members of the group must use the same protocol.

a. In SmartConsole, configure all the servers that you want to include in the server group.

For each server, enter its priority in the group. The lower the number is, the higher the priority.

For example, if you create a group with 3 servers, with priorities 1,2 and 3, the server with number 1 is approached first, the server with number 2 second, and the server with number 3, third.

b. Create the server group:

In SmartConsole, go to **Object Explorer** and click **New > Server > More > TACACS Group**.

- c. Configure the group properties and add servers to the group:
 - i. Give the group a **Name**. It can be any name.
 - ii. Click the plus (+) for each server you want to add, and select each server from the drop-down list.
 - iii. Click OK.
 - iv. Publish the SmartConsole session.
- d. Add a new user.
- e. Publish the SmartConsole session.
- f. Install the Access Control Policy.

Creating a User Account with SecurID Authentication

SecurID requires users to both possess a token authenticator and to supply a PIN or password. Token authenticators generate one-time passwords that are synchronized to an RSA Authentication Manager (AM) and may come in the form of hardware or software. Hardware tokens are key-ring or credit card-sized devices. Software tokens reside on the PC or device from which the user wants to authenticate. All tokens generate a random, one-time use access code that changes approximately every minute. When a user attempts to authenticate to a protected resource, the one-time use code must be validated by the AM.

The Security Gateway forwards authentication requests by remote users to the AM. The AM manages the database of RSA users and their assigned hard or soft tokens. The Security Gateway acts as an AM agent and directs all access requests to the AM for authentication. For more information on agent configuration, refer to RSA Authentication Manager documentation. There are no specific parameters required for the SecurID authentication method. Authentication requests can be sent over SDK-supported API or through REST API.

After you configure SecurID authentication, you can, in addition, configure authentication with a certificate file. The user can then authenticate to the Security Gateway with the SecurID or the certificate file.

To configure SecurID authentication for users:

1. Configure the API to send authentication requests

You can select to enable one of two API types:

SDK-supported API

A proprietary API that uses a proprietary communication protocol on UDP port 5500 through SDKs available for selected platforms.

To enable SecurID authentication over SDK-supported API

a. Create the sdconf.rec file on an ACE/Server and copy it to your computer.

For details, refer to the RSA documentation.

- Important Use the IP address of a Security Gateway interface that connects to the ACE/Server:
 - For a specific Security Gateway Configure the IP address as the authentication agent.
 - For a Cluster
 Configure these IP addresses as authentication agents: Physical IP address of each Cluster Member and Cluster Virtual IP address.
 - For a VSX Virtual System on a specific VSX Gateway Configure these IP addresses as authentication agents: IP address of the VSX Gateway and IP address of the Virtual System.
 - For a VSX Virtual System on VSX Cluster Configure these IP addresses as authentication agents: Cluster Virtual IP address of the VSX Cluster and Cluster Virtual IP address of the Virtual System.
- b. Open the SecurID object in SmartConsole, click **Browse** and import the sdconf.rec file into the SecurID object.
- c. Install the Access Control policy.

Note - During the policy installation, the sdconf.rec file is transferred the Security Gateway to /var/ace/sdconf.rec.

REST API

To enable SecurID authentication over REST API

- a. Connect to the command line on the Security Gateway.
- b. Log in to the Expert mode.
- c. On a VSX Gateway or VSX Cluster Member, go to the context of VSID 0: vsenv 0
- d. Back up the current \$CPDIR/conf/RSARestServer.conf file:

cp -v \$CPDIR/conf/RSARestServer.conf{,_BKP}

e. Edit the \$CPDIR/conf/RSARestServer.conf file.

```
vi $CPDIR/conf/RSARestServer.conf
```

Fill in these fields:

- host The configured host name of the RSA server.
- port, client key, and accessid From the RSA SecurID Authentication API window.
- certificate The name of the certificate file.
- f. Save the changes in the file and exit the editor.

Note - If you do not complete the REST API configuration, the authentication is performed through the SDK-supported API.

2. Configure user groups

- a. In SmartConsole, open the Object Explorer (F11).
- b. Click New > More > User/Identity > User Group.

The New User Group window opens.

c. Enter the name of the group.

For example: SecurID_Users

Make sure the group is empty.

- d. Click OK.
- e. Publish the SmartConsole session.
- f. Install the Access Control policy.

3. Create a new user and define SecurID as the authentication method

This configuration procedure is different for internal users (that are defined in SmartConsole) and for external users.

To configure SecurID authentication settings for internal users

Internal users are users that you configure in SmartConsole. The Security Management Server keeps these users in the management database.

- a. In SmartConsole, open the Object Explorer (F11).
- b. Click **New > More > User/Identity > User**.

The New User window opens.

- c. Choose the applicable user template and click OK.
- d. In the top field, enter the applicable object name.

This must be a unique, case sensitive character string.

If you generate a user certificate with a non-Check Point Certificate Authority, enter the Common Name (CN) component of the Distinguished Name (DN).

For example:

```
If the DN is: CN = James, O = My Organization, C = My Country
```

then enter James as the user name.

If you use Common Names as user names, they must contain exactly one string with no spaces.

- e. Optional: Enter the comment.
- f. On the General page, configure the applicable settings:
 - Email address (optional)
 - Mobile phone number (optional)
 - Expire at

This is the date, after which the user is no longer authorized to access network resources and applications.

- g. On the **Groups** page, you can select the applicable user group objects (in addition or instead those configured in the user template).
- h. On the Authentication page, in the Authentication method field, select SecurID.

- i. On the Location page:
 - i. Configure the allowed sources from which this user can access or send data and traffic.

These objects must already exist before you can select them.

ii. Configure the allowed destinations to which this user can access or send data and traffic.

These objects must already exist before you can select them.

j. On the **Time** page:

If the user has specific working days or hours, you can configure when the user can be authenticated for access.

- From and To Enter start time and end time of an expected workday. This user will not be authenticated if a login attempt is made at a time outside the given range.
- Days in week or Daily Select the days on which the user can authenticate and access resources. This user will not be authenticated if a login attempt is made on an unselected day.
- k. On the Certificates page:

You can configure the applicable certificates for this user for more secured access control.

- i. Click **New**.
- ii. Select the applicable option:
 - Registration Key for certificate enrollment

Sends a registration key that activates the certificate.

- i. Enter the number of days the user has to activate the certificate, before the registration key expires.
- ii. Optional: Enter a comment.
- iii. Optional: Click Template to preview the email template.
- iv. Click Send.
- v. Click OK to save this key.
- Certificate file (p12)

Creates a \star . $\mathtt{p12}$ certificate file with a private password for the user.

i. Enter and confirm the certificate password.

A password is required to protect the sensitive data in the certificate file.

- ii. Optional: Enter a comment.
- iii. Click OK.
- iv. Wait for the Save As window to open.
- v. In the File name field, make sure to include the username.
- vi. In the Save as type field, select Certificate Files (*p12).

The certificate file is in the PKCS #12 format, and has a .p12 extension.

- vii. Browse to a secure location on the SmartConsole computer.
- viii. Click Save.
 - ix. Give the user this file and password.

iii. Click OK.



- If a user will not be in the system for some time (for example, going on an extended leave), you can revoke the certificate. This leaves the user account in the system, but it cannot be accessed until you renew the certificate.
- To revoke a key / certificate, select the key / certificate and click Revoke.
- I. On the Encryption page:

You can configure the IKEv2 authentication and encryption settings for Remote Access VPN.

- i. Select IKE.
- ii. Click Edit.

The encryption IKE Phase 2 Properties window opens.

- iii. On the Authentication page, select the authentication schemes:
 - i. **Password -** The user authenticates with a pre-shared secret password.
 - ii. **Public Key** The user authenticates with a public key contained in a certificate file.
- iv. On the **Encryption** page, there are no settings to configure.

Youy configure these algorithms in SmartConsole > Global Properties > **Remote Access > VPN - Authentication >** section **Encryption algorithms**.

- v. Click OK.
- m. Click OK.

To configure SecurID authentication settings for external users


External users are users that are you configure the Legacy SmartDashboard.

The Security Management Server does not keep these users in the management database.

- a. In SmartConsole, click Manage & Settings > Blades.
- b. In the Mobile Access section, click Configure in SmartDashboard.

Legacy SmartDashboard opens.

c. In the bottom left Network Objects pane, and click Users.



- d. Right-click on an empty space and select the applicable option:
 - If you support only one external authentication scheme, click New > External User Profile > Match all users.
 - If you support more than one external authentication scheme, click New
 > External User Profile > Match by domain.
- e. Configure the External User Profile properties:
 - i. On the General Properties page:
 - If selected Match all users, then configure:
 - In the External User Profile name field, leave the default name generic*.
 - In the **Expiration Date** field, set the applicable date.
 - If selected Match by domain, then configure:
 - In the External User Profile name field, enter the applicable name. This name is used to authenticate users by the Authentication Manager.
 - In the **Expiration Date** field, set the applicable date.
 - In the **Domain Name matching definitions** section, configure the applicable settings.
 - ii. On the Authentication page:

From the Authentication Scheme drop-down list, select SecurID.

- iii. Click OK.
- f. From the top toolbar, click **Update** (or press the **CTRL S** keys).
- g. Close the Legacy SmartDashboard.

4. Complete the SecurID authentication configuration

a. Make sure that connections between the Security Gateway and the Authentication Manager are not NATed in the Address Translation Rule Base.

On a VSX Virtual System, follow the instructions in <u>sk107281</u>.

b. In SmartConsole, install the Access Control policy.

When a Security Gateway has multiple interfaces, the SecurID agent on the Security Gateway sometimes uses the wrong interface IP to decrypt the reply from the Authentication Manager, and authentication fails.

To overcome this problem, place a new text file, named sdopts.rec in the same directory as sdconf.rec.

The file sdopts.rec should contain this line:

CLIENT IP=<IP Address>

Where <IP Address> is the primary IP address of the Security Gateway, as defined on the Authentication Manager. This is the IP address of the interface, to which the server is routed.

Example:

CLIENT IP=192.168.20.30



 Note - On a VSX Gateway and VSX Cluster Members, you must create the same sdopts.rec file in the context VSID 0 and in the context of each applicable Virtual System.

Access Roles

Access Role objects let you configure network access according to:

- Networks
- Users and user groups
- Computers and computer groups
- Remote Access VPN clients (supported for Security Gateways R80.10 and higher)

After you activate the Identity Awareness Software Blade, you can create access role objects and use them in the **Source** and **Destination** columns of Access Control Policy rules.

For more information, see the <u>R82 Identity Awareness Administration Guide</u>.

Adding Access Roles

Important - Before you add Active Directory users, machines, or groups to an Access Role, make sure there is LDAP connectivity between the Security Management Server and the AD Server that holds the management directory. The management directory is defined on the Objects Management tab in the Properties window of the LDAP Account Unit.

To create an Access Role

1. In the object tree, click New> More > Users > Access Role.

The New Access Role window opens.

- 2. Enter a Name for the access role.
- 3. Enter a **Comment** (optional).
- 4. Select a Color for the object (optional).
- 5. In the Networks pane, select one of these:
 - Any network
 - Specific networks For each network, click + and select the network from the list
- 6. In the Users pane, select one of these:
 - Any user
 - All identified users includes any user identified by a supported authentication method (internal users, Active Directory users, or LDAP users).

- Specific users/groups For each user or user group, click + and select the user or the group from the list
- 7. In the Machines pane, select one of these:
 - Any machine
 - All identified machines includes machines identified by a supported authentication method (Active Directory).
 - Specific machines For each machine, click + and select the machine from the list
- 8. In the **Remote Access Clients** pane, select the clients for remote access.
- 9. Click OK.

Identity Awareness engine automatically recognizes changes to LDAP group membership and updates identity information, including access roles.

User Directory

The Check Point User Directory stores user-specific information.

Note - User Directory requires a special license. If you have the Mobile Access Software Blade, you have the User Directory license.

The User Directory lets you:

- Configure High Availability, to duplicate user data across multiple servers for backup.
 See "Account Units and High Availability" on page 214.
- Configure *Multiple Account Units*, for distributed databases.
- Define LDAP Account Units, for encrypted User Directory connections.

See "Modifying the LDAP Server" on page 214.

Configure *Profiles*, to support multiple LDAP vendors.

See "User Directory Profiles" on page 190.

User Directory Considerations

Before you begin, plan your use of User Directory.

 Decide whether to use the User Directory servers for user management, CRL retrieval, user authentication, or all of those.

See "Working with LDAP Account Units" on page 208.

Decide how many Account Units you need.

You can have one for each User Directory server, or you can divide branches of one User Directory server among different Account Units.

See "Account Units" on page 208.

Decide whether to use High Availability setup.

See "Account Units and High Availability" on page 214.

 Determine the order of priority among the User Directory servers for High Availability and querying purposes.


See "Setting High Availability Priority" on page 215.

Assign users to different Account Units, branches, and sub-branches, so that users with common attributes (such as their role in the organization, permissions, an so on) are grouped together.

See "Managing Users on a User Directory Server" on page 203.

Deploying User Directory

User Directory integrates the Security Management Server and an LDAP server and lets the Security Gateways use the LDAP information.



Item	Description
1	Security Gateway - Retrieves LDAP user information and CRLs
2	Internet
3	Security Gateway - Queries LDAP user information, retrieves CRLs, and does bind operations for authentication
4	Security Management Server - Uses User Directory to manage user information
5	LDAP server - Server that holds one or more Account Units

Enabling User Directory

In SmartConsole, enable the Security Management Server to manage users in the Account Unit. See *"Working with LDAP Account Units" on page 208*.



Note - You cannot use the SmartConsole User Database when the User Directory LDAP server is enabled.

To enable User Directory on the Security Management Server

1. From the Menu, select **Global Properties** > **User Directory**.

The User Directory page opens.

- 2. Select Use User Directory for Security Gateways.
- 3. Configure login and password settings.
- 4. Click OK.
- 5. In the **Gateways & Servers** view (Ctrl+1), open the Security Management Server object for editing
- 6. On General Properties page, Management tab, select Network Policy Management and User Directory.
- 7. Click OK.
- 8. Install the policy.

User Directory Schema for LDAP

The User Directory default schema is a description of the structure of the data in a user directory.

It has user definitions defined for an LDAP server.

This schema does not have Security Management Server or Security Gateway specific data, such as IKE-related attributes, authentication methods, or values for remote users.

You can use the default User Directory schema, if all users have the same authentication method and are defined according to a default template.

But if users in the database have different definitions, it is better to apply a Check Point schema to the LDAP server.

See "User Directory Schema for LDAP" above.

The Check Point Schema adds Security Management Server and Security Gateway specific data to the structure in the LDAP server.

Use the Check Point Schema to extend the definition of objects with user authentication functionality.

For example, an Object Class entitled **fw1Person** is part of the Check Point schema.

This Object Class has mandatory and optional attributes to add to the definition of the Person attribute.

Another example is **fw1Template**. This is a standalone attribute that defines a template of user information.

Schema Checking

When schema checking is enabled, User Directory requires that every Check Point object class and its associated attributes is defined in the directory schema.

Before you work with User Directory, make sure that schema checking is disabled. Otherwise the integration will fail.

After the Check Point object classes and attributes are applied to the User Directory server's schema, you must enable schema checking again.

OID Proprietary Attributes

Each of the proprietary object classes and attributes (all of which begin with "fw1") has a proprietary Object Identifier (OID), listed below.

Object Class OIDs

object class	OID
fw1template	1.3.114.7.4.2.0.1
fw1person	1.3.114.7.4.2.0.2

The OIDs for the proprietary attributes begin with the same prefix ("1.3.114.7.4.2.0.X").

Only the value of "X" is different for each attribute.

See "User Directory Schema Attributes" below.

User Directory Schema Attributes

cn

The entry's name.

This is also referred to as "Common Name".

For users this can be different from the uid attribute, the name used to login to the Security Gateway.

This attribute is also used to build the User Directory entry's distinguished name, that is, it is the RDN of the DN.

The user's login name, that is, the name used to login to the Security Gateway.

This attribute is passed to the external authentication system in all authentication methods except for "Internal Password", and must be defined for all these authentication methods.

The login name is used by the Security Management Server to search the User Directory server(s).

For this reason, each user entry should have its own unique UID value.

It is also possible to login to the Security Gateway using the full DN.

The DN can be used when there is an ambiguity with this attribute or in "Internal Password" when this attribute may be missing.

The DN can also be used when the same user (with the same uid) is defined in more than one Account Unit on different User Directory servers.

description

Descriptive text about the user.

The default is "no value".

mail

User's email address.

```
The default is "no value".
```

member

An entry can have zero or more values for this attribute.

- In a template: The DN of user entries using this template. DNs that are not users (object classes that are not one of: "person", "organizationalPerson", "inetOrgPerson", or "fw1person") are ignored.
- In a group: The DN of user.

userPassword

Must be given if the authentication method (fw1auth-method) is "Internal Password". The value can be hashed using "crypt". In this case the syntax of this attribute is:

"{crypt}xxyyyyyyyyy"

where:

uid

- "xx" is the "salt"
- "yyyyyyyyyy" is the hashed password

It is possible (but not recommended) to store the password without hashing. However, if hashing is specified in the User Directory server, you should not specify hashing here, in order to prevent the password from being hashed twice. You should also use SSL in this case, to prevent sending an unencrypted password.

The Security Gateway never reads this attribute, though it does write it. Instead, the User Directory bind operation is used to verify a password.

fw1authmethod

One of these:

- RADIUS
- TACACS
- SecurID
- OS Password
- Defender

This default value for this attribute is overridden by **Default authentication scheme** in the **Authentication** tab of the **Account Unit** window in SmartConsole.

For example: a User Directory server can contain User Directory entries that are all of the object-class "person" even though the proprietary object-class "fwlperson" was not added to the server's schema.

If **Default authentication scheme** in SmartConsole is "Internal Password", all the users will be authenticated using the password stored in the "userPassword" attribute.

fw1authserver

"X" in OID	fw1person	fw1template	default
1	у	у	"undefined"

The name of the server that will do the authentication.

This field must be given if fw1auth-method is "RADIUS" or "TACACS".

For all other values of fw1auth-method, it is ignored. Its meaning is given below:

method	meaning
RADIUS	name of a RADIUS server, a group of RADIUS servers, or "Any"

method	meaning
TACACS	name of a TACACS server
"X" in OID	fw1template

fw1pwdLastMod

The date on which the password was last modified.

The format is yyyymmdd (for example, 20 August 1998 is 19980820).

A password can be modified through the Security Gateway as a part of the authentication process.

"X" in OID	fw1person	fw1template	default
3	У	У	If no value is given, then the password has never been modified.

fw1expiration-date

The last date on which the user can login to a Security Gateway, or "no value" if there is no expiration date.

The format is yyyymmdd (for example, 20 August 1998 is 19980820).

The default is "no value".

"X" in OID	fw1person	fw1template	default
8	у	у	"no value"

fw1hour-range-from

The time from which the user can login to a Security Gateway.

The format is hh:mm (for example, 8:15 AM is 08:15).

"X" in OID	fw1person	fw1template	default
9	у	у	"00:00"

fw1hour-range-to

The time until which the user can login to a Security Gateway.

The format is hh:mm (for example, 8:15 AM is 08:15).

"X" in OID	fw1person	fw1template	default
10	у	у	"23:59"

fw1day

The days (of week) on which the user can login to a Security Gateway.

Can have the values "SUN", "MON", and so on.

"X" in OID	fw1person	fw1template	default
11	у	у	all days of the week

fw1allowed-src

The names of one or more network objects from which the user can run a client, or "Any" to remove this limitation, or "no value" if there is no such client.

The names should match the name of network objects defined in Security Management Server.

"X" in OID	fw1person	fw1template	default
12	у	у	"no value"

fw1allowed-dst

The names of one or more network objects which the user can access, or "Any" to remove this limitation, or "no value" if there is no such network object.

The names should match the name of network objects defined on the Security Management Server.

"X" in OID	fw1person	fw1template	default
13	у	у	"no value"

fw1allowed-vlan

Not currently used.

"X" in OID	fw1person	fw1template	default
14	у	у	"no value"

fw1SR-keym

The algorithm used to encrypt the session key in SecuRemote.

Can be "CLEAR", "FWZ1", "DES", or "Any".

"X" in OID	fw1person	fw1template	default
15	у	у	"Any"

fw1SR-datam

The algorithm used to encrypt the data in SecuRemote.

Can be "CLEAR", "FWZ1", "DES", or "Any".

"X" in OID	fw1person	fw1template	default
16	у	У	"Any"

fw1SR-mdm

The algorithm used to sign the data in SecuRemote.

Can be "none" or "MD5".

"X" in OID	fw1person	fw1template	default
17	у	у	"none"

fw1enc-fwz-expiration

The number of minutes after which a SecuRemote user must re-authenticate himself or herself to the Security Gateway.

"X" in OID	fw1person	fw1template
18	у	у

fw1sr-auth-track

The exception to generate on successful authentication via SecuRemote.

Can be "none", "cryptlog", or "cryptalert".

"X" in OID	fw1person	fw1template	default
19	у	У	"none"

fw1groupTemplate

This flag is used to resolve a problem related to group membership.

The group membership of a user is stored in the group entries to which it belongs, in the user entry itself, or in both entries.

Therefore there is no clear indication in the user entry if information from the template about group relationship should be used.

If this flag is "TRUE", then the user is taken to be a member of all the groups to which the template is a member.

This is in addition to all the groups in which the user is directly a member.

"X" in OID	fw1person	fw1template	default
20	у	у	"False"

fw1ISAKMP-EncMethod

The key encryption methods for SecuRemote users using IKE.

This can be one or more of: "DES", "3DES".

A user using IKE (formerly known as ISAMP) may have both methods defined.

"X" in OID	fw1person	fw1template	default
21	у	у	"DES", "3DES"

fw1ISAKMP-AuthMethods

The allowed authentication methods for SecuRemote users using IKE, (formerly known as ISAMP).

This can be one or more of: "preshared", "signatures".

"X" in OID	fw1person	fw1template	default
22	у	у	"signatures"

fw1ISAKMP-HashMethods

The data integrity method for SecuRemote users using IKE, (formerly known as ISAMP).

This can be one or more of: "MD5", "SHA1".

A user using IKE must have both methods defined.

"X" in OID	fw1person	fw1template	default
23	у	у	"MD5", "SHA1"

fw1ISAKMP-Transform

The IPSec Transform method for SecuRemote users using IKE, (formerly known as ISAMP).

This can be one of: "AH", "ESP".

"X" in OID	fw1person	fw1template	default
24	у	у	"ESP"

fw1ISAKMP-DataIntegrityMethod

The data integrity method for SecuRemote users using IKE, (formerly known as ISAMP).

This can be one of: "MD5", "SHA1".

"X" in OID	fw1person	fw1template	default
25	у	у	"SHA1"

fw1ISAKMP-SharedSecret

The pre-shared secret for SecuRemote users using IKE, (formerly known as ISAMP).

The value can be calculated using the fw ikecrypt command line.

"X" in OID	fw1person	fw1template
26	у	у

fw1ISAKMP-DataEncMethod

fw1ISAKMP-DataEncMethod

The data encryption method for SecuRemote users using IKE, (formerly known as ISAMP).

"X" in OID	fw1person	fw1template	default
27	у	у	"DES"

fw1enc-Methods

The encryption method allowed for SecuRemote users.

This can be one or more of: "FWZ", "ISAKMP" (meaning IKE).

"X" in OID	fw1person	fw1template	default
28	у	у	"FWZ"

fw1userPwdPolicy

Defines when and by whom the password should and can be changed.

"X" in OID	fw1person
29	у

fw1badPwdCount

Number of allowed wrong passwords entered sequentially.

"X" in OID	fw1person
30	у

fw1lastLoginFailure

Time of the last login failure.

"X" in OID	fw1person
31	4

memberof template

DN of the template that the user is a member of.

"X" in OID	fw1person
33	4

Netscape LDAP Schema

To add the propriety schema to your Netscape directory server, use the \$FWDIR/lib/ldap/schema.ldif file.



R Important - This deletes the object class definition from the schema and adds the updated one in its place.

We recommend that you back up the User Directory server before you run the command.

The ldif file:

- Adds the new attributes to the schema
- Deletes old definitions of fw1person and fw1template
- Adds new definitions of fw1person and fw1template

To change the Netscape LDAP schema, run the **Idapmodify** command with the **schema.Idif** file.

Note - On some server versions, the delete objectclass operation can return an error, even if it was successful. Use ldapmodify with the -c (continuous) option.

User Directory Profiles

The User Directory profile is a configurable LDAP policy that lets you define more exact User Directory requests and enhances communication with the server.

Profiles control most of the LDAP server-specific knowledge. You can manage diverse technical solutions, to integrate LDAP servers from different vendors.

Use User Directory profiles to make sure that the user management attributes of a Security Management Server are correct for its associated LDAP server.

For example, if you have a certified OPSEC User Directory server, apply the OPSEC_DS profile to get enhanced OPSEC-specific attributes.

LDAP servers have difference object repositories, schemas, and object relations.

- The organization's user database may have unconventional object types and relations because of a specific application.
- Some applications use the cn attribute in the User object's Relatively Distinguished Name (RDN) while others use uid.
- In Microsoft Active Directory, the user attribute memberOf describes which group the user belongs to, while standard LDAP methods define the member attribute in the group object itself.
- Different servers implement different storage formats for passwords.

- Some servers are considered v3 but do not implement all v3 specifications. These servers cannot extend the schema.
- Some LDAP servers already have built in support for certain user data, while others require a Check Point schema extended attribute.

For example, Microsoft Active Directory has the accountExpires user attribute, but other servers require the Check Point attribute fwlexpirationdate, which is part of the Check Point defined fwlperson objectclass.

Some servers allow queries with non-defined types, while others do not.

Default User Directory Profiles

These profiles are defined by default:

- **OPSEC_DS** the default profile for a standard OPSEC certified User Directory.
- **Netscape_DS** the profile for a Netscape Directory Server.
- **Novell_DS** the profile for a Novell Directory Server.
- **Microsoft_AD** the profile for Microsoft Active Directory.

Modifying User Directory Profiles

Profiles have these major categories:

- **Common** Profile settings for reading and writing to the User Directory.
- **Read** Profile settings only for reading from the User Directory.
- Write Profile settings only for writing to the User Directory.

Some of these categories list the same entry with different values, to let the server behave according to type of operation. You can change certain parameters of the default profiles for finer granularity and performance tuning.

To apply a profile:

- 1. Open the Account Unit.
- 2. Select the profile.

To change a profile:

- 1. Create a new profile.
- 2. Copy the settings of a User Directory profile into the new profile.
- 3. Change the values.

Fetch User Information Effectively

User Directory servers organize groups and members through different means and relations. User Directory operations are performed by Check Point on users, groups of users, and user templates where the template is defined as a group entry and users are its members. The mode in which groups/templates and users are defined has a profound effect on the performance of some of the Check Point functionality when fetching user information. There are three different modes:

- Defining a "Member" attribute per member, or "*Member*" user-to-group membership mode. In this case, each member of a specific group gets the 'Member" attribute, where the value of this attribute is the DN of that member.
- Defining a "Memberof" attribute per group, or "*MemberOf*" user-to-group membership mode. In this case, each group gets the "Memberof" attribute per group, where the value of this attribute is the DN of a group entry. This is referred to as "*MemberOf*" user-togroup membership mode.
- Defining a "Memberof" attribute per member and group, or "*Both*" user-to-group membership mode. In this case both members and groups are given the "Memberof" attribute.

The most effective mode is the "MemberOf" and "Both" modes where users' group membership information is available on the user itself and no additional User Directory queries are necessary.

Setting User-to-Group Membership Mode

Set the user-to-group membership mode in the profile objects for each User Directory server in the $objects_5_0.c$ file.

- To specify the user-to-group and template-to-group membership mode set the GroupMembership attribute to one of the following values: "Member", "MemberOf", "Both" accordingly.
- To specify the user-to-template membership mode set the TemplateMembership attribute to one of the following values: "Member", "MemberOf" accordingly.

After successfully converting the database, set the User Directory server profile in the $objects_5_0.c$ file to the proper membership setting and start the Security Management Server.

Make sure to install policy/user database on all Security Gateways to enable the new configuration.

Profile Attributes

UserLoginAttr

The unique username User Directory attribute (uid).

In addition, when fetching users by the username, this attribute is used for query.

Default	Other
 uid (most servers) SamAccountName (in Microsoft_AD) 	One value allowed

UserPasswordAttr

This user password is User Directory attribute.

Default	Other
 userPassword (most servers) unicodePwd (in Microsoft_AD) 	One value allowed

TemplateObjectClass

The object class for Check Point User Directory templates.

If you change the default value with another object-class, make sure to extend that objectclass schema definition with relevant attributes from fwltemplate.

default	Other
fw1template	Multiple values allowed

ExpirationDateAttr

The account expiration date is User Directory attribute.

This could be a Check Point extended attribute or an existing attribute.

Default	Other
 fw1expiration-date (most servers) 	One value allowed
 accountExpires (in Microsoft_AD) 	

ExpirationDateFormat

Expiration date format.

This format will be applied to the value defined at ExpirationDateAttr.

Default	Other
CP format is yyyymmdd	One value allowed

PsswdDateFormat

The format of the password modified date is User Directory attribute.

This formation will be applied to the value defined at PsswdDateAttr.

Default	Other
 CP (most servers) format is yyyymmdd MS (in Microsoft_AD) 	One value allowed

PsswdDateAttr

The password last modified date is User Directory attribute.

Default	Other
 fw1pwdLastMod (most servers) pwdLastSet (in Microsoft_AD) 	One value allowed

BadPwdCountAttr

User Directory attribute to store and read bad password authentication count.

Default	Other
fw1BadPwdCount	One value allowed

ClientSideCrypt

If 0, the sent password will not be encrypted.

If 1, the sent password will be encrypted with the algorithm specified in the DefaultCryptAlgorithm.

Default	Other
0 for most servers1 for Netscape_DS	One value allowed
if not using encrypted password, SSL is recommended	

DefaultCryptAlgorith

The algorithm used to encrypt a password before updating the User Directory server with a new password.

CryptedPasswordPrefix

The text to prefix to the encrypted password when updating the User Directory server with a modified password.

Default	Other
{Crypt} (for Netscape_DS)	One value allowed

PhoneNumberAttr

User Directory attribute to store and read the user phone number.

Default	Other
internationalisednumber	One value allowed

AttributesTranslationMap

General purpose attribute translation map, to resolve problems related to peculiarities of different server types.

For example, an X.500 server does not allow the "-" character in an attribute name.

To enable the Check Point attributes containing "-", specify a translation entry: (e.g., "fw1-expiration =fw1expiration").

Default	Other
none	Multiple values allowed

ListOfAttrsToAvoid

All attribute names listed here will be removed from the default list of attributes included in read/write operations.

This is most useful in cases where these attributes are not supported by the User Directory server schema, which might fail the entire operation.

This is especially relevant when the User Directory server schema is not extended with the Check Point schema extension.

Default	Other
There are no values by default. In case the User Directory server was not extended by the Check Point schema, the best thing to do is to list here all the new Check Point schema attributes.	Multiple values allowed

BranchObjectClass

Use this attribute to define which type of objects (objectclass) is queried when the object tree branches are displayed after the Account Unit is opened in SmartConsole.

Default	Other
 Organization OrganizationalUnit Domain (most servers) Container (extra for Microsoft_AD) 	Multiple values allowed

BranchOCOperator

If "One" is set, an "OR"ed query will be sent and every object that matches the criteria will be displayed as a branch.

If "All" is set, an "AND"ed query will be sent and only objects of all types will be displayed.

Default	Other
One	One value allowed

OrganizationObjectClass

This attribute defines what objects should be displayed with an organization object icon.

A new object type specified here should also be in BranchObjectClass.

Default	Other
organization	Multiple values allowed

OrgUnitObjectClass

This attribute defines what objects should be displayed with an organization object icon.

A new object type specified here should also be in BranchObjectClass.

Default	Other
 organizationalUnit (most servers) Contained (added to Microsoft_AD) 	Multiple values allowed

DomainObjectClass

This attribute defines what objects should be displayed with a Domain object icon.

A new object type specified here should also be in BranchObjectClass.

Default	Other
Domain	Multiple values allowed

UserObjectClass

This attribute defines what objects should be read as user objects.

The user icon will be displayed on the tree for object types specified here.

Default	Other
 User (in Microsoft_AD) Person OrganizationalPerson	Multiple values allowed

UserOCOperator

If "One" is set, an "OR"ed query will be sent and every object that matches one of the types will be displayed as a user.

If "All" is set, an "AND"ed query will be sent and only objects of all types will be displayed.

Default	Other
One	One value allowed

GroupObjectClass

This attribute defines what objects should be read as groups.

The group icon will be displayed on the tree for objects of types specified here.

Default	Other
 Groupofnames Groupofuniquenames (most servers) Group Groupofnames (in Microsoft_AD) 	Multiple values allowed

GroupOCOperator

If "One" is set, an "OR"ed query will be sent and every object that matches one of the types will be displayed as a user.

If "All" is set, an "AND"ed query will be sent and only objects of all types will be displayed.

Default	Other
One	One value allowed

GroupMembership

Defines the relationship Mode between the group and its members (user or template objects) when reading group membership.

Default	Other
 Member mode defines the member DN in the Group object (most servers) MemberOf mode defines the group DN in the member object (in Microsoft_AD) Modes define member DN in Group object and group DN in Member object. 	One value allowed

UserMembershipAttr

Defines what User Directory attribute to use when reading group membership from the user or template object if GroupMembership mode is 'MemberOf' or 'Both' you may be required to extend the user/template object schema in order to use this attribute.

Default	Other
MemberOf	One value allowed

TemplateMembership

Defines the user to template membership mode when reading user template membership information.

Default	Other
 Member mode defines the member DN in the Group object (most servers) MemberOf mode defines the group DN in the member object (in Microsoft_AD) 	One value allowed

TemplateMembershipAttr

Defines which attribute to use when reading the User members from the template object, as User DNs, if the TemplateMembership mode is Member.

Default	Other
member	Multiple values allowed

UserTemplateMembershipAttr

Defines which attribute to use when reading from the User object the template DN associated with the user, if the TemplateMembership mode is MemberOf.

Default	Other
member	Multiple values allowed

OrganizationRDN

This value will be used as the attribute name in the Relatively Distinguished Name (RDN) when you create a new organizational unit in SmartConsole.

Default	Other
0	One value allowed

OrgUnitRDN

This value is used as the attribute name in the Relatively Distinguished Name (RDN) when you create a new organizational Unit in SmartConsole.

Default	Other
ou	One value allowed

UserRDN

This value is used as the attribute name in the Relatively Distinguished Name (RDN), when you create a new User object in SmartConsole.

Default	Other
cn	One value allowed

GroupRDN

This value is used as the attribute name for the RDN, when you create a new Group object in SmartConsole.

Default	Other
cn	One value allowed

DomainRDN

This value is used as the attribute name for the RDN, when you create a new Domain object in SmartConsole.

Default	Other
dc	One value allowed

AutomaticAttrs

This field is relevant when you create objects in SmartConsole.

The format of this field is <code>Objectclass:name:value</code>. Therefore, if the object created is of type <code>ObjectClass</code>, additional attributes is included in the created object with name 'name' and value 'value'.

Default	Other
user:userAccountControl:66048 For Microsoft_AD This means that when a user object is created an extra attribute is included automatically: userAccountControl with the value 66048	Multiple values allowed

GroupObjectClass

This field is used when you modify a group in SmartConsole.

The format of this field is **ObjectClass:memberattr** meaning that for each group objectclass there is a group membership attribute mapping.

List here all the possible mappings for this User Directory server profile.

When a group is modified, based on the group's objectclass the right group membership mapping is used.

Default	Other
 groupOfNames:member groupOfUniqueNames:uniqueMember (All other servers) 	Multiple values allowed

OrgUnitObjectClass

This determines which ObjectClass to use when creating/modifying an OrganizationalUnit object.

These values can be different from the read counterpart.

Default	Other
OrganizationalUnit	Multiple values allowed

OrganizationObjectClass

This determines which ObjectClass to use when creating and/or modifying an Organization object.

These values can be different from the read counterpart.

Default	Other
Organization	Multiple values allowed

UserObjectClass

This determines which ObjectClass to use when creating and/or modifying a user object.

These values can be different from the read counterpart.

Default	Other
 User (in Microsoft_AD) person organizationalPerson inetOrgPerson fw1Person (All other servers) 	Multiple values allowed

DomainObjectClass

Determines which ObjectClass to use when creating and/or modifying a domain context object.

These values can be different from the read counterpart.

Default	Other
Domain	Multiple values allowed

Managing Users on a User Directory Server

Managing Users on a User Directory Server

In SmartConsole, users and user groups in the Account Unit show in the same tree structure as on the LDAP server.

- To see User Directory users, open Users and Administrators. The LDAP Groups folder holds the structure and accounts of the server.
- You can change the User Directory templates. Users associated with this template get the changes immediately. If you change user definitions manually in SmartConsole, the changes are immediate on the server.

Distributing Users in Multiple Servers

The users of an organization can be distributed across several LDAP servers. Each LDAP server must be represented by a separate Account Unit.

Managing LDAP Information

User Directory lets you use SmartDashboard to manage information about users and OUs (Organizational Units) that are stored on the LDAP server.

To manage LDAP information from SmartDashboard

- 1. In SmartConsole, go to Manage & Settings > Blades.
- 2. Click Configure in SmartDashboard.

SmartDashboard opens.

- 3. From the object tree, select Servers and OPSEC.
- 4. Double-click the Account Unit.

The LDAP domain object opens.

5. Double-click the LDAP branch.

The Security Management Server queries the LDAP server and SmartDashboard shows the LDAP objects.

6. Expand the **Objects List** pane.

Example:

Managing Users on a User Directory Server

무 숙 숙 🖪 🔒 🕄 🗸 🗸	🖁 Objects List 📴 Ider	tity Awareness 🕓 SmartW	orkflow
Users and Administrators	Search is Unavailable	Q Users and A	dministrators 🔻 🚺 AD_Directory\com\checl
Access Roles	Full Name	Login Name	DN (Distinguished Name)
Administrator Groups Administrators	Julie Adams	juliea	$CN{=}Julie\;Adams,OU{=}Sales,DC{=}sample,DC$
External User Profiles	Charlie Daniels	charlied	CN=Charlie Daniels, OU=Sales, DC=sample,
DAP Groups	Steve Fields	stevef	CN=Steve Fields,OU=Sales,DC=sample,DC
Templates			
Iser Groups Research Stress			
▲ AD_Directory			
⊿ 🗇 com			
I I I I I I I I I I I I I I I I I I I			
Computers			
ForeignSecurityPrincipals			
 Program Data System 			
Users			
 System Users Domain Controllers Sales 			
Sales			

7. Double-click the LDAP object.

The **Objects List** pane shows the user information.

8. Right-click a user and select Edit.

The LDAP User Properties window opens.

9. Edit the user information and settings. Click OK.

LDAP Groups for the User Directory

Create LDAP groups for the User Directory. These groups classify users according to type and can be used in Policy rules. You can add users to groups, or you can create dynamic filters.

To create LDAP groups for User Directory

- 1. In SmartConsole, open **Object Categories > New > More > Users > LDAP group**.
- 2. In the **New LDAP Group** window that opens, select the **Account Unit** for the User Directory group.
- 3. Define Group's Scope select one of these:
 - All Account-Unit's Users All users in the group
 - Only Sub Tree Users in the specified branch
 - Only Group in branch Users in the branch with the specified DN prefix
- 4. Apply an advanced LDAP filter:

- a. Click Apply filter for dynamic group.
- b. Enter the filter criteria.
- 5. Click OK.

Examples:

- If the User objects for managers in your organization have the object class "myOrgManager", define the Managers group with the filter: objectclass=myOrgManagers
- If users in your organization have an e-mail address ending with us.org.com, you can define the US group with the filter: mail=*us.org.com

Retrieving Information from a User Directory Server

When a Security Gateway requires user information for authentication, it goes through this process:

- 1. The Security Gateway searches for the user in the *internal management database*.
- 2. If the specified user is not defined in the *internal management database*, the Security Gateway queries the *LDAP server* defined in the Account Unit with the highest priority.
- 3. If the query against an LDAP server with the highest priority fails (for example, the connection is lost), the Security Gateway queries the server with the next highest priority.

If there is more than one Account Unit, the Account Units are queried concurrently. The results of the query are taken from the first Account Unit to meet the conditions, or from all the Account Units which meet the conditions.

4. If the query against all LDAP servers fails, the Security Gateway matches the user against the generic external user profile..

Running User Directory Queries

Use queries to get User Directory user or group data. For best performance, query Account Units when there are open connections. Some connections are kept open by the Security Gateways, to make sure the user belongs to a group that is permitted to do a specified operation.

To query User Directory

- 1. In SmartConsole, go to Manage & Settings > Blades.
- 2. Click Configure in SmartDashboard.

SmartDashboard opens.

- 3. In the Objects Tree, click Users.
- 4. Double-click the Account Unit to open a connection to the LDAP server.
- 5. Right-click the Account Unit and select Query Users/Group.

The LDAP Query Search window opens.

Click **Advanced** to select specified objects types, such as Users, groups, or templates.

- 6. Define the query.
- 7. To add more conditions, select or enter the values and click Add.

Query conditions:

- Attributes Select a user attribute from the drop-down list, or enter an attribute.
- Operators Select an operator from the drop-down list.
- Value Enter a value to compare to the entry's attribute. Use the same type and format as the actual user attribute. For example, if Attribute is fw1expiration-date, then Value must be in the yyymmdd syntax.
- Free Form Enter your own query expression. See RFC 1558 for information about the syntax of User Directory (LDAP) query expressions.
- Add Appends the condition to the query (in the text box to the right of Search Method).

Example of a Query

If you create a query where:

- Attributes=mail
- Contains
- Value=Andy

The server queries the User Directory with this filter:

```
filter:(&(|(objectclass=fwlperson)(objectclass=person)
(objectclass=organizationalPerson)(objectclass=inetOrgPerson))
(|(cn=Brad)(mail=*Andy*)))
```

Querying Multiple LDAP Servers

The Security Management Server and the Security Gateways can work with multiple LDAP servers concurrently. For example, if a Security Gateway needs to find user information, and it does not know where the specified user is defined, it queries all the LDAP servers in the system. (Sometimes a Security Gateway can find the location of a user by looking at the user DN, when working with certificates.)

Account Units

An *Account Unit* represents branches of user information on one or more LDAP servers. The Account Unit is the interface between the LDAP servers and the Security Management Server and Security Gateways.

You can have a number of Account Units representing one or more LDAP servers. Users are divided among the branches of one Account Unit, or between different Account Units.

 Note - When you enable the Identity Awareness and Mobile Access Software Blade, SmartConsole opens a First Time Configuration Wizard. The Active Directory Integration window of this wizard lets you create a new AD Account Unit. After you complete the wizard, SmartConsole creates the AD object and Account Unit.

Working with LDAP Account Units

Use the **LDAP Account Unit Properties** window in SmartConsole to create a new or to edit an existing Account Unit or to create a new one manually.

To create or edit an existing LDAP Account Unit:

- Create: In the Objects tab, click New > More > User/Identity > LDAP Account unit.
 - Edit: In SmartConsole, open the Object Explorer (press the CTRL+E keys) > Users/Identities > LDAP Account Units > Right-click the LDAP Account Unit and select Edit.

The LDAP Account Unit Properties window opens.

2. Edit the settings in these tabs:

General

Configure how the Security Management Server uses the Account Unit

These are the configuration fields in the General tab:

- Name Name for the Account Unit
- Comment Optional comment
- Color Optional color associated with the Account Unit
- Profile LDAP vendor
- Domain Domain of the Active Directory servers, when the same user name is used in multiple Account Units (this value is also necessary for AD Query and SSO)
- **Prefix** Prefix for non-Active Directory servers, when the same user name is used in multiple Account Units
- Account Unit usage Select applicable options:
 - CRL retrieval The Security Management Server manages how the CA sends information about revoked licenses to the Security Gateways
 - User Management The Security Management Server uses the user information from this LDAP server (User Directory must be enabled on the Security Management Server).
 - Note LDAP SSO (Single Sign On) is only supported for Account Unit objects that use User Management.
 - Active Directory Query This Active Directory server is used as an Identity Awareness source.
 - Note This option is only available if the Profile is set to Microsoft_AD.
- Enable Unicode support Encoding for LDAP user information in non-English languages
- Active Directory SSO configuration Click to configure Kerberos SSO for Active Directory - Domain Name, Account Name, Password, and Ticket encryption method

Servers

Manage LDAP servers that are used by this Account Unit. You can add, edit, or delete LDAP server objects.

To configure an LDAP server for the Account Unit

a. To add a new server, click **Add**. To edit an existing one, select it from the table and click **Edit**.

The LDAP Server Properties window opens.

b. From the Host drop-down menu, select the server object.

If necessary, create a new SmartConsole server object:

- i. Click New.
- ii. In the **New Host** window opens, enter the settings for the LDAP server.
- iii. Click OK.
- c. Enter the login credentials and the **Default priority**.
 - Note If you create the LDAP account unit to submit group queries, no special permissions are needed.
 If you create the LDAP account unit to submit Active Directory queries, you must have the permissions provided in <u>sk93938</u>.
- d. Select access permissions for the Check Point Gateways:
 - · Read data from this server
 - · Write data to this server
- e. LDAP connections can be authenticated by using client certificates that are supplied by a trust Certificate Authority (CA). In the **Encryption** tab, configure the optional SSL encryption settings.
 - Use Encryption (SSL) lets you encrypt LDAP connections using SSL. Make sure that you enter the relevant Encryption port number.
 - Click Fetch to fetch the server name, the CA name, and the CA fingerprint.
 - Select **CRL check** to verify that the server certificate is not revoked.
 - To use certificates, the LDAP server must be configured with SSL **Strong** encryption.
- f. Click OK.

To remove an LDAP server from the Account Unit:

- a. Select a server from the table.
- b. Click Remove.

If all the configured servers use the same login credentials, you can modify those simultaneously.

To configure the login credentials for all the servers simultaneously:

a. Click Update Account Credentials.

The Update Account to All Servers window opens.

- b. Enter the login credentials.
- c. Click OK.

Objects Management

Configure the LDAP server for the Security Management Server to query and the branches to use

Note - Make sure there is LDAP connectivity between the Security Management Server and the LDAP Server that holds the management directory.

To configure LDAP query parameters:

- a. From the **Manage objects on** drop-down menu, select the LDAP server object.
- b. Click Fetch branches.

The Security Management Server queries and shows the LDAP branches.

- c. Configure Branches in use:
 - To add a branch, click **Add** and in the LDAP Branch Definition window that opens, enter a new **Branch Path**
 - To edit a branch, click **Edit** and in the LDAP Branch Definition window that opens, modify the **Branch Path**
 - To delete a branch, select it and click Delete
- d. Select **Prompt for password when opening this Account Unit**, if necessary (optional).
- e. Configure the number of **Return entries** that are stored in the LDAP database (the default is 500).

Authentication

Configure the authentication scheme for the Account Unit. These are the configuration fields in the Authentication tab:

- Use common group path for queries Select to use one path for all the LDAP group objects (only one query is necessary for the group objects)
- Allowed authentication schemes Select one or more authentication schemes allowed to authenticate users in this Account Unit - Check Point Password, SecurID, RADIUS, OS Password, or TACACS
- Users' default values The default settings for new LDAP users:
 - User template Template that you created
 - Default authentication scheme one of the authentication schemes selected in the Allowed authentication schemes section
- Limit login failures (optional):
 - Lock user's account after Number of login failures, after which the account gets locked
 - Unlock user's account after Number of seconds, after which the locked account becomes unlocked
- IKE pre-shared secret encryption key Pre-shared secret key for IKE
 users in this Account Unit
- 3. Click OK.
- 4. Install the Access Control Policy.

Configuring LDAP query parameters

- 1. From the Manage objects on drop-down menu, select the LDAP server object.
- 2. Click Fetch branches.

The Security Management Server queries and shows the LDAP branches.

- 3. Configure Branches in use:
 - To add a branch, click Add and in the LDAP Branch Definition window that opens, enter a new Branch Path
 - To edit a branch, click Edit and in the LDAP Branch Definition window that opens, modify the Branch Path
 - To delete a branch, select it and click Delete
- 4. Select **Prompt for password when opening this Account Unit**, if necessary (optional).

5. Configure the number of **Return entries** that are stored in the LDAP database (the default is 500).

Modifying the LDAP Server

1. On the LDAP Account Unit Properties > Servers tab, double-click a server.

The LDAP Server Properties window opens.


- 2. On the General tab, you can change:
 - Port of the LDAP server
 - Login DN
 - Password
 - Priority of the LDAP server, if there are multiple servers
 - Security Gateway permissions on the LDAP server
- 3. On the **Encryption** tab, you can change the encryption settings between Security Management Server / Security Gateways and LDAP server.

If the connections are encrypted, enter the encryption port and strength settings.

 Note - User Directory connections can be authenticated by client certificates from a Certificate Authority (CA). To use certificates, the LDAP server must be configured with SSL strong authentication. See "Authenticating with Certificates" on the next page.

Account Units and High Availability

With User Directory replications for High Availability, one Account Unit represents all the replicated User Directory servers. For example, two User Directory server replications can be defined on one Account Unit, and two Security Gateways can use the same Account unit.



Item	Description
1	Security Management Server. Manages user data in User Directory. It has an Account Unit object, where the two servers are defined.
2	User Directory server replication.
3	Security Gateway . Queries user data and retrieves CRLs from nearest User Directory server replication (2).
4	Internet
5	Security Gateway . Queries user data and retrieves CRLs from nearest User Directory server replication (6).
6	User Directory server replication.

Setting High Availability Priority

With multiple replications, define the priority of each LDAP server in the Account Unit. Then you can define a server list on the Security Gateways.

Select one LDAP server for the Security Management Server to connect to. The Security Management Server can work with one LDAP server replication. All other replications must be synchronized for standby.

To set priority on the Account Unit

- 1. Open the LDAP Account Unit Properties window.
- 2. Open the Servers tab.
- 3. Add the LDAP servers of this Account Unit in the order of the priority that you want.

Authenticating with Certificates

The Security Management Server and Security Gateways can use certificates to secure communication with LDAP servers. If you do not configure certificates, the management server, Security Gateways, and LDAP servers communicate without authentication.

To configure User Directory to use certificates

- 1. Close all SmartConsole windows connected to the Management Server.
- 2. On each Account Unit, to which you want to authenticate with a certificate, set the ldap use cert auth attribute to true:

- a. Connect with *Database Tool (GuiDBEdit Tool)* to the Management Server.
- b. In the left pane, browse to **Table > Managed Objects > servers**.
- c. In the right pane, select the Account Unit object.
- d. In the bottom pane, search for the ldap_use_cert_auth attribute, and set it to true.
- e. Save the changes and close Database Tool (GuiDBEdit Tool).
- 3. Connect with SmartConsole to the Management Server.
- 4. Add a CA object:
 - a. In the Object Explorer (F11), click New > More > Server > More > Trusted CA.
 The Certificate Authority Properties window opens.
 - b. In Certificate Authority Type, select External Check Point CA.
 - c. Set the other options of the CA.
- 5. For all necessary network objects (such as Security Management Server, Security Gateway, Policy Server) that require certificate-based User Directory connections:
 - a. On the **IPSec VPN** page of the network object properties, click **Add** in the **Repository of Certificates Available** list.
 - Note A management-only server does not have an IPSec VPN page. The User Directory on a management-only server cannot be configured to authenticate to an LDAP server using certificates.
 - b. In the Certificate Properties window, select the defined CA.
- 6. Test connectivity between the Security Management Server and the LDAP Server.

See "Managing LDAP Information" on page 203.

Configuring Users on an External LDAP Server

LDAP is an external identity integration technology supported by Check Point Quantum.

An LDAP provides these capabilities:

- The Security Gateway can use the LDAP data to authenticate and authorize users.
- The Security Gateway can retrieve CRLs when using certificate information.

Other identity integration options include: Check Point Quantum management internal user database, Entra ID, and Check Point Infinity Identity.

Microsoft Active Directory

For an overview of Microsoft Active Directory, see Active Directory Domain Services.

The branch CN=Schema, CN=Configuration, DCROOT contains all schema definitions.

Check Point can take advantage of an existing Active Directory object as well as add new types. For users, the existing user can be used "as is" or be extended with fwlperson as an auxiliary of "User" for full feature granularity. The existing Active Directory "Group" type is supported "as is". A User Directory template can be created by adding the fwltemplate object-class. This information is downloaded to the directory using the schema_microsoft_ad.ldif file (see "Adding New Attributes to the Active Directory" on page 219).

Performance

For certain Software Blades, the information which is related to the Active Directory group-is stored in the user object. Therefore, when fetching the user object, no additional query is necessary in order to assign the group to the user. The same is true for users and templates. In some cases, The Security Gateway sends additional queries. See <u>sk128212</u>.

Manageability

SmartDashboard allows the creation and management of existing and new objects. However, some specific Active Directory fields are not enabled in SmartDashboard.

Enforcement

You can work with the existing Active Directory objects without extending the schema. This is made possible by defining an Internal Template object and assigning to it the User Directory Account Unit defined on the Active Directory server.

For example, if you wish to enable all users with IKE+Hybrid based on the Active Directory passwords, create a new template with the IKE properties enabled and "Check Point password" as the authentication method.

Updating the Registry Settings

To modify the Active Directory schema, add a new registry DWORD key named Schema Update Allowed with the value different from zero under HKLM\System\CurrentControlSet\Services\NTDS\Parameters.

Delegating Control

Delegating control over the directory to a specific user or group is important because by default the system administrator is not allowed to modify the schema or even manage directory objects through User Directory protocol.

To delegate control over the directory

- 1. On the Domain Controller, open the Active Directory **Users and Computers Control** console.
- 2. Right-click the domain name displayed in the left pane and select **Delegate control** from the right-click menu.

The **Delegation of Control wizard** window is displayed.

- 3. Add a user or a group to the list of users who can control the directory.
- 4. Reboot the machine.

Extending the Active Directory Schema

Modify the file with the Active Directory schema, to use SmartConsole to configure the Active Directory users.

To extend the Active Directory schema

- 1. From the Security Gateway, go to the directory of the schema file: \$FWDIR/lib/ldap.
- 2. Copy schmea_microsoft_ad.ldif to the C:\ drive in the Active Directory server.
- 3. From Active Directory server, with a text editor open the schema file.
- 4. Find the value DOMAINNAME, and replace it with the name of your domain in LDIF format.

For example, the domain sample.checkpoint.com in LDIF format is: DC=sample, DC=checkpoint, DC=com

5. Make sure that there is a dash character – at the end of the modify section.

This is an example of the modify section.

```
dn: CN=User,CN-
Schema,CN=Configuration,DC=sample,DC=checkpoint,DC=com
changetype: modify
add: auxiliaryClass
auxiliaryClass: 1.3.114.7.3.2.0.2
-
```

6. Run:

ldifde -i -f c:/schema_microsoft_ad.ldif

Adding New Attributes to the Active Directory

Below is an example in LDAP Data Interchange (LDIF) format which shows how to add one attribute to the Microsoft Active Directory:

```
dn:CN=fw1auth-method,CN=Schema,CN=Configuration,DCROOT
changetype: add
adminDisplayName: fwlauth-method
attributeID: 1.3.114.7.4.2.0.1
attributeSyntax: 2.5.5.4
cn: fwlauth-method
distinguishedName:
CN=fwlauth-method, CN=Schema, CN=Configuration, DCROOT
instanceType: 4
isSingleValued: FALSE
LDAPDisplayName: fwlauth-method
name: fwlauth-method
objectCategory:
CN=Attribute-
Schema, CN=ConfigurationCN=Schema, CN=Configuration, DCROOT
ObjectClass: attributeSchema
oMSyntax: 20
rangeLower: 1
rangeUpper: 256
showInAdvancedViewOnly: TRUE
```

You can add all Check Point attributes in the same way.

The definitions of all attributes in LDIF format are contained in the schema_microsoft_ ad.ldif file located in the \$FWDIR/lib/ldap directory.

Before attempting to run the ldapmodify command, edit schema_microsoft_ad.ldif and replace all instances of DCROOT with the domain root of your organization. For example, if your domain is support.checkpoint.com, replace DCROOT with dc=support,dc=checkpoint,dc=com. After modifying the file, run the ldapmodify command to load the file into the directory. For example if you use the system administrator account of the dc=support,dc=checkpoint,dc=com domain, the command syntax will be as follows:

Note - A shell script is available for UNIX gateways. The script is at: \$FWDIR/lib/ldap/update schema microsoft ad

ldapmodify -c -h support.checkpoint.com -D cn=administrator, cn=users, dc=support, dc=checkpoint, dc=com" -w SeCrEt -f \$FWDIR/lib/ldap/schema microsoft ad.ldif

Updating the user or service account password to the LDAP account unit on the Active Directory

Security Gateways authenticate to the LDAP server using the LDAP server user name and password saved in the SmartConsole LDAP account unit. After establishing a connection to the LDAP server from a Security Gateway, the Security Gateway reuses this connection to transmit subsequent LDAP queries without undergoing reauthentication.

If you update the password in the Active Directory on the LDAP server, you must do these steps for the changes to apply:

- 1. Update the information in the LDAP account unit.
- 2. Install policy.

Managing Gateways

This section describes how to create, update, and manage Security Gateways, and to use Secure Internal Communication (SIC) methods for Check Point platforms and products to authenticate each other.

Secure Internal Communication (SIC)

Check Point platforms and products authenticate each other through one of these Secure Internal Communication (SIC) methods:

- Certificates.
- Standards-based TLS for the creation of secure channels.
- Encryption.

SIC creates trusted connections between Security Gateways, management servers and other Check Point components. Trust is required to install polices on Security Gateways and to send logs between Security Gateways and management servers.

Note - To see SIC errors, examine the \$CPDIR/log/sic_info.elg file on the Security Management Server and on the Security Gateway.

Initializing Trust

To establish the initial trust, a Security Gateway and a Security Management Server use a one-time password. After the initial trust is established, further communication is based on security certificates.

Note - Make sure the clocks of the Security Gateway and Security Management Server are synchronized, before you initialize trust between them. This is necessary for SIC to succeed. To set the time settings of the Security Gateway and Security Management Server, go to the Gaia Portal > System Management > Time.

To initialize Trust

- 1. In SmartConsole, open the Security Gateway network object.
- 2. In the General Properties page of the Security Gateway, click Communication.
- 3. In the **Communication** window, enter the **Activation Key** that you created during installation of the Security Gateway.
- 4. Click Initialize.

The ICA signs and issues a certificate to the Security Gateway.

Trust state is **Initialized but not trusted**. The Internal Certificate Authority (ICA) issues a certificate for the Security Gateway, but does not yet deliver it.

The two communicating peers authenticate over SSL with the shared Activation Key. The certificate is downloaded securely and stored on the Security Gateway. The Activation Key is deleted.

The Security Gateway can communicate with Check Point hosts that have a security certificate signed by the same ICA.

SIC Status

After the Security Gateway receives the certificate issued by the ICA, the SIC status shows if the Security Management Server can communicate securely with this Security Gateway:

- Communicating The secure communication is established.
- Unknown There is no connection between the Security Gateway and Security Management Server.
- Not Communicating The Security Management Server can contact the Security Gateway, but cannot establish SIC. A message shows more information.


Trust State

If the Trust State is compromised (keys were leaked, certificates were lost) or objects changed (user leaves, open server upgraded to appliance), reset the Trust State. When you reset Trust, the SIC certificate is revoked.

The Certificate Revocation List (CRL) is updated for the serial number of the revoked certificate. The ICA signs the updated CRL and issues it to all Security Gateways during the next SIC connection. If two Security Gateways have different CRLs, they cannot authenticate.

- 1. In SmartConsole, from the Gateways & Servers view, double-click the Security Gateway object.
- 2. Click Communication.
- 3. In the Trusted Communication window that opens, click Reset.
- 4. Install Policy on the Security Gateways.

This deploys the updated CRL to all Security Gateways. If you do not have a Rule Base (and therefore cannot install a policy), you can reset Trust on the Security Gateways.



Troubleshooting SIC

If SIC fails to Initialize:

- 1. Make sure there is connectivity between the Security Gateway and Security Management Server.
- 2. Make sure that the Security Management Server and the Security Gateway use the same SIC activation key (one-time password).
- 3. If the Security Management Server is behind a gateway, make sure there are rules that allow connections between the Security Management Server and the remote Security Gateway. Make sure Anti-spoofing settings are correct.
- 4. Make sure the name and the IP address of the Security Management Server are in the /etc/hosts file on the Security Gateway.

If the IP address of the Security Management Server mapped through static NAT by its local Security Gateway, add the public IP address of the Security Management Server to the /etc/hosts file on the remote Security Gateway. Make sure the IP address resolves to the server's hostname.

- 5. Make sure the date and the time settings of the operating systems are correct. If the Security Management Server and remote the Security Gateway reside in different time zones, the remote Security Gateway may have to wait for the certificate to become valid.
- 6. Try to establish SIC again.

Remote User access to resources and Mobile Access

If you install a certificate on a Security Gateway that has the Mobile Access Software Blade already enabled, you must install the policy again. Otherwise, remote users will not be able to reach network resources.

To establish a new trust state for a Security Gateway

- 1. Open the command line interface on the Security Gateway.
- 2. Run:

cpconfig

- 3. Enter the number for Secure Internal Communication and press Enter.
- 4. Enter **y** to confirm.
- 5. Enter and confirm the activation key.
- 6. When done, enter the number for **Exit**.
- 7. Wait for Check Point processes to stop and automatically restart.

In SmartConsole:

- 1. In the General Properties window of the Security Gateway, click Communication.
- 2. In the **Trusted Communication** window, enter the one-time password (activation key) that you entered on the Security Gateway.
- 3. Click Initialize.
- 4. Wait for the Certificate State field to show Trust established.
- 5. Click OK.

Understanding the Check Point Internal Certificate Authority (ICA)

The ICA (Internal Certificate Authority) is created on the Security Management Server when you configure it for the first time. The ICA issues certificates for authentication:

- Secure Internal Communication (SIC) Authenticates communication between Security Management Servers, and between Security Gateways and Security Management Servers.
- VPN certificates for gateways Authentication between members of the VPN community, to create the VPN tunnel.
- Users For strong methods to authenticate user access according to authorization and permissions.

ICA Clients

In most cases, certificates are handled as part of the object configuration. To control the ICA and certificates in a more granular manner, you can use one of these ICA clients:

- The Check Point Configuration Tool This is the cpconfig CLI utility. One of the options creates the ICA, which issues a SIC certificate for the Security Management Server.
- SmartConsole SIC certificates for Security Gateways and administrators, VPN certificates, and user certificates.
- "The ICA Management Tool" on page 639 VPN certificates for users and advanced ICA operations.

See audit logs of the ICA in SmartConsole Logs & Events > New Tab > Open Audit Logs View.

SIC Certificate Management

Manage SIC certificates in:

- Communication tab of the Security Gateway properties window.
- "The ICA Management Tool" on page 639.

Certificates have these configurable attributes:

Attributes	Default	Comments
validity	5 years	
key size	2048 bits	
KeyUsage	5	Digital Signature and Key encipherment
ExtendedKeyUsage	0 (no KeyUsage)	VPN certificates only

To learn more about key size values, see <u>RSA key lengths</u>.

To view license information for each Software Blade

Step	Instructions
1	Select a Security Gateway or a Security Management Server.
2	In the Summary tab below, click the object's License Status (for example: OK). The Device & License Information window opens. It shows basic object information and License Status , license Expiration Date , and important quota information (in the Additional Info column) for each Software Blade. Notes:
	 Quota information, quota-dependent license statuses, and blade information messages are only supported for R80 and higher. The tooltip of the SKU is the product name.

The possible values for the Software Blade License Status are:

Status	Description
Active	The Software Blade is active and the license is valid.
Available	The Software Blade is not active, but the license is valid.
No License	The Software Blade is active but the license is not valid.
Expired	The Software Blade is active, but the license expired.
About to Expire	The Software Blade is active, but the license will expire in thirty days (default) or less (7 days or less for an evaluation license).

Status	Description
Quota Exceeded	The Software Blade is active, and the license is valid, but the quota of related objects (Security Gateways, Virtual Systems, files, and so on, depending on the blade) is exceeded.
Quota Warning	The Software Blade is active, and the license is valid, but the number of objects of this blade is 90% (default) or more of the licensed quota.
N/A	The license information is not available.

Creating a New Security Gateway

A Security Gateway enforces security policies configured on the Security Management Server.

To install security policies on the Security Gateway, configure the Security Gateway object in SmartConsole.

To define a new Security Gateway object

- 1. From the navigation toolbar, select Gateways & Servers.
- 2. Click New, and select Gateway.

The Check Point Security Gateway Creation window opens.

3. Click Classic Mode.

The **Check Point Gateway** properties window opens and shows the **General Properties** screen.

- 4. Enter the host Name and the IPv4 Address or IPv6 Address.
- 5. Click Communication.

The Trusted Communication window opens.

6. Select a Platform.

Important - Make sure to select the correct Appliance model. Otherwise, policy installation may fail.

7. In the Authentication section, enter and confirm the One-time password.

If you selected **Small Office Appliance** platform, make sure **Initiate trusted** communication automatically when the Gateway connects to the Security Management Server for the first time is selected. 8. Click **Initialize** to establish trusted communication with the Security Gateway (see *"Secure Internal Communication (SIC)" on page 221*).

If trust fails to establish, click **OK** to continue configuring the Security Gateway.

- 9. Click OK.
- 10. The **Get Topology Results** window that opens, shows interfaces successfully configured on the Security Gateway.
- 11. Click Close.
- 12. In the Platform section, select the Hardware, the Version, and the OS.

If trust is established between the server and the Security Gateway, click **Get** to automatically retrieve the information from the Security Gateway.

13. Select the Software Blades to enable on the Security Gateway.

For some of the Software Blades a first-time setup wizard will open. You can run the wizard now or later. For more on the setup wizards, see the relevant Administration Guide.

1 Note - You cannot add additional information fields to the Security Gateway object.

Manually Updating the Gateway Topology

As the network changes, you must update the Security Gateway topology.

To update the Security Gateway topology

- 1. In SmartConsole, click Gateways & Servers.
- 2. Double-click the Security Gateway object.

The Security Gateway property window opens.

- 3. Click Network Management.
- 4. Click Get Interfaces and select the applicable option:
 - Get Interfaces With Topology

A warning window asks if you want to overwrite the existing Topology and Anti-Spoofing settings.

Click Yes.

- Note The physical interfaces that are part of a Bridge interface always appear with the topology "Undefined". Workaround: Use the API command "get-interfaces".
- Get Interfaces Without Topology
- 5. The Get Topology Results window opens.
- 6. Click Accept.
- 7. Configure the applicable Topology and Anti-Spoofing settings for the interfaces.
- 8. Click OK.
- 9. Install the Access Control Policy.

Get Interfaces API

You can use the Check Point API to execute the Get Interfaces command.

The Get Interfaces API:

- Supports a larger number of interfaces compared with SmartConsole.
- Supports these interfaces which are not supported by SmartConsole: Bridge and Bond interfaces without IP addresses.
- Configures the default topology for internal networks for Security Gateway and ClusterXL R80.20 and higher to Network defined by routes, where applicable (the default in SmartConsole is This network (Internal)).
- Does not get unnecessary Bridge and Bond satellite interfaces.

The Get Interfaces API command only supports Security Gateways and ClusterXL that run on Gaia operating system.

For explanations on how to use the API Get Interfaces command, see the <u>Check Point</u> Management API Reference.

Dynamically Updating the Security Gateway Topology

When selected, the range of IP addresses behind the internal interface is automatically calculated every second (default value) without the need for the administrator to click **Get Interfaces** and install a policy.

To configure dynamic topology updates

- 1. Open Gateway Properties > Network Management.
- 2. Select an interface and click Edit.
- 3. In the Topology section, click Modify.
- 4. In the Leads To section, select Network defined by routes.
- 5. Click OK.

This default update value is configured in **SmartConsole > Preferences** and set to one second. The value set here applies to all internal interfaces for all gateways in the Domain.

To set the update value for a specific interface

- 1. Open Gateway Properties > Network Management.
- 2. Select an interface and click Actions > Settings.
- 3. Select Use custom update time (seconds) and set the applicable update time.
- 4. Click OK.

Dynamic Anti-Spoofing

When Anti-Spoofing is selected and you click **Get interfaces**, the Security Gateway generates a list of valid IP addresses based on the IP address and netmask of the interface and the routes assigned to the interface.

Anti-Spoofing drops packets with a source IP address that does not belong to the network behind the packet's interface. For example, packets with an internal IP address that comes from an external interface.

When the **Network defined by routes** option is selected along with **Perform Anti-Spoofing based on interface topology**, you get *Dynamic Anti-Spoofing*. The valid IP addresses range is automatically calculated without the administrator having to do click **Get Interfaces** or install a policy.

Managing Licenses

After you run the First Time Configuration Wizard on a Security Management Server, and the Security Management Server connects to the User Center, it automatically activates its license . If the Security Management Server loses Internet connectivity before the license is activated, it tries again, on an interval.

If you make changes to Management Software Blade licenses of a Security Management Server in the Check Point User Center, these changes are automatically synchronized with that Security Management Server.

Notes:

- Automatic activation is supported on Check Point appliances only.
- Automatic synchronization is supported on all R80.30 servers and higher.

To make sure that your environment is synchronized with the User Center, even when the Security Management Server is not connected to the Internet, we recommend that you configure a Check Point server with Internet connectivity as a proxy.

Managing Server and Gateway Licenses

Starting from R81, you can add or remove licenses manually in SmartConsole.

Adding and removing a license

Step	Instructions
1	In SmartConsole, from the left navigation panel, click Gateways & Servers.
2	In the top pane, select the object of the applicable Management Server or Security Gateway.
3	In the bottom pane, click the Licenses tab.
4	 Add or remove a license: To add a license from a license file: a. Click Add and select License File. b. Browse for the license file. c. Select the license file. d. Click Open. To add a license from a license string: a. Click Add and select License String. b. Paste the license string. c. Click OK. To remove a license: a. Select the license in the leftmost column. b. Click Remove.

Note - To add or remove licenses on the Licenses tab, an administrator must have the Run One Time Script permission selected in their profile. To assign this permission, in SmartConsole, go to Manage & Settings > Permissions & Administrators > Permission Profiles. Open the relevant permission profile, go to Gateways > Scripts, and select Run One-Time Scripts.

See also "Assigning Permission Profiles to Administrators" on page 115

You can see these columns with license information:

Column	Description
IP Address	The IP address, for which this license was generated.
Expiration Date	Date when the Check Point support contract expires.
СК	Unique Certificate Key of the license instance.
SKU	Catalog ID from the Check Point User Center.

Note - SmartConsole R81 and higher does not support viewing a license of Quantum Spark appliances with Gaia Embedded OS (in the "Gateways & Servers" view, select the Security Gateway object > in the bottom pane, click the "Licenses" tab).

Workaround: Use SmartUpdate to view the licenses.

Important - To distribute licenses to CloudGuard laaS Security Gateways, see the *R82 CloudGuard Controller Administration Guide*.

Viewing Licenses in SmartConsole

To view license information

Step	Instructions
1	From the left navigation panel, click Gateways & Servers.
2	From the Columns drop-down list, select Licenses.

You can see these columns:

Column	Description
License Status	 The general state of the Software Blade licenses: OK - All the blade licenses are valid. Not Activated - Blade licenses are not installed. This is only possible in the first 15 days after the establishment of the SIC with the Security Management Server. After the initial 15 days, the absence of licenses will result in the blade error message. Error with <number> blade(s) - The specified number of blade licenses are not installed or not valid.</number> Warning with <number> blade(s) - The specified number of blade licenses have warnings.</number> N/A - No available information.
СК	Unique Certificate Key of the license instance.
SKU	Catalog ID from the Check Point User Center.
Account ID	User's account ID.
Support Level	Check Point level of support.
Support Expiration	Date when the Check Point support contract expires.

To view license information for each Software Blade

Step	Instructions
1	Select a Security Gateway or a Security Management Server.

Step	Instructions
2	In the Summary tab below, click the object's License Status (for example: OK). The Device & License Information window opens. It shows basic object information and License Status , license Expiration Date , and important quota information (in the Additional Info column) for each Software Blade. Notes:
	 Quota information, quota-dependent license statuses, and blade information messages are only supported for R80 and higher. The tooltip of the SKU is the product name.

The possible values for the Software Blade License Status are:

Status	Description
Active	The Software Blade is active and the license is valid.
Available	The Software Blade is not active, but the license is valid.
No License	The Software Blade is active but the license is not valid.
Expired	The Software Blade is active, but the license expired.
About to Expire	The Software Blade is active, but the license will expire in thirty days (default) or less (7 days or less for an evaluation license).
Quota Exceeded	The Software Blade is active, and the license is valid, but the quota of related objects (Security Gateways, files, virtual systems, and so on, depending on the blade) is exceeded.
Quota Warning	The Software Blade is active, and the license is valid, but the number of objects of this blade is 90% (default) or more of the licensed quota.
N/A	The license information is not available.

Viewing license information for VSX

SmartConsole reports an error when viewing licenses of Virtual System or Virtual Router objects.

To see the VSX license information:

Select the VSX Gateway or VSX Cluster object (and not objects of Virtual Systems or Virtual Routers).

Monitoring Licenses in SmartConsole

To keep track of license issues, you can use these options:

Option	Description
License Status view	To see and export license information for Software Blades on each specific Security Management Server, Security Gateway, or Log Server object.
License Status report	To see filter and export license status information for all configured Security Management Server, Security Gateway, or Log Server objects.
License Inventory report	To see filter and export license information for Software Blades on all configured Security Management Server, Security Gateway, or Log Server objects.

The SmartEvent Software Blade lets you customize the License Status and License Inventory information from the Logs & Events view of SmartConsole.

It is also possible to view license information from the **Gateways & Servers** view of SmartConsole without enabling the SmartEvent blade on Security Management Server.

The Gateways & Servers view in SmartConsole lets you see and export the *License Inventory* report.

Step	Instructions
1	 View the License Inventory report from the Gateways & Servers view: 1. In SmartConsole, from the left navigation panel, click Gateways & Servers. 2. From the top toolbar, click Actions > License Report. 3. Wait for the SmartView to load and show this report. By default, this report contains: Inventory page: Blade Names, Devices Names, License Statuses License by Device page: Devices Names, License statuses, CK, SKU, Account ID, Support Level, Next Expiration Date
2	 Export the License Inventory report from the Gateways & Servers view: 1. In the top right corner, click the Options button. 2. Select the applicable export option - Export to Excel, or Export to PDF.

The Logs & Events view in SmartConsole lets you see, filter and export the *License Status* report.

Step	Instructions							
1	 View License Status report from the Logs & Events view: 1. In SmartConsole, from the left navigation panel, click Logs & Events 2. At the top, open a new tab by clicking New Tab, or [+]. 3. In the left section, click Views. 4. In the list of reports, double-click License Status. 5. Wait for the SmartView to load and show this report. By default, this report contains: Names of the configured objects, License status for each object, CK, SKU, Account ID, Support Level, Next Expiration Date 							
2	 Filter the License Status report in the Logs & Events view: In the top right corner, click the Options button > View Filter. The Edit View Filter window opens. Select a Field to filter results. For example, Device Name, License Status, Account ID. Select the logical operator - Equals, Not Equals, or Contains. Select or enter a filter value. Note - Click the X icon to delete a filter. Optional: Click the + icon to configure additional filters. Click OK to apply the configured filters. The report is filtered based on the configured filters. 							
3	 Export the License Status report in the Logs & Events view: 1. In the top right corner, click the Options button. 2. Select the applicable export option - Export to Excel, or Export to PDF. 							

The Logs & Events view in SmartConsole lets you see, filter and export the <i>License</i>
Inventory report.

Step	Instructions							
1	View the License Inventory report from the Logs & Events view:							
	 In SmartConsole, from the left navigation panel, click Logs & Events At the top, open a new tab by clicking New Tab, or [+]. In the left section, click Reports. In the list of reports, double-click License Inventory. Wait for the SmartView to load and show this report. By default, this report contains: Inventory page: Blade Names, Devices Names, License Statuses License by Device page: Devices Names, License statuses, CK, SKU, Account ID, Support Level, Next Expiration Date 							
2	Filter the License Inventory report in the Logs & Events view:							
	 In the top right corner, click the Options button > Report Filter. The Edit Report Filter window opens. Select a Field to filter results. For example, Blade Name, Device Name, License Overall Status, Account ID. Select the logical operator - Equals, Not Equals, or Contains. Select or enter a filter value. Note - Click the X icon to delete a filter. Optional: Click the + icon to configure additional filters. Click OK to apply the configured filters. The report is filtered based on the configured filters. 							
3	Export the License Inventory report in the Logs & Events view:							
	 In the top right corner, click the Options button. Select the applicable export option - Export to Excel, or Export to PDF. 							

License or Quota Changes

The SmartConsole GUI client is not aware of license or quota changes in real time. As a result, the alert for 'License quota Exceeded' does not pop up immediately when the license quota is exceeded on the Security Management Server.

To see the license changes:

- 1. Connect with SmartConsole to the Security Management Server.
- 2. From the left navigation panel, click Logs & Events.

- 3. From the top, click [+] to open a new tab.
- 4. Open the **Compliance** view (for more information, see <u>sk120256 ATRG: Compliance</u> <u>Blade (R80.10 and higher)</u>).

Changes in quota data in the entitlement or compliance are updated after:

- Compliance midnight scan
- License changes
- Running the 'cpstop ; cpstart' commands on the Security Management Server

Security Gateway Indicators

An administrator manages multiple Security Gateways in SmartConsole. The Security Gateway indicators feature in the Gateways & Servers view helps the administrator verify which Jumbo Hotfix Accumulators are installed and ensure all Security Gateways are up to date with the recommended versions.

In the Gateways & Servers view, the **Version** column displays the current Jumbo Hotfix Accumulator installed on each Security Gateway. When you hover over the **Version** column, if the currently installed Jumbo Hotfix Accumulator is not recommended, a message appears suggesting the recommended Jumbo Hotfix Accumulator for installation.

The Version column shows an indicator based on the Security Gateway status:

- No color indicator:
 - The Security Gateway is updated. The latest Jumbo Hotfix Accumulator is installed on the Security Gateway.
 - The Jumbo Hotfix Accumulator installed on Security Gateway is not the latest. A message appears suggesting the recommended Jumbo Hotfix Accumulator for installation.
- Yellow color indicator The Jumbo Hotfix Accumulator take is too old, and requires upgrading to the recommended Jumbo Hotfix Accumulator.
- **Red color indicator** The version installed on the Security Gateway is unsupported.
- Gray color indicator There is no available information about the Security Gateway. A gray indicator appears in these cases:
 - The Security Gateway is of a version of take that do not support the feature.
 - The Security Gateway is not connected to the Check Point Download Center for at least a month.
 - The Check Point Download Center does not allow updates on the Security Gateway.
 - The Security Gateway has no license or contract.

For a list of indicator exceptions, see <u>sk182159</u>.

The Security Gateway indicators also appear in the **Summary** tab for each Security Gateway at the bottom of the Gateways & Servers view.

You can filter the Gateways & Servers view based on the Gateway indicators. To do so, go to the top toolbar menu, select the filter icon **Y**, and then select **version warning**. From the available options, you can select:

- None Security Gateways with no color indicator
- Unsupported Security Gateways with a red color indicator
- Alert Security Gateways with a yellow color indicator
- N/A Security Gateways with a gray color indicator

Notes:

- Indications for Cluster Members show for each Cluster Member independently and not for the Security Cluster object.
- Upgrading a VSX Gateway also upgrades all related Virtual Gateways.

Installing the Recommended Take on the Security Gateway

When you hover over the Security Gateway, a message appears indicating the Jumbo Hotfix Accumulator to install on the Security Gateway.

To postpone the installation date Jumbo Hotfix Accumulator on the Security Gateway

1. Click the **Options** button in the message.

A window opens with the name of the recommended Jumbo Hotfix Accumulator take number.

SmartConsole					
Ignore R81.20 J	Jumbo Hotfix Take 41 update				
Remind me in	1 week 👻				
Apply to all g	gateways and servers OK Cancel				

- In this window you can set a reminder for a future installation date. Select the required future rescheduling time from the drop-down menu. If you select the Apply to all gateways and servers checkbox, the reminder is set to all Security Gateways and servers to which the Hotfix applies.
- 3. Click OK.

The indicator turns off on all relevant Security Gateways and servers.

To install the recommended Jumbo Hotfix Accumulator on the Security Gateway

1. Click the **Open Installation Window** button.

The Install Jumbo/Hotfix window opens.

- 2. In the Hotfix/Jumbo section, select one of these options:
 - Install the Recommended Hotfix/Jumbo

or

Install a Specific Hotfix/Jumbo

- a. Enter the version number / Hotfix file name.
- b. Click the search icon next to the text box.

This process makes sure that the package is available for download from the Check Point servers.

3. In the Gateways section, see the Security Gateway that you selected for this installation.


Note - To install the package on more than one Security Gateway or Cluster Member, go to the Gateways & Servers view, press and hold the CTRL key to select all the required Security Gateways and Cluster Members. Then, from the top toolbar menu, click Actions and select Install Jumbo/Hotfix.

- 4. In the **Settings** section, select the applicable option for the High Availability cluster:
 - Install on all cluster members Installs the selected package on all members in this cluster (active and standby). This can cluster failover and interrupt the traffic.
 - Install on non-active members only Installs the selected package only on standby cluster members.
 - Once installation is complete, turn non-active member to active Changes the cluster state of a standby cluster member to active.
- 5. In the Download package timing section Select this check box if you want to download the package during the verification process: Download/Deliver package to Security Gateways as part of verification. If you do not select this check box, the verification process is performed first and then the file is downloaded as a separate action.
- 6. In the **Advanced** section, select the source from which the Security Gateway downloads the package:
 - Automatic If the package is in the Package Repository, the Management Server transfers it to the Security Gateway. If the package is not in the Package Repository, the Security Gateway downloads it from the Check Point Cloud.
 - Gateway The Security Gateway downloads the package from the Check Point Cloud. The Security Gateway must be connected to the Internet.
 - Management The Security Gateway downloads the package from the Management Server.
- 7. At the bottom, click Verify.

The verification process starts. The verification process makes sure that the selected Hotfix can be installed on the targets. The verification process makes sure this package does not override other installed Hotfixes and that enough free disk space is available for the process to complete.

To see the progress of the verification process open the **Tasks** view in the bottom left corner of SmartConsole and click **Details**.

Example:



- 8. Click Install.
- 9. Central Deployment makes sure that Access Control Policy is installed.
- 10. After the installation is complete, you must install the applicable Threat Prevention policy on the target Security Gateways and Clusters.

Central Deployment of Hotfixes and Version Upgrades

Introduction

Use Central Deployment in SmartConsole to perform batch deployment of:

- Jumbo Hotfix Accumulators and Hotfixes on Security Gateways and Cluster Members.
- Upgrade Packages on Security Gateways, Cluster Members, Log Servers and secondary management.
- Uninstall Jumbo Hotfix Accumulators and Hotfixes.

You can Deploy a Hotfix or Upgrade Package from:

- The Check Point Cloud.
- The Package Repository on the Management Server.

First, you must upload the applicable package to the Package Repository. See "Adding a package to the Package Repository" on page 246.

To use Central Deployment through the API, see the <u>Check Point Management API</u> <u>Reference</u>.

- Best Practice Use the Package Repository on the Management Server if the target's connectivity to the Management Server is better than the target's connectivity to the cloud, or if the target is overloaded with traffic.
- Note You can select up to 30 Security Gateways and Cluster Members, but installation can take place only on 10 targets at the same time. The Management Server places each target above the 10th in a queue. Each time an installation completes on one of the targets, the Management Server installs it on the next target in the queue.

Some Security Gateways have Recommended Hotfixes. See the **Recommended Jumbo** column in the **Gateways & Servers** view:

	🔹 😍 Install Policy 🗄 Diagnostic Window 👘 Discard Session 🔹 🥎 Publish						SmartConsole	_ □			
Columns:	· ⑦ General	•		*• `	X Script	s 🕶 📑 Action:	s + 🗘 Monitor 🔍 Search		6 🥏	Q Search	
Status	Name	IP	Version	Active Blades	Hardware	CPU Usage	Recommended Updates	Recommended Jumbo	Comments	← 🏦 🗄 🗰 New •	•
	 A-Cluster 	172.28.2.114	R80.20	565 its-	Open server					Object Categories	
•	🖀 A-Member	172.28.2.115	R80.20		Open server	e 0%	8 updates available	Check_Point_R80_20_JUMBO_HF_MAIN_Bundle_T8_FULL.tgz		A Network Objects	20
0	B-Member	172.28.2.116	R80.20		Open server	0 96	8 updates available	Check_Point_R80_20_JUMBO_HF_MAIN_Bundle_T8_FULL.tgz		Services	514
0	A-Gateway	172.28.2.165	R80.20	203	Open server	0 %	9 updates available	Check_Point_R80_20_JUMBO_HF_MAIN_Bundle_T8_FULL.tgz		Applications/Categories	7508
0	📾 B-Gateway	172.28.2.166	6 R80.20	III	Open server	0 %	8 updates available	Check_Point_R80_20_JUMBO_HF_MAIN_Bundle_T8_FULLtgz		VPN Communities	2
•	🖷 harry-main-take-	188 172.28.2.101	R80.40	₩ E8	Open server	496	1 update available			Ao Data Types	63
										Lu Data types	
										Servers	
										 Servers Time Objects 	
										S UserCheck Interactions	1
										Limit	
	Tasks Fre	175							÷		
Summ		rs				Arrow	r Blader		÷		
E	B-Gateway						s Blades		÷		
IPv4 J	B-Gateway	2.28.2.166		Oper	n server		s Blades F Firewall		×		
IPv4	B-Gateway Address: 17. sss Control Policy: Sta	2.28.2.166 ndard		Oper	n server				:		
IPv4 J Acces	Address: 17. sss Control Policy: Sta 03	2.28.2.166 ndard Nov-19 16:24							÷		
IPv4 J Acces OS:	Address: 17. ss Control Policy: Sta 03 Ga	2.28.2.166 ndard Nov-19 16:24 ia			n server				÷		
IPv4 / Acces OS: Versio	Address: 17. ss Control Policy: Sta 03 Ga on: R8	2.28.2.166 ndard Nov-19 16:24 ia 0.20							:		
IPv4 / Acces OS: Versio	Address: 17. ss Control Policy: Sta 03 Ga	2.28.2.166 ndard Nov-19 16:24 ia 0.20							:		
IPv47 Acces OS: Versio	Address: 17. ss Control Policy: Sta 03 Ga on: R8	2.28.2.166 ndard Nov-19 16:24 ia 0.20		CPU:	0%				2		
IPv4 / Acces OS: Versio	Address: 17. ss Control Policy: Sta 03 Ga on: R8	2.28.2.166 ndard Nov-19 16:24 ia 0.20		CPU:					2		
IPv47 Acces OS: Versio	Address: 17. ss Control Policy: Sta 03 Ga on: R8	2.28.2.166 ndard Nov-19 16:24 ia 0.20		CPU: Memory:	0%				t Activate Blades		

You can deploy a Recommended Jumbo Hotfix Accumulator or a specific Jumbo Hotfix Accumulator take.

Prerequisites

To use Central Deployment:

- The administrator must have SmartUpdate write permission on the Management Server.
- The latest build of the CPUSE Deployment Agent must be installed on the target Security Gateways and Cluster Members or on the Management Server.
- SIC must already be established between the Management Server and the target Security Gateways and Cluster Members.
- A policy must be installed on the target Security Gateways and Cluster Members.
- Only full clusters can be selected (you cannot select one cluster member).

To use Central Deployment directly from the Check Point Cloud:

- 1. The Management Server must be able to connect to the Check Point Cloud.
- 2. The target Security Gateways and Cluster Members must be able to connect to the Check Point Cloud.

Limitations

- Upgrade from the R80.30, R80.20, and R80.10 versions (to upgrade from these versions to a higher version, use the CPUSE in-place upgrade).
- Central Deployment does not support:
 - Connecting from SmartConsole to the Security Management Server through a proxy server.
 In this case, use the applicable API command.
 - ClusterXL in Load Sharing mode.
 - VRRP Cluster.
 - Security Group in Maestro.
 - Security Group on Scalable Chassis 40000 / 60000.
 - ElasticXL Cluster.
 - For Centrally Managed Quantum Spark Appliances running Gaia Embedded operating system:
 - Downloading the package from the Check Point Cloud. You must manually add the required package to the Package Repository on the Security Management Server.
 - When using SmartConsole Central Deployment to install a firmware package of the same version, but of a lower build number than is already installed on a Quantum Spark appliance, the "Verify" action does not compare the firmware build numbers. Therefore, SmartConsole shows that "The package is valid for installation", while in fact, the installation will fail by design.
 - On Multi-Domain Servers, SmartConsole connected to the Global Domain, or the Multi-Domain Server context.

Installation

Adding a package to the Package Repository

- 1. From the left navigation panel, click Manage & Settings.
- 2. From the left tree, click **Package Repository**.
- 3. Click **New** and select one of these options:
 - Download from cloud To download the package to the Package Repository from the Check Point Cloud, paste the package CPUSE identifier and click Download.

 Upload from local - To upload the package to the Package Repository from your device, browse to the applicable package and click Open.

After the download or upload is complete, the package appears in the **Package Repository** window in SmartConsole > **Manage & Settings** view.

Notes:

- Add one package to the repository at a time.
- For Quantum Spark Appliances that run Gaia Embedded OS R80.20.xx and higher, you must download a special TAR package (that contains the firmware image and the required configuration file hf.config) and use the "Upload from local" option.
- When you upload a package to the Package Repository in a Multi-Domain environment:
 - You can upload the package to the Global Domain. In this case, you can see the uploaded package from all Domains and install it on the Domain or Domains of your choice.
 - You can upload the package to a specific Domain. In this case, you can see the package and install it only on that specific Domain.

Installing a Hotfix or Upgrade Package on multiple Security Gateways or Cluster Members

- Warning Before you install firmware on a Quantum Spark appliance that runs Gaia Embedded OS, you must disconnect any external storage from the USB port (at the minimum, make sure that the external storage does not contain firmware images for Quantum Spark appliances).
- Best Practice Central deployment of Hotfixes or upgrade packages on the Security Management Server relies on the status reports from the managed Gaia servers. Therefore, we recommend to wait for two minutes after the Gaia server is up and running before you install a Hotfix or upgrade package.
 - 1. From the left navigation panel, click Gateways & Servers.
 - 2. Select the target Security Gateways or Cluster Members for deployment.

To select multiple targets, press and hold the CTRL key.

To upgrade Cluster Members, select the cluster object.

- 3. From the toolbar menu, click Actions and select one of these options:
 - Install Hotfix/Jumbo
 - Version Upgrade

The **Install Hotfix** or **Version Upgrade** window opens, and shows information about the selected targets and their corresponding recommended Hotfix or Upgrade Package.

- 4. If you selected "Install Hotfix/Jumbo", in the "Hotfix/Jumbo" section, select one of these options:
 - Install the Recommended Hotfix/Jumbo

or

- Install a Specific Hotfix/Jumbo
 - Note If there is no recommended Jumbo Hotfix Accumulator for the selected targets, this option is grayed out. If a recommended Jumbo Hotfix Accumulator applies only to some of the selected targets, the deployment takes place only for those targets.
 - a. Enter the Hotfix file name.

You can copy the Hotfix file name from the applicable SK article to the Install Specific Hotfix text box.



• Note - Use the field "Install a Specific Hotfix/Jumbo" to install a firmware package on Quantum Spark Appliances that run Gaia Embedded OS R80.20.xx and higher. The Management Server considers firmware packages based on the same main version as Jumbo Hotfixes. For example, all firmware packages R81.10.XX are based on the main version R81.10.

Example for a Security Gateway R80.20:

•	Ongoing	Take

Product	Take	Date	CPUSE Online Identifier	SmartConsole package
Security Gateway / Standalone	Jumbo HF	03 Dec 2019	Check_Point_R80_20_JUMB0_HF_Bundle_T127_sk137592 _Security_Gateway_and_Standalone_2_6_18_FULL.tgz	🖄 (EXE)
Security Management	Take_127		Check_Point_R80_20_JUMB0_HF_Bundle_T127_sk137592 _Security_Management_3_10_FULL.tgz	

b. Click the search icon next to the text box to find the available package.

If you selected "Version Upgrade", in the "Upgrade Version" window, select one of these options:

Upgrade to the Recommended Major Version

or


- Upgrade to a Specific Major Version
 - a. Enter the version number.
 - b. Click the search icon next to the text box to find the available package.
- 5. In the **Gateways** section, you see the targets you selected for installing the package.
- 6. In the **Settings** section, select the applicable option for the High Availability cluster:

- Install on all cluster members Installs the selected package on all members in this cluster (active and standby). This can cluster failover and interrupt the traffic.
- Install on non-active members only Installs the selected package only on standby cluster members.
 - Once installation is complete, turn non-active member to active -Changes the cluster state of a standby cluster member to active.
- 7. In the **Advanced** section, select where the Security Gateway downloads package from:
 - Automatic If the package is in the Package Repository, the Management Server transfers it to the Security Gateway. If the package is not in the Package Repository, the Security Gateway downloads it from the Check Point Cloud.
 - Gateway The Security Gateway downloads the package from the Check Point Cloud. The Security Gateway must be connected to the Internet.
 - Management The Security Gateway downloads the package from the Management Server.
- 8. At the bottom, click Verify.

The verification process starts. The verification process makes sure that the selected Hotfix or Upgrade Package can be installed on the targets. The verification process makes sure this package does not override other installed Hotfixes and that enough free disk space is available for the process to complete.

To see the progress of the verification process open the **Tasks** view in the bottom left corner of SmartConsole and click **Details**.

Example:



- 9. Click Install.
- 10. Central Deployment makes sure that Access Control Policy is installed.

- 11. After the installation is complete, you must install the applicable Threat Prevention policy on the target Security Gateways and Clusters.
- Notes:
 - If different targets have different recommended Hotfixes or Upgrade Packages, each target gets its applicable recommended Hotfix or Upgrade Package.
 - Before you install a firmware on a Quantum Spark appliance that runs Gaia Embedded operating system, you must disconnect an external storage from the USB port (at minimum, make sure it does not contain firmware images for Quantum Spark appliances).

Uninstalling a Hotfix or a Jumbo Hotfix Accumulator

To uninstall a Hotfix or a Jumbo Hotfix Accumulator

- 1. From the left navigation panel, click Gateways & Servers.
- 2. Select the target Security Gateways or Cluster Members for deployment.

To select multiple targets, press and hold the CTRL key.

To uninstall the package on Cluster Members, select the cluster object.

3. From the toolbar menu, click Actions and select Uninstall Hotfix/Jumbo.

The Uninstall Hotfix/Jumbo window opens.

- 4. In the Hotfix/Jumbo section, enter the Hotfix/Jumbo to uninstall.
- 5. In the **Gateways** section, see the targets you selected for uninstalling the Hotfix or Jumbo Hotfix Accumulator.
- 6. At the bottom, click Verify.

The verification process starts. The verification process makes sure all necessary conditions are met so that the selected Hotfix or Jumbo Hotfix Accumulator can be uninstalled from the targets.

To see the progress of the verification process open the **Tasks** view in the bottom left corner of SmartConsole and click **Details**.

7. Click Uninstall.

How the Central Deployment Upgrades a Cluster


When you use the Central Deployment to install a software package on all members of a ClusterXL in High Availability mode or VSX Cluster (non-VSLS), the Central Deployment follows these steps:

- 1. Verifies that the states of the Cluster Members are valid (Active and Standby).
- 2. Prepares the Access Control Policy for the Cluster:
 - a. Changes the version in the Cluster object.
 - b. Changes the applicable configuration settings and Access Control Policy.
- 3. Upgrades the Standby Cluster Member to the new version.
- 4. Runs a Multi-Version Cluster (MVC):
 - a. Makes sure the upgraded Cluster Member is in the Standby or Ready state.
 - b. Performs cluster failover to one of the upgraded Cluster Members.
- 5. Upgrades the former Active Cluster Member.
- 6. Verifies that the states of the Cluster Members are valid (Active and Standby).

Configuring a Security Gateway to Access the Management Server or Log Server at its NATed IP Address

You can configure a Security Gateway to access the Security Management Server or Log Server at the server's NATed IP address for fetching policy or sending logs.

This diagram describes the flow of this process:



Procedure:

- 1. Connect to the command line on the Security Gateway / each Cluster Member.
- 2. Log in to the Expert mode.
- 3. On a VSX Gateway / each VSX Cluster Member, go to the context of the applicable Virtual System:

vsenv <VSID>

- 4. Run the applicable command (this change survives reboot):
 - a. To force the Security Gateway / Cluster Member to connect only to the public (NATed) IP address (this is the default behavior) of the Management Server or Log Server, run:

```
ckp_regedit -a SOFTWARE\\CheckPoint\\FW1 FORCE_NATTED_IP
-n 1
```

b. To force the Security Gateway / Cluster Member to connect only to the **real** IP address of the Management Server or Log Server, run:

```
ckp_regedit -a SOFTWARE\\CheckPoint\\FW1 FORCE_NATTED_IP
-n 0
```

Notes:

- This change survives reboot.
- In a Cluster, you must configure all the Cluster Members in the same way.

Configuring a Security Gateway to Access the Management Server or Log Server at its NATed

5. Restart the FWD process:

See the instructions in <u>sk97638</u> > section *Infrastructure Processes*.

Configuring Implied Rules or Kernel Tables for Security Gateways

Introduction

An administrator configures Security Policy and other inspection settings in SmartConsole.

During a policy installation, the Management Server creates the applicable files and transfers them to the target Security Gateways.

The Management Server creates these files based on:

- Security Policy in SmartConsole
- Global properties in SmartConsole
- Security Gateway properties
- Multiple configuration files on the Management Server that control the inspection of various network protocols

It is possible to modify these configuration files on the Management Server to fine-tune the inspection in your network (in Check Point INSPECT language).

There are two main categories of these configuration files:

- Files for Security Gateways that have the same software version as the Management Server.
- Files for Security Gateways that have the a lower software version than the Management Server. This category is called "Backward Compatibility".

File Name	Controls	Location
user.def	User-defined implied rules.	See "Location of 'user.def' Files on the Management Server" on page 257
implied_ rules.def	Default implied rules.	See "Location of 'implied_rules.def' Files on the Management Server" on page 258

Configuration files

File Name	Controls	Location
table.def	Definitions of various kernel tables.	See "Location of 'table.def' Files on the Management Server" on page 260
crypt.def	VPN encryption macros.	See "Location of 'crypt.def' Files on the Management Server" on page 262
vpn_table.def	Definitions for various kernel tables that hold VPN data. For example, VPN timeouts, number of VPN tunnels, whether a specific kernel table should be synchronized between cluster members, and others.	See "Location of 'vpn_ table.def' Files on the Management Server" on page 264
communities.def	VPN encryption macros for X11 server (X Window System) traffic.	See "Location of 'communities.def' Files on the Management Server" on page 268
base.def	Definitions of packet inspection for various network protocols.	See "Location of 'base.def' Files on the Management Server" on page 270
dhcp.def	Definitions of packet inspection for DHCP traffic - DHCP Request, DHCP Reply, and DHCP Relay.	See "Location of 'dhcp.def' Files on the Management Server" on page 272
gtp.def	Definitions of packet inspection for GTP (GPRS Tunnelling Protocol) traffic.	See "Location of 'gtp.def' Files on the Management Server" on page 274

Configuration Procedure

- 1. Connect to the command line on the Security Management Server.
- 2. Log in to the Expert mode.
- 3. Back up the current file:

```
cp -v /<Full Path to File>/<File Name>{, BKP}
```

Example:

cp -v \$FWDIR/conf/user.def.FW1{,_BKP}

4. Edit the current file:

```
vi /<Full Path to File>/<File Name>
```

Example:

```
vi $FWDIR/conf/user.def.FW1
```

- 5. Make the applicable changes as described in the applicable SK article, or as instructed by Check Point Support.
- 6. Save the changes in the file and exit the editor.
- 7. Connect with SmartConsole to the Security Management Server.
- 8. In SmartConsole, install the Access Control Policy on the applicable Security Gateway or Cluster object.

Location of 'user.def' Files on the Management Server

The 'user.def' files contain the user-defined implied rules.

Important:

 You must edit this file in the context of the applicable Domain Management Server.

To go to the required context, use the command: mdsenv <IP Address or Name of Domain Management Server>

If the required file does not exist, create a copy of the \$FWDIR/conf/user.def.FW1 file, rename it, and edit it.

Version of the Target Security Gateway	Location of the File
R82	\$FWDIR/conf/user.def.FW1
R81.20	\$FWDIR/conf/user.def.R8120CMP
R81.10	\$FWDIR/conf/user.def.R8120CMP
R81.10.x on Quantum Spark Appliances 1500 / 1600 / 1800	\$FWDIR/conf/user.def.SFWR81CMP
R81	\$FWDIR/conf/user.def.R8120CMP
R80.40	\$FWDIR/conf/user.def.R8040CMP
R80.30SP in Maestro	\$FWDIR/conf/user.def.R8040CMP
R80.30	\$FWDIR/conf/user.def.R8040CMP
R80.20SP in Maestro, or Scalable Chassis	\$FWDIR/conf/user.def.R8040CMP
R80.20	\$FWDIR/conf/user.def.R8040CMP
R80.20.x on Quantum Spark Appliances 1500 / 1600 / 1800	\$FWDIR/conf/user.def.SFWR80CMP
R80.10	\$FWDIR/conf/user.def.R8040CMP
R77.20.x on SMB Appliances 1100 / 1200R / 1400	\$FWDIR/conf/user.def.SFWR77CMP

Location of 'implied_rules.def' Files on the Management Server

The 'implied_rules.def' files contain the default implied rules.

Important:

 You must edit this file in the context of the applicable Domain Management Server.

To go to the required context, use the command:

mdsenv <IP Address or Name of Domain Management Server>

If the required file does not exist, create a copy of the \$FWDIR/lib/implied_ rules.def file, rename it, and edit it.

Version of the Target Security Gateway	Location of the File
R82	\$FWDIR/lib/implied_rules.def
R81.20	/opt/CPR8120CMP-R82/lib/implied_ rules.def
R81.10	/opt/CPR8120CMP-R82/lib/implied_ rules.def
R81.10.x on Quantum Spark Appliances 1500 / 1600 / 1800	/opt/CPSFWR81CMP- R82/lib/implied_rules.def
R81	/opt/CPR8120CMP-R82/lib/implied_ rules.def
R80.40	/opt/CPR8040CMP-R82/lib/implied_ rules.def
R80.30SP in Maestro	/opt/CPR8040CMP-R82/lib/implied_ rules.def
R80.30	/opt/CPR8040CMP-R82/lib/implied_ rules.def
R80.20SP in Maestro, or Scalable Chassis	/opt/CPR8040CMP-R82/lib/implied_ rules.def
R80.20	/opt/CPR8040CMP-R82/lib/implied_ rules.def

Location of 'implied_rules.def' Files on the Management Server

Version of the Target Security Gateway	Location of the File
R80.20.x on Quantum Spark Appliances 1500 / 1600 / 1800	/opt/CPSFWR80CMP- R82/lib/implied_rules.def
R80.10	/opt/CPR8040CMP-R82/lib/implied_ rules.def
R77.20.x on SMB Appliances 1100 / 1200R / 1400	/opt/CPSFWR77CMP- R82/lib/implied_rules.def

Location of 'table.def' Files on the Management Server

The 'table.def' files contain definitions of various kernel tables for Security Gateways.

Important:

 You must edit this file in the context of the applicable Domain Management Server.

To go to the required context, use the command: mdsenv <IP Address or Name of Domain Management Server>

If the required file does not exist, create a copy of the \$FWDIR/lib/table.def file, rename it, and edit it.

Version of the Target Security Gateway	Location of the File
R82	\$FWDIR/lib/table.def
R81.20	/opt/CPR8120CMP- R82/lib/table.def
R81.10	/opt/CPR8120CMP- R82/lib/table.def
R81.10.x on Quantum Spark Appliances 1500 / 1600 / 1800	/opt/CPSFWR81CMP- R82/lib/table.def
R81	/opt/CPR8120CMP- R82/lib/table.def
R80.40	/opt/CPR8040CMP- R82/lib/table.def
R80.30SP in Maestro	/opt/CPR8040CMP- R82/lib/table.def
R80.30	/opt/CPR8040CMP- R82/lib/table.def
R80.20SP in Maestro, or Scalable Chassis	/opt/CPR8040CMP- R82/lib/table.def
R80.20	/opt/CPR8040CMP- R82/lib/table.def
R80.20.x on Quantum Spark Appliances 1500 / 1600 / 1800	/opt/CPSFWR80CMP- R82/lib/table.def

Location of 'table.def' Files on the Management Server

Version of the Target Security Gateway	Location of the File
R80.10	/opt/CPR8040CMP- R82/lib/table.def
R77.20.x on SMB Appliances 1100 / 1200R / 1400	/opt/CPSFWR77CMP- R82/lib/table.def

Location of 'crypt.def' Files on the Management Server

The 'crypt.def' files contain VPN encryption macros.

Important:

 You must edit this file in the context of the applicable Domain Management Server.

To go to the required context, use the command: mdsenv <IP Address or Name of Domain Management Server>

If the required file does not exist, create a copy of the \$FWDIR/lib/crypt.def file, rename it, and edit it.

Version of the Target Security Gateway	Location of the File
R82	\$FWDIR/lib/crypt.def
R81.20	/opt/CPR8120CMP- R82/lib/crypt.def
R81.10	/opt/CPR8120CMP- R82/lib/crypt.def
R81.10.x on Quantum Spark Appliances 1500 / 1600 / 1800	/opt/CPSFWR81CMP- R82/lib/crypt.def
R81	/opt/CPR8120CMP- R82/lib/crypt.def
R80.40	/opt/CPR8040CMP- R82/lib/crypt.def
R80.30SP in Maestro	/opt/CPR8040CMP- R82/lib/crypt.def
R80.30	/opt/CPR8040CMP- R82/lib/crypt.def
R80.20SP in Maestro, or Scalable Chassis	/opt/CPR8040CMP- R82/lib/crypt.def
R80.20	/opt/CPR8040CMP- R82/lib/crypt.def
R80.20.x on Quantum Spark Appliances 1500 / 1600 / 1800	/opt/CPSFWR80CMP- R82/lib/crypt.def

Location of 'crypt.def' Files on the Management Server

Version of the Target Security Gateway	Location of the File
R80.10	/opt/CPR8040CMP- R82/lib/crypt.def
R77.20.x on SMB Appliances 1100 / 1200R / 1400	/opt/CPSFWR77CMP- R82/lib/crypt.def

Location of 'vpn_table.def' Files on the Management Server

The 'vpn table.def' files contain definitions for various kernel tables that hold VPN data.

For example, VPN timeouts, number of VPN tunnels, whether a specific kernel table should be synchronized between cluster members, and others.

Important:

 You must edit this file in the context of the applicable Domain Management Server.

To go to the required context, use the command:

mdsenv <IP Address or Name of Domain Management Server>

If the required file does not exist, create a copy of the \$FWDIR/lib/vpn_table.def file, rename it, and edit it.

Version of the Target Security Gateway	Location of the File
R82	\$FWDIR/lib/vpn_table.def
R81.20	/opt/CPR8120CMP-R82/lib/vpn_ table.def
R81.10	/opt/CPR8120CMP-R82/lib/vpn_ table.def
R81.10.x on Quantum Spark Appliances 1500 / 1600 / 1800	/opt/CPSFWR81CMP-R82/lib/vpn_ table.def
R81	/opt/CPR8120CMP-R82/lib/vpn_ table.def
R80.40	/opt/CPR8040CMP-R82/lib/vpn_ table.def
R80.30SP in Maestro	/opt/CPR8040CMP-R82/lib/vpn_ table.def
R80.30	/opt/CPR8040CMP-R82/lib/vpn_ table.def
R80.20SP in Maestro, or Scalable Chassis	/opt/CPR8040CMP-R82/lib/vpn_ table.def
R80.20	/opt/CPR8040CMP-R82/lib/vpn_ table.def

Location of 'vpn_table.def' Files on the Management Server

Version of the Target Security Gateway	Location of the File
R80.20.x on Quantum Spark Appliances 1500 / 1600 / 1800	/opt/CPSFWR80CMP-R82/lib/vpn_ table.def
R80.10	/opt/CPR8040CMP-R82/lib/vpn_ table.def
R77.20.x on SMB Appliances 1100 / 1200R / 1400	/opt/CPSFWR77CMP-R82/lib/vpn_ table.def

Location of 'vpn_route.conf' Files on the Management Server

The 'vpn route.conf' files contain the configuration for Domain-Based Site to Site VPN.

Important:

 You must edit this file in the context of the applicable Domain Management Server.

To go to the required context, use the command:

mdsenv <IP Address or Name of Domain Management Server>

If the required file does not exist, create a copy of the \$FWDIR/conf/vpn_route.conf file, rename it, and edit it.

Version of the Target Security Gateway	Location of the File
R82	\$FWDIR/conf/vpn_route.conf
R81.20	/opt/CPR8120CMP-R82/conf/vpn_ route.conf
R81.10	/opt/CPR8120CMP-R82/conf/vpn_ route.conf
R81.10.x on Quantum Spark Appliances 1500 / 1600 / 1800	/opt/CPSFWR81CMP-R82/conf/vpn_ route.conf
R81	/opt/CPR8120CMP-R82/conf/vpn_ route.conf
R80.40	/opt/CPR8040CMP-R82/conf/vpn_ route.conf
R80.30SP in Maestro	/opt/CPR8040CMP-R82/conf/vpn_ route.conf
R80.30	/opt/CPR8040CMP-R82/conf/vpn_ route.conf
R80.20SP in Maestro, or Scalable Chassis	/opt/CPR8040CMP-R82/conf/vpn_ route.conf
R80.20	/opt/CPR8040CMP-R82/conf/vpn_ route.conf

Location of 'vpn_route.conf' Files on the Management Server

Version of the Target Security Gateway	Location of the File
R80.20.x on Quantum Spark Appliances 1500 / 1600 / 1800	/opt/CPSFWR80CMP-R82/conf/vpn_ route.conf
R80.10	/opt/CPR8040CMP-R82/conf/vpn_ route.conf

Location of 'communities.def' Files on the Management Server

The 'communities.def' files contain VPN encryption macros for X11 server (X Window System) traffic.

Important:

 You must edit this file in the context of the applicable Domain Management Server.

To go to the required context, use the command: mdsenv <IP Address or Name of Domain Management Server>

If the required file does not exist, create a copy of the \$FWDIR/lib/communities.def file, rename it, and edit it.

Version of the Target Security Gateway	Location of the File
R82	\$FWDIR/lib/communities.def
R81.20	/opt/CPR8120CMP- R82/lib/communities.def
R81.10	/opt/CPR8120CMP- R82/lib/communities.def
R81.10.x on Quantum Spark Appliances 1500 / 1600 / 1800	/opt/CPSFWR81CMP- R82/lib/communities.def
R81	/opt/CPR8120CMP- R82/lib/communities.def
R80.40	/opt/CPR8040CMP- R82/lib/communities.def
R80.30SP in Maestro	/opt/CPR8040CMP- R82/lib/communities.def
R80.30	/opt/CPR8040CMP- R82/lib/communities.def
R80.20SP in Maestro, or Scalable Chassis	/opt/CPR8040CMP- R82/lib/communities.def
R80.20	/opt/CPR8040CMP- R82/lib/communities.def

Location of 'communities.def' Files on the Management Server

Version of the Target Security Gateway	Location of the File
R80.20.x on Quantum Spark Appliances 1500 / 1600 / 1800	/opt/CPSFWR80CMP- R82/lib/communities.def
R80.10	/opt/CPR8040CMP- R82/lib/communities.def
R77.20.x on SMB Appliances 1100 / 1200R / 1400	/opt/CPSFWR77CMP- R82/lib/communities.def

Location of 'base.def' Files on the Management Server

The 'base.def' files contain definitions of packet inspection for various network protocols.

- Important:
 - You must edit this file in the context of the applicable Domain Management Server.

To go to the required context, use the command: mdsenv <IP Address or Name of Domain Management Server>

If the required file does not exist, create a copy of the \$FWDIR/lib/base.def file, rename it, and edit it.

Version of the Target Security Gateway	Location of the File	
R82	\$FWDIR/lib/base.def	
R81.20	/opt/CPR8120CMP- R82/lib/base.def	
R81.10	/opt/CPR8120CMP- R82/lib/base.def	
R81.10.x on Quantum Spark Appliances 1500 / 1600 / 1800	/opt/CPSFWR81CMP- R82/lib/base.def	
R81	/opt/CPR8120CMP- R82/lib/base.def	
R80.40	/opt/CPR8040CMP- R82/lib/base.def	
R80.30SP in Maestro	/opt/CPR8040CMP- R82/lib/base.def	
R80.30	/opt/CPR8040CMP- R82/lib/base.def	
R80.20SP in Maestro, or Scalable Chassis	/opt/CPR8040CMP- R82/lib/base.def	
R80.20	/opt/CPR8040CMP- R82/lib/base.def	
R80.20.x on Quantum Spark Appliances 1500 / 1600 / 1800	/opt/CPSFWR80CMP- R82/lib/base.def	

Location of 'base.def' Files on the Management Server

Version of the Target Security Gateway	Location of the File
R80.10	/opt/CPR8040CMP- R82/lib/base.def
R77.20.x on SMB Appliances 1100 / 1200R / 1400	/opt/CPSFWR77CMP- R82/lib/base.def

Location of 'dhcp.def' Files on the Management Server

The 'dhcp.def' files contain definitions of packet inspection for DHCP traffic - DHCP Request, DHCP Reply, and DHCP Relay.

Important:

 You must edit this file in the context of the applicable Domain Management Server.

To go to the required context, use the command:

mdsenv <IP Address or Name of Domain Management Server>

If the required file does not exist, create a copy of the \$FWDIR/lib/dhcp.def file, rename it, and edit it.

Version of the Target Security Gateway	Location of the File
R82	\$FWDIR/lib/dhcp.def
R81.20	/opt/CPR8120CMP- R82/lib/dhcp.def
R81.10	/opt/CPR8120CMP- R82/lib/dhcp.def
R81.10.x on Quantum Spark Appliances 1500 / 1600 / 1800	/opt/CPSFWR81CMP- R82/lib/dhcp.def
R81	/opt/CPR8120CMP- R82/lib/dhcp.def
R80.40	/opt/CPR8040CMP- R82/lib/dhcp.def
R80.30SP in Maestro	/opt/CPR8040CMP- R82/lib/dhcp.def
R80.30	/opt/CPR8040CMP- R82/lib/dhcp.def
R80.20SP in Maestro, or Scalable Chassis	/opt/CPR8040CMP- R82/lib/dhcp.def
R80.20	/opt/CPR8040CMP- R82/lib/dhcp.def

Location of 'dhcp.def' Files on the Management Server

Version of the Target Security Gateway	Location of the File
R80.20.x on Quantum Spark Appliances 1500 / 1600 / 1800	/opt/CPSFWR80CMP- R82/lib/dhcp.def
R80.10	/opt/CPR8040CMP- R82/lib/dhcp.def
R77.20.x on SMB Appliances 1100 / 1200R / 1400	/opt/CPSFWR77CMP- R82/lib/dhcp.def

Location of 'gtp.def' Files on the Management Server

The 'gtp.def' files contain definitions of packet inspection for GTP (GPRS Tunnelling Protocol) traffic.

Important:

 You must edit this file in the context of the applicable Domain Management Server.

To go to the required context, use the command:

mdsenv <IP Address or Name of Domain Management Server>

If the required file does not exist, create a copy of the \$FWDIR/lib/gtp.def file, rename it, and edit it.

Version of the Target Security Gateway	Location of the File
R82	\$FWDIR/lib/gtp.def
R81.20	/opt/CPR8120CMP- R82/lib/gtp.def
R81.10	/opt/CPR8120CMP- R82/lib/gtp.def
R81.10.x on Quantum Spark Appliances 1500 / 1600 / 1800	/opt/CPSFWR81CMP- R82/lib/gtp.def
R81	/opt/CPR8120CMP- R82/lib/gtp.def
R80.40	/opt/CPR8040CMP- R82/lib/gtp.def
R80.30SP in Maestro	/opt/CPR8040CMP- R82/lib/gtp.def
R80.30	/opt/CPR8040CMP- R82/lib/gtp.def
R80.20SP in Maestro, or Scalable Chassis	/opt/CPR8040CMP- R82/lib/gtp.def
R80.20	/opt/CPR8040CMP- R82/lib/gtp.def

Location of 'gtp.def' Files on the Management Server

Version of the Target Security Gateway	Location of the File
R80.20.x on Quantum Spark Appliances 1500 / 1600 / 1800	/opt/CPSFWR80CMP- R82/lib/gtp.def
R80.10	/opt/CPR8040CMP- R82/lib/gtp.def
R77.20.x on SMB Appliances 1100 / 1200R / 1400	/opt/CPSFWR77CMP- R82/lib/gtp.def

The HealthCheck Point Tool

HealthCheck Point (HCP) tool is a self-updatable suite of tools designed for:

- Tests: Assesses the health of your system.
- WTS (What's The Story): Provides a timeline of critical and informative events that occurred in the system.
- **Topology**: Visualizes the firewall topology.

The HCP tool runs on the managed Security Gateways every 6 hours and sends the status report to the Security Management Server / Domain Management Server.

The HCP status report in SmartConsole is **disabled** by default for all managed devices.

When the HCP status report is enabled, SmartConsole shows the HCP status report as part of the overall system status.

For more information on the HCP tool, see <u>sk171436</u>.

To enable the HCP tool status reports for multiple managed devices

- 1. Go to the **Gateways & Servers** view, press and hold the **Ctrl** key and left-click each device you wish to select.
- 2. From the top toolbar, click Actions.
- 3. From the drop-down menu, select Enable HealthCheck Point Alerts.

To disable the HCP tool status reports for multiple managed devices

- 1. Go to the **Gateways & Servers** view, press and hold the **Ctrl** key and left-click each device you wish to select.
- 2. From the top toolbar, click Actions.
- 3. From the drop-down menu, select **Disable HealthCheck Point Alerts**.

To enable the HCP tool status reports for a specific managed device

- 1. Go to the Gateways & Servers view.
- 2. Right-click the managed device object.
- 3. From the drop-down menu, select **Actions** and select **Enable HealthCheck Point Alerts**.

To disable the HCP tool status reports for a specific managed device

- 1. Go to the Gateways & Servers view.
- 2. Right-click the managed device object.
- 3. From the drop-down menu, select **Actions** and select **Disable HealthCheck Point Alerts**.

To enable the HCP tool status reports for a specific Legacy VSX Gateway / Legacy VSX Cluster

- 1. Close all SmartConsole windows.
- 2. Connect with the *Database Tool (GuiDBEdit Tool)* to the Security Management Server / Domain Management Server.
- 3. In the top left panel, go to **Table > Network Objects** and click **network_objects**.
- 4. In the top right-panel, click the Legacy VSX Gateway / Legacy VSX Cluster object.
- In the bottom panel, right-click the attribute "hcp" > click "Edit" > change the value to "true" > click OK.
- 6. Save the changes: click the File menu > Save All.
- 7. Close the Database Tool (GuiDBEdit Tool).

To disable the HCP tool status reports for a specific Legacy VSX Gateway / Legacy VSX Cluster

- 1. Close all SmartConsole windows.
- 2. Connect with the <u>Database Tool (GuiDBEdit Tool)</u> to the Security Management Server / Domain Management Server.
- 3. In the top left panel, go to **Table > Network Objects** and click **network_objects**.
- 4. In the top right-panel, click the Legacy VSX Gateway / Legacy VSX Cluster object.
- In the bottom panel, right-click the attribute "hcp" > click "Edit" > change the value to "false" > click OK.
- 6. Save the changes: click the File menu > Save All.
- 7. Close the Database Tool (GuiDBEdit Tool).

Statuses in SmartConsole

SmartConsole shows these statues in the Gateways & Servers view:

- Success
- A Warning
- Error
- No status was reported

To see the HCP status in SmartConsole:

- 1. In the Gateways & Servers view, right-click the Security Gateway object.
- 2. From the drop-down menu, select Monitor.
- 3. In the window that opens, go to **Device Status**.
- 4. Scroll down to the HealthCheck Point section.

Here you can view the status, including both a short and a detailed description of it.

Note - In the Gateways & Servers view:

- For a short description of the HCP status, hover over the Status column of a Security Gateway.
- For a detailed description of HCP status, select a specific Security Gateway, and go to the Alerts tab at the bottom panel of the screen.

Limitations

 The status of a Traditional VSX Virtual System is not shown on the Virtual System object itself.

Instead, it is displayed on the parent Legacy VSX Gateway / Legacy VSX Cluster object.

 For SMO Security Gateway objects that represent Scalable Platforms (ElasticXL, Maestro, Scalable Chassis), the HealthCheck Point status is an aggregate status for the entire Security Group (and not individually for each Security Group Member).

Best Practice - Install the HCP Extension in SmartConsole as described in <u>sk171436</u>. To resolve the "Warning" or "Error" statuses, click the HealthCheck Point button in the Gateways & Servers view, and see the HCP report.

Managing Objects

Network Objects are defined in SmartConsole and stored in the proprietary Check Point object database. They represent physical and virtual network components (such as Security Gateways, servers, and users), and logical components (such as IP address ranges and Dynamic Objects). Each of these components corresponds to an object in your Check Point security management configuration. Before you create Network Objects, analyze the needs of your organization:

- What are the physical components of your network: devices, hosts, Security Gateways and their active Software Blades?
- What are the logical components: services, resources, applications, ranges?
- Who are the users? How should you group them, and with what permissions?
- Note In SmartConsole, when you configure properties of an object and create a new object from the original object, the new object is not available in the original Object Editor.

To resolve this issue:

- 1. After you close the second Object Editor, click OK in the original Object Editor.
- 2. Edit the original object again. The new object is now available.

Object Categories

Objects in SmartConsole represent networks, devices, protocols and resources. SmartConsole divides objects into these categories:

lcon	Object Type	Examples
*	Network Objects	Security Gateways, hosts, networks, address ranges, dynamic objects, security zones
4	Services	Services, Service groups
	Custom Applications/Sites	Applications, Categories, Mobile applications
*	VPN Communities	Site to Site or Remote Access communities
111	Users	Users, user groups, and user templates
A •	Data Types	International Bank Account Number - IBAN, HIPAA - Medical Record Number - MRN, Source Code.
	Servers	Trusted Certificate Authorities, RADIUS, TACACS
\odot	Time Objects	Time, Time groups
2	UserCheck Interactions	Message windows: Ask , Cancel , Certificate Template , Inform , and Drop
	Limit	 Download and upload bandwidth Important: After policy installation, a bandwidth limit is not enforced on a connection that is matched to an Access Control rule with the Action "Limit" in one of these scenarios: The 'Keep all connections' option is selected in the security object The 'Keep connections open after the policy has been installed' option is selected in the Service object used in this rule

Actions with Objects

You can add, edit, delete, and clone objects. A clone is a copy of the original object, with a different name. You can also replace one object in the Policy with another object.

• Note - Do not create two objects with the same name. A validation error shows when you try to publish the SmartConsole session. To resolve, change one of the object names.

To work with objects, right-click the object in the object tree or in the Object Explorer, and select the action.

You can delete objects that are not used, and you can find out where an object is used.

To clone an object

1. In the object tree or in the Object Explorer, right-click the object and select Clone.

The Clone Object window opens.

- 2. Enter a name for the cloned object.
- 3. Click OK.

To find out where an object is used

In the object tree or in the Object Explorer, right-click the object and select Where Used.

To replace an object with a different object

- 1. In the object tree or in the Object Explorer, right-click the object and select Where Used.
- 2. Click the **Replace** icon.
- 3. From the **Replace with** list, select an item.
- 4. Click Replace.

To delete all instances of an object

- 1. In the object tree or in the Object Explorer, right-click the object and select Where Used.
- 2. Click the **Replace** icon.
- 3. From the Replace with list, select None (remove item).
- 4. Click Replace.



- When you create a new object ("object 2") from within an editor of another existing object ("object 1"), object 2 may not appear in the editor of object 1 immediately. To see object 2 in the editor of object 1, click OK to close object 1 and open it again.
- In SmartConsole, you can only search or filter for objects whose name contain two or more characters.

Object Tags

Object tags are keywords or labels that you can assign to the network objects or groups of objects for search purposes. These are the types of tags you can assign:

- User tags Assigned manually to individual objects or groups of objects
- System tags Predefined keywords, such as "application"

Each tag has a name and a value. The value can be static, or dynamically filled by detection engines.

Adding a Tag to an Object

To add a tag to an object

- 1. Open the network object for editing.
- 2. In the Add Tag field, enter the label to associate with this object.
- 3. Press Enter.

The new tag shows to the right of the Add Tag field.

4. Click OK.

Network Object Types

This section describes various object types available in SmartConsole.

Networks

A **Network** is a group of IP addresses defined by a network address and a net mask. The net mask indicates the size of the network.

A Broadcast IP address is an IP address which is destined for all hosts on the specified network. If this address is included, the Broadcast IP address will be considered as part of the network.

Network Groups

A **Network Group** is a collection of hosts, gateways, networks, or other groups. Groups can be used to facilitate and simplify network management. When you have the same set of objects which you want to use in different places in the Rule Base, you can create a group to include such set of objects and reuse it. Modifications are applied to the group instead of to each member of the group.

Groups are also used where SmartConsole lets you select only one object, but you need to work with more than one. For example, in the Security Gateway object > **Network Management > VPN Domain > Manually defined**, you can only select on object from the drop-down menu. If you want to select more than one object for your VPN Domain, you can create a group, add the required objects to the group, and select the group from the drop-down menu.

Grouping Network Objects

To create a group of network objects

1. In the **Objects** tree, click **New > Network Group**.

The New Network Group window opens.

- 2. Enter a name for the group
- 3. Set optional parameters:
 - Object comment
 - Color
 - Tag (as custom search criteria)
- 4. For each network object you want to add, click the [+] sign and select it from the list that shows.
- 5. Click OK.

From version R80.20.M2, you can also associate groups to a network object directly from the object editor.

To associate groups to a network object

- 1. Open the object editor, and go to Groups in the navigation tree.
- 2. For each group you want to add, click the [+] sign and select it from the list that shows.

Check Point Hosts

A **Check Point Host** can have multiple interfaces but no routing takes place. It is an endpoint that receives traffic for itself through its interfaces. (In comparison, a Security Gateway routes traffic between its multiple interfaces.) For example, if you have two unconnected networks that share a common Security Management Server and Log Server, configure the common server as a Check Point Host object.

A Check Point Host has one or more Software Blades installed. But if the Firewall blade is enabled on the Check Point Host, it cannot function as a Security Gateway. The Host requires SIC and other features provided by the actual Security Gateway.

A Check Point Host has no routing mechanism, is not capable of IP forwarding, and cannot be used to implement Anti-Spoofing. If the host must do any of these, convert it to be a Security Gateway.

The Security Management Server object is a Check Point Host.

0

Note - When you upgrade a Management Server from R77.30 or earlier versions, Node objects are converted to Host objects.

Gateway Cluster

A cluster is a group of Security Gateways configured as one logical object. Clustered gateways add redundancy through High Availability or Load Sharing.

For more information, see the <u>R82 ClusterXL Administration Guide</u>.

Address Ranges

An **Address Range** is a range of IP addresses on the network, defined by the lowest and the highest IP addresses. Use an Address Range object when you cannot define a range of IP addresses by a network IP and a net mask. The Address Range objects are also necessary for the implementation of NAT and VPN.

Wildcard Objects

Wildcard objects are IP address objects that share a common pattern that can be permitted or denied access in a security policy.

Note - This feature is only supported for Security Gateways R80.20 and higher.

To create a new wildcard object

- 1. Open Object Explorer > New > More > Network Object > Wildcard object.
- 2. Enter the Wildcard IP address and Wildcard Netmask in IPv4 or IPv6 Format.
- 3. Click OK.

Understanding Wildcard Objects

The wildcard object contains a wildcard IP address and a wildcard netmask.

The *wildcard netmask* is the mask of bits that indicate which parts of the IP address must match and which do not have to match. For example:

Wildcard IP:	194.	29.	0.	1
Wildcard Netmask:	0.	0.	3.	0

The third octet represents the mask of bits. If we convert the 3 to binary, we get 00000011.

The 0 parts of the mask must match the equivalent bits of the IP address.

The 1 parts of the mask do not have to match, and can be any value.

0	0	0	0	0	0	1	1
Must	match tl	ne equiv	alent bit	s in the l	P address	Do no	t have to match

The binary netmask produces these possible decimal values:

128	64	32	16	8	4	2	1		
						Bina	ry	-	Decimal
0	0	0	0	0	0	0	0		0
0	0	0	0	0	0	0	1		1
0	0	0	0	0	0	1	0		2
0	0	0	0	0	0	1	1		3

The netmask permits only these IP addresses:

- **1**94.29.0.1
- **194.29.1.1**
- 192.29.2.1
- **1**94.29.3.1

Examples of Use Cases

Scenario One

A supermarket chain has all of its cash registers on subnet 194.29.x.1, where x defines the region. In this use case, all the cash registers in this region must have access to the database server at 194.30.1.1.

Instead of defining 256 hosts (194.29.0.1, 194.29.1.1, 194.29.2.1....194.29.255.1), the administrator creates a wildcard object that represents all the cash registers in the region:

Wildcard IP:	194.	29.	0.	1
Wildcard Mask:	0.	0.	255.	0


The wildcard object can now be added to the Access Control Policy.

Source	Destination	Action	Track
Wildcard Object	Database server object	Accept	Log

Scenario Two

In this use case, a supermarket chain has stores in Europe and Asia.

The 192.30.0-255.1 network contains both the Asian and European regions, and the stores within those regions.



2	Database Server for Asia
3	European and Asia network

The administrator wants stores in the European and Asia regions to access different database servers. In this topology, the third octet of the European and Asia network's IP address will be subject to a wildcard. The first four bits of the wildcard will represent the region and the last four bits will represent the store number.

Bits that represent the region	Bits that represent the store number
0000	0000

In the Wildcard IP:

- The Asia region is represented by **0001xxxx** (Region **1** in decimal)
- The European region is represented by **0010xxxx** (Region **2** in decimal)

In binary:

Binary		Decimal
Region	Store	
0001	0000	16 - Asia Region
0010	0000	32 - European Region

To include all the stores of a particular region, the last four bits of the wildcard mask must be set to 1 (15 in Decimal):

Binary		Decimal
Region	Store	
xxxx	1111	15 - all Asian stores
xxxx	1111	15 - all European stores

A wildcard object that represents all the Asian stores will look like this:

Wildcard IP address	192.30.16.1	(The region)
Wildcard netmask	0.0.15.0	(for stores in the region)

For this range of IP addresses: 192.30.16-31.1

A wildcard object that represents all the European stores will look like this:

Wildcard IP address	192.30.32.1	(the region)
Wildcard netmask	0.0.15.0	(for stores in the region)

For this range of IP addresses: 192.30.32-47.1

The administrator can now use these wildcard objects in the Access Control Policy:

Source	Destination	Action	Track
Asian Stores Wildcard	Database Server for Asia	Accept	Log
European Stores Wildcard	Database Server for Europe	Accept	Log

Scenario Three

In this scenario, the netmask bits are not consecutive.

Wildcard IP	1	1	0	1	
Wildcard mask	0	0	5	0	
Wildcard IP	000	00000001.000			01.00000000.00000001
Wildcard Mask 0000000.0000000.00000101.00000				00.00000101.00000000	

Mask:

0	0	0	0	0	0	0	0	0	0	1	1	1	1	1	1	1	1	1	1	2	2	2	2	2	2	2	2	2	2	3	3
0	1	2	3	4	5	6	7	8	9	0	1	2	3	4	5	6	7	8	9	0	1	2	3	4	5	6	7	8	9	0	1
0	0	0	0	0	0	0	0	0	0	0	0	0	0	0	0	0	0	0	0	0	1	0	1	0	0	0	0	0	0	0	0

Which will match only these IP addresses:

IP Address	Binary	Comment
1.1.0.1	0000001.0000001.0000000.0000001	The IP address itself
1.1.1.1	0000001.0000001.0000001.0000001	The equivalent bit at position 23 does not matter
1.1.4.1	0000001.0000001.00000100.00000001	The equivalent bit at position 21 does not matter
1.1.5.1	0000001.0000001.00000101.00000001	The equivalent bits at positions 21 and 23 do not matter

IPv6

The same principles apply to IPv6 addresses. For example, if the wildcard object has these values:

IPv6 Address	2001::1:10:0:1:41
Wildcard netmask	0::ff:0:0

The wildcard will match: 2001::1:10:0-255:1:41

Domains

A **Domain** object represents a host or DNS domain by its name only. It is not necessary to have the IP address of the site.

You can use the Domain object in the source and destination columns of an Access Control Policy.

You can configure a Domain object in two ways:

Select FQDN

In the object name, use the Fully Qualified Domain Name (FQDN).

Use the format .x.y.z (with a dot "." before the FQDN).

For example, if you use .www.example.com then the Security Gateway matches www.example.com

This option is supported for R80.10 and higher, and is the default. It is more accurate and faster than the non-FQDN option.

The Security Gateway looks up the FQDN with a direct DNS query, and uses the result in the Rule Base.

This option supports SecureXL Accept templates.

Using Domain objects with this option in a rule has no effect on the performance of the rule, or of the rules that come after it.

Clear FQDN

This option enforces the domain and its sub-domains.

In the object name, use the format .x.y for the name.

For example, use .example.com or .example.co.uk for the name.

If you use <code>.example.com</code>, then the Security Gateway matches <code>www.example.com</code> and <code>support.example.com</code>

The Security Gateway resolves the name using DNS reverse lookups, which can be inaccurate.

The Security Gateway uses the result in the Rule Base, and caches the result to use again.

Updatable Objects

Introduction to Updatable Objects

An **Updatable Object** is a network object that represents an external service, such as Office 365, AWS, GEO locations, and more. External services providers publish lists of IP addresses or Domains or both to allow access to their services. These lists are dynamically updated.

Updatable objects derive their contents from these published lists of the providers, which Check Point uploads to the Check Point cloud. The updatable objects are updated automatically on the Security Gateway each time the provider changes a list. There is no need to install policy for the updates to take effect.

You can use updatable objects in all three types of policies: Access Control, Threat Prevention, and HTTPS Inspection.

You can use an updatable object in the Access Control, Threat Prevention or the HTTPS Inspection policy as a Source or a Destination. In the Threat Prevention policy, you can also use an updatable object as the Protected Scope.

Notes:

- For Access Control, this feature is supported on Security Gateways R80.20 and higher.
- For Threat Prevention and HTTPS Inspection, this feature is supported on Security Gateways R80.40 and higher.
- Updatable Objects cannot be added to a network group.

Adding an Updatable Object to the Access Control Policy

- 1. Make sure the Security Management Server / Domain Management Server and the Security Gateway have access to the Check Point cloud in the Internet (see <u>sk83520</u>).
- 2. Connect with SmartConsole to the Security Management Server / Domain Management Server.
- 3. From the left navigation panel, click Security Policies.
- 4. In the top panel, click Access Control > Policy.
- 5. Add a new rule in the required position.
- 6. In the **Destination** column, click the + icon.

1 Note - You can also add Updated objects in the Source column.

7. In the top right corner, click **Import > Updatable Objects**.

The Updatable Objects window opens.

8. Select the Updatable objects to add.

9. Click OK.

The selected Updatable objects are added in the rule column.

- 10. Configure other columns in this rule.
- Publish the SmartConsole session.
- 12. Install the Access Control Policy.

Adding an Updatable Object to the Custom Threat Prevention Policy

- 1. Make sure the Security Management Server / Domain Management Server and the Security Gateway have access to the Check Point cloud in the Internet (see sk83520).
- 2. Connect with SmartConsole to the Security Management Server / Domain Management Server.
- 3. From the left navigation panel, click **Security Policies**.
- 4. In the top panel, click **Threat Prevention > Custom Policy**.
- 5. Add a new rule in the required position.
- 6. In the **Protected Scope** column, click the **+** icon.
- 7. In the top right corner, click **Import > Updatable Objects**.

The Updatable Objects window opens.



ONDE - You can also add objects to the **Source** column.

- 8. Select the Updatable objects to add.
- 9. Click OK.

The selected Updatable objects are added in the rule column.

- 10. Configure other columns in this rule.
- 11. Publish the SmartConsole session.
- 12. Install the Threat Prevention Policy.

Adding an Updatable Object to the HTTPS Inspection Policy

- 1. Make sure the Security Management Server / Domain Management Server and the Security Gateway have access to the Check Point cloud in the Internet (see <u>sk83520</u>).
- 2. Connect with SmartConsole to the Security Management Server / Domain Management Server.
- 3. From the left navigation panel, click **Security Policies**.
- 4. In the top panel, click the applicable policy:
 - HTTPS Inspection > Inbound Policy
 - HTTPS Inspection > Outbound Policy
- 5. Add a new rule in the required position.
- 6. In the **Destination** column, click the + icon.

Note - You can also add Updated objects in the Source column.

7. In the top right corner, click **Import > Updatable Objects**.

The Updatable Objects window opens.

- 8. Select the Updatable objects to add.
- 9. Click OK.

A

The selected Updatable objects are added in the rule column.

- 10. Configure other columns in this rule.
- 11. Publish the SmartConsole session.
- 12. Install the HTTPS Inspection Policy.

Monitoring Updatable Objects

You can monitor how the Updatable Objects update their corresponding IP addresses in SmartConsole or SmartView in the Logs & Events view > the Logs tab.

Follow the most applicable procedure for you.

Procedure 1 - Show all logs for the slected Updatable object from a policy

- 1. From the left navigation panel, click Security Policies.
- 2. In the top panel, click the applicable policy:
 - Access Control > Policy
 - Threat Prevention > Custom Policy
- 3. Locate a rule that contains the relevant Updated object.
- 4. Hover the moouse cursor over the Updated object.
- 5. In the menu that appears, click the **Show Logs** icon (the clipboard icon).

The **Logs** window opens and contains the name of the Updatable Object enclosed in double quotes in the top search field.

- 6. On the left side, select the applicable period.
- 7. Double-click the relevant log entry.

The Log Details window opens.

8. When the update is successful, the Status field shows:

Succeeded

Procedure 2 - Search for the specific Updatable object in logs

- 1. From the left navigation panel, click Logs & Events > Logs.
- 2. In the top search bar, enter the name of the Updatable Object enclosed in double quotes.

Example:

"Office365 Services"

- 3. On the left side, select the applicable period.
- 4. Double-click the relevant log entry.

The Log Details window opens.

5. When the update is successful, the **Status** field shows:

Succeeded

Updating the Updatable Objects through the Management Server

If your Security Gateway is not connected to the Internet, then it can get the updates for the Updatable Objects through the Management Server (that would act as a proxy server):

- 1. Connect to the command line on the Security Gateway / each Cluster Member / Scalable Platform Security Group.
- 2. Log in to the Expert mode.
- 3. Back up the current configuration file:

```
cp -v $CPDIR/conf/downloads/dl_prof_ONLINE_SERVICES.xml{,_BKP}
```

4. Edit the current configuration file:

```
vi $CPDIR/conf/downloads/dl prof ONLINE SERVICES.xml
```

5. Change the value of the "ProxyRoute" parameter from 0 to 1:

```
<ProxyRoute>1</ProxyRoute>
```

Example (refer to the bottom of the file):

```
<?xml version="1.0" encoding="UTF-8"?>
<DownloadPreferences>
    <ModuleName>Online Services</ModuleName>
    <ID>111</ID>
    <Version>1.0</Version>
    <Files>online services gw.tgz</Files>
    <DeletionMethod>2</DeletionMethod>
    <Interval>120</Interval>
    <SVT Log ID>Firewall</SVT Log ID>
    <SVT Log Desc>IPs and Domains for Online Services
objects</SVT_Log_Desc>
    <SVT Log Severity>2</SVT Log Severity>
    <SVT Log Failure Impact>Online Services objects update has
failed</SVT_Log_Failure_Impact>
    <CK Identifier>fw1:6.0:xlate</CK Identifier>
    <CK Identifier>fw1:6.0:auth</CK Identifier>
    <CK Identifier>fw1:6.0:content</CK Identifier>
    <URL>
https://updates.checkpoint.com/WebService/services/DownloadMetaDa
taService?wsdl</URL>
    <Updatable>Yes</Updatable>
    <ProxyRoute>1</ProxyRoute>
</DownloadPreferences>
```

- 6. Save the changes in the file and exit the editor.
- 7. On Scalable Platform Security Group, copy the modified file to all Security Group Members:

```
asg_cp2blades $CPDIR/conf/downloads/dl_prof_ONLINE_
SERVICES.xml
```

Dynamic Objects

A **Dynamic Object** is a "logical" object where the IP address is resolved differently for each Security Gateway, using the "dynamic objects" command.

For Security Gateways R80.10 and higher, dynamic objects support SecureXL Accept templates. Therefore, there is no performance impact on a rule that uses a dynamic object, or on rules that come after it.

Dynamic Objects are predefined for **LocalMachine-all-interfaces**. The DAIP computer interfaces (static and dynamic) are resolved into this object.

Generic Data Center Objects

From R81, you can enforce access to and from IP addresses defined in files located in external web servers.

To do that, use the **Generic Data Center** object in SmartConsole. The Generic Data Center object points to a JSON file in an external server which contains the IP addresses which you want to access. This way, when the Generic Data Center object is used in a policy, SmartConsole can retrieve the IP information from the JSON file as necessary.

You can host the JSON file also locally on the Security Management Server.

This feature is useful in cases where one administrator creates the Rule Base and defines the objects, and another administrator manages the content of these objects.

This feature is supported in the Access Control, Threat Prevention, HTTPS Inspection, and NAT Rule Bases.

The feature is supported only on a Security Management Server R81 and higher, and Security Gateway (Cluster) R81 and higher.

After you create the Generic Data Center object, any change made in the file is automatically enforced on the Security Gateway with no need to install policy.

To create the JSON file, follow the guidelines described in <u>sk167210</u>.

Using the Generic Data Center object in a Security Policy

1. In SmartConsole, go to the Object Explorer and click New > More > Cloud > Data Center > Generic Data Center.

The New Generic Data Center object window opens.

- 2. Configure these fields:
 - a. URL Enter the URL of the JSON file.
 - b. Interval Enter the internal at which the file is sampled.

The default interval is 60 seconds.

- c. Add Custom Header If you need to add a custom header to the request to the server, select this checkbox and enter the Key and Value.
- d. Click Test Connection to make sure you can access the file.
- 3. Add the applicable Generic Data Center object to your Rule Base:

In the **Source** or **Destination** column, click **Import** > **Data Center** > **Generic Data Center**, and select the applicable data center object from the list.

Note - The list contains all the data center objects included in you JSON file.

4. Install Policy.

Limitations

- You can make up to 15,000 changes in a JSON file between two time intervals at which the JSON file is sampled, with a maximum of 30,000 IP addresses.
- A Security Gateway supports a total of 5,000 objects of these types: Dynamic objects, Updatable objects, Generic Data Center objects, and Network Feed objects.

Security Zones

With **Security Zones** you can create a strong Access Control Policy that controls the traffic between parts of the network.


A Security Zone object represents a part of the network (for example, the internal network or the external network). You assign a network interface of a Security Gateway to a Security Zone. You can then use the Security Zone objects in the Source and Destination columns of the Rule Base.

Use Security Zones to:

- Simplify the Policy. Apply the same rule to many Security Gateways.
- Add networks to Security Gateways interfaces without changing the Rule Base.

For example, in the diagram, we have three Security Zones for a typical network: *ExternalZone* (1), *DMZZone* (2) and *InternalZone* (3).

- Security Gateway (4) has three interfaces. One interface is assigned to *ExternalZone* (1), one interface is assigned to *DMZZone* (2), and one interface is assigned to *InternalZone* (3).
- Security Gateway (5) has two interfaces. One interface is assigned to *ExternalZone* (1) and one interface is assigned to *InternalZone* (3).



A Security Gateway interface can belong to only one Security Zone. Interfaces to different networks can be in the same Security Zone.

Workflow

1. Configure Security Zone objects.

Or, use the predefined Security Zones (see "Predefined Security Zones" on page 307).

- 2. Assign Security Gateway interfaces to Security Zones (see "Creating and Assigning Security Zones" below).
- 3. Use the Security Zone objects in the Source and Destination of a rule.

For example:

Source	Destination	VPN	Service	Action
InternalZone	ExternalZone	Any Traffic	Any	Accept

4. Install the Access Control Policy (see "Installing the Access Control Policy" on page 396).

Processing Flow for Rule Base Execution when using Security Zones and NAT Rules

1. Matching NAT Rules

The system performs NAT Rule Base matching as the first step. It identifies and records the outbound IP address, which is used both for translation and routing. This step ensures the system can map traffic to the appropriate Security Zones.

2. Retrieving the Outgoing Interface

After identifying the outbound IP address, the kernel queries the routing API to determine the corresponding network interface. The system then assigns this interface to the appropriate outbound Security Zone. This assignment ensures that Rule Base execution aligns with the NAT configurations and accurately routes traffic.

3. Executing the Rule Base

Using the configured outbound interface and Security Zone, the system applies Security Policies to manage traffic. This ensures that all traffic adheres to predefined rules, supporting efficient and accurate network operations.

Example: Resolving Conflicts with Third-Party Tools

Third-party Rule Base tools, such as Algosec, may encounter conflicts when analyzing Check Point policies. These conflicts arise because the Rule Base does not explicitly define NATtranslated IPs. To resolve this, the system processes the NAT Rule Base before executing the main Rule Base. By combining NAT data with routing information, it configures the correct outgoing interface zone. This integration allows third-party tools to interpret the policy correctly and enforce traffic rules without errors.

Creating and Assigning Security Zones

Before you can use Security Zones in the Rule Base, you must assign Security Gateway interfaces to Security Zones.

To create a Security Zone

- In the Objects bar (F11), click New > More > Network Object > Security Zone.
 The Security Zone window opens.
- 2. Enter a name for the Security Zone.
- 3. Enter an optional comment or tag.
- 4. Click OK.

To assign an interface to a Security Zone

1. In the Gateways & Servers view, right-click a Security Gateway object and select Edit.

The Gateway Properties window opens.

2. In the Network Management pane, right-click an interface and select Edit.

The **Interface** window opens. The **Topology** area of the **General** pane shows the Security Zone to which the interface is already bound. By default, the Security Zone is calculated according to where the interface **Leads To**.

3. Click Modify.

The Topology Settings window opens.

- 4. In the Security Zone area, click User Defined and select Specify Security Zone.
- 5. From the drop-down box, select a Security Zone.

Or click **New** to create a new one.

6. Click OK.

Predefined Security Zones

These are the predefined Security Zones, and their intended purposes:

- WirelessZone Networks that can be accessed by users and applications with a wireless connection.
- ExternalZone Networks that are not secure, such as the Internet and other external networks.
- DMZZone A DMZ (demilitarized zone) is sometimes referred to as a *perimeter* network. It contains company servers that can be accessed from external sources.

A DMZ lets external users and applications access specific internal servers, but prevents the external users accessing secure company networks.

Add rules to the Security Gateway Rule Base that allow traffic to the company DMZ. For example, a rule that allows HTTP and HTTPs traffic to your web server in the DMZ.

InternalZone - Company networks with sensitive data that must be protected and used only by authenticated users.

Limitations

- NAT policy supports Security Zones only for R81 Security Gateways and higher.
- The Threat Prevention Policy supports Security Zones only for R81 Security Gateways and higher.
- If the clean-up rule contains Security Zones, it might prevent the creation of Drop templates for that rule.

Externally Managed Gateways and Hosts

An Externally Managed Security Gateway or a Host is a Security Gateway or a Host which has Check Point software installed on it.

This Externally Managed Security Gateway is managed by an external Management Server. While it does not receive the Check Point Security Policy, it can participate in Check Point VPN communities and solutions.

Interoperable Devices

An Interoperable Device is a device that has no Check Point Software Blades installed.

The Interoperable Device:

- Cannot have a policy installed on it
- Can participate in Check Point VPN communities and solutions.

VoIP Domains

There are five types of VoIP Domain objects:

- VoIP Domain SIP Proxy
- VoIP Domain H.323 Gatekeeper
- VoIP Domain H.323 Gateway
- VoIP Domain MGCP Call Agent
- VoIP Domain SCCP Call Manager

In many VoIP networks, the control signals follow a different route through the network than the media. This is the case when the call is managed by a *signal routing* device. Signal routing is done in SIP by the *Redirect Server*, *Registrar*, and/or *Proxy*. In SIP, signal routing is done by the *Gatekeeper* and/or *Gateway*.

Enforcing signal routing locations is an important aspect of VoIP security. It is possible to specify the endpoints that the signal routing device is allowed to manage. This set of locations is called a *VoIP Domain*.

For more information, see the <u>R82 VoIP Administration Guide</u>.

Logical Servers

A **Logical Server** is a group of machines that provides the same services. The workload of this group is distributed between all its members.

When a Server group is stipulated in the **Servers group** field, the client is bound to this physical server.

There are two modes of operation:

- Persistency by Service Once a client is connected to a physical server for a specified service, subsequent connection to the same Logical Server and the same service will be redirected to the same physical server for the duration of the session.
- Persistency by Server Once a client is connected to a physical server, subsequent connections to the same Logical Server (for any service) are redirected to the same physical server for the duration of the session.

Balance Method

The load balancing algorithm stipulates how the traffic is balanced between the servers. There are several types of balancing methods:

- Server Load The Security Gateway determines which Security Management Server is best equipped to handle the new connection.
- Round Trip Time On the basis of the shortest round trip time between Security Gateway and the servers, executed by a simple ping, the Security Gateway determines which Security Management Server is best equipped to handle the new connection.
- Round Robin The new connection is assigned to the first available server.
- **Random** The new connection is assigned to a server at random.
- Domain The new connection is assigned to a server based on domain names.

Fore more information, see the <u>*R82 Quantum Security Gateway Guide*</u> > Chapter *ConnectControl - Server Load Balancing*.

Open Security Extension (OSE) Devices

With the **Open Security Extension** (OSE) features you can manage third-party devices with the Check Point SmartConsole. The number of managed devices, both hardware and software packets, depends on your license. OSE devices commonly include hardware security devices for routing or dedicated Network Address Translation and Authentication appliances. Security devices are managed in the Security Policy as Embedded Devices.

The Security Management Server generates Access Lists from the Security Policy and downloads them to selected routers and open security device. Check Point supports these devices:

OSE Device	Supported Versions
Cisco Systems	9.x, 10.x, 11.x, 12.x

The Check Point Rule Base must not have these objects. If it does, the Security Management Server does not generate Access Lists.

- Drop (in the Action column)
- Encrypt (Action)
- Alert (Action)
- RPC (Service)
- ACE (Service)
- Authentication Rules
- Negate Cell

Defining OSE Device Interfaces

OSE devices report their network interfaces and setup at boot time. Each OSE device has a different command to list its configuration. You must define at least one interface for each device, or **Install Policy** will fail.

To define an OSE Device

- 1. From the Object Explorer, click **New > More**.
- 2. Click Network Object > More > OSE Device.
- 3. Enter the general properties (see "OSE Device Properties Window "General" Tab" on the next page).

We recommend that you also add the OSE device to the host lists on other servers: hosts (Linus) and lmhosts (Windows).

4. Open the **Topology** tab and add the interfaces of the device.

You can enable Anti-Spoofing on the external interfaces of the device. Double-click the interface. In the Interface Properties window > Topology tab, select External and Perform Anti-Spoofing.

5. Open the **Setup** tab and define the OSE device and its administrator credentials (see *"Anti-Spoofing Parameters and OSE Devices Setup (Cisco)" below*).

OSE Device Properties Window - "General" Tab

- Name The name of the OSE device, as it appears in the system database on the server.
- IP Address The device's IP address.
- Get Address Click this button to resolve the name to an address.
- Comment Text to show on the bottom of the Network Object window when this object is selected.
- Color Select a color from the drop-down list. The OSE device will be represented in the selected color in SmartConsole, for easier tracking and management.
- **Type** Select from the list of supported vendors.

Anti-Spoofing Parameters and OSE Devices Setup (Cisco)

For Cisco (Version 10.x and higher) devices, you must specify the direction of the filter rules generated from anti-spoofing parameters. The direction of enforcement is specified in the **Setup** tab of each router.

For Cisco routers, the direction of enforcement is defined by the **Spoof Rules Interface Direction** property.

Access List No - The number of Cisco access lists enforced. Cisco routers Version 12x and below support an ACL number range from 101-200. Cisco routers Version 12x and above support an ACL range number from 101-200 and also an ACL number range from 2000-2699. Inputting this ACL number range enables the support of more interfaces.

For each credential, select an option:

- None Credential is not needed.
- Known The administrator must enter the credentials.
- **Prompt** The administrator will be prompted for the credentials.

Username - The name required to logon to the OSE device.

Password - The Administrator password (Read only) as defined on the router.

Enable Username - The user name required to install Access Lists.

Enable Password - The password required to install Access Lists.

Version - The Cisco OSE device version (9.x, 10.x, 11.x, 12.x).

OSE Device Interface Direction - Installed rules are enforced on data packets traveling in this direction on all interfaces.

Spoof Rules Interface Direction - The spoof tracking rules are enforced on data packets traveling in this direction on all interfaces.

Managing Policies

SmartConsole offers a number of tools that address policy management tasks, both at the definition stage and for maintenance.

At the definition stage:

- Policy Packages let you group different types of policies, to be installed together on the same installation targets.
- Predefined Installation Targets let you associate each package with a set of gateways. You do not have to repeat the gateway selection process each time you install a Policy Package.

At the maintenance level:

- Search gives versatile search capabilities for network objects and the rules in the Rule Base.
- Database version control lets you track past changes to the database.

Working with Policy Packages

A policy package is a collection of different types of policies. After installation, the Security Gateway enforces all the policies in the package. A policy package can have one or more of these policy types:

- Access Control consists of these types of rules:
 - Firewall
 - NAT
 - Application Control & URL Filtering
 - Content Awareness
 - Mobile Access
- QoS Quality of Service rules for bandwidth management
- Desktop Security the Firewall policy for endpoint computers that have the Endpoint Security VPN remote access client installed as a standalone client.
- Threat Prevention consists of:

- IPS IPS protections continually updated by IPS Services
- Anti-Bot & Advanced DNS- Detects bot-infected machines, prevents bot damage by blocking bot commands and Control (C&C) communications
- Anti-Virus Includes heuristic analysis, stops viruses, worms, and other malware at the gateway
- Threat Emulation Detects zero-day and advanced polymorphic attacks by opening suspicious files in a sandbox
- Threat Extraction- Extracts potentially malicious content from e-mail attachments before they enter the corporate network
- Zero Phishing Prevents unknown zero-day and known phishing attacks on websites in real-time, by utilizing industry leading Machine-Learning algorithms and patented inspection technologies.
- HTTPS Inspection Consists of rules to inspect traffic encrypted by the Transport Layer Security (TLS) protocol between internal browser clients and web servers. From R82 on, the HTTPS Inspection policy is divided into Inbound Policy and Outbound Policy.
- Important Legacy SmartDashboard does not show the QoS and Desktop policies when an administrator with read-only permissions is logged in, and the "Desktop Security" policy is enabled in the policy package.

The installation process:

Runs a heuristic verification on rules to make sure they are consistent and that there are no redundant rules.


If there are verification errors, the policy is not installed. If there are verification warnings (for example, if anti-spoofing is not enabled for a Security Gateway with multiple interfaces), the policy package is installed with a warning.

- Makes sure that each of the Security Gateways enforces at least one of the rules. If none of the rules are enforced, the default drop rule is enforced.
- Distributes the user database and object database to the selected installation targets.

You can create different policy packages for different types of sites in an organization.

Example

An organization has four sites, each with its own requirements. Each site has a different set of Software Blades installed on the Security Gateways:



Item	Security Gateway	Installed Software Blades
1	Sales California	Firewall, VPN
2	Sales Alaska	Firewall, VPN, IPS, DLP
3	Executive management	Firewall, VPN, QoS, and Mobile Access
4	Server farm	Firewall
5	Internet	

To manage these different types of sites efficiently, you need to create three different Policy Packages . Each Package includes a combination of policy types that correspond to the Software Blades installed on the site's Security Gateway. For example:

A policy package that includes the Access Control policy type. The Access Control policy type controls the firewall, NAT, Application Control & URL Filtering, and Content Awareness Software Blades. This package also determines the VPN configuration.

Install the Access Control policy package on *all* Security Gateways.

 A policy package that includes the QoS policy type for the QoS blade on Security Gateway that manages bandwidth.

Install this policy package on the *executive management* Security Gateway.

• A policy package that includes the Desktop Security Policy type for the Security

Gateway that handles Mobile Access.

Install this policy package on the *executive management* Security Gateway.

Creating a New Policy Package

1. From the Menu, select Manage policies and layers.

The Manage policies and layers window opens.

2. Click New.

The **New Policy** window opens.

- 3. Enter a name for the policy package.
- 4. In the **General** page > **Policy types** section, select one or more of these policy types:
 - Access Control & HTTPS Inspection
 - Threat Prevention
 - QoS, select Recommended or Express
 - Desktop Security

To see the **QoS**, and **Desktop Security** policy types, enable them on one or more Gateways:

Go to gateway editor > General Properties > Network Security tab:

- For QoS, select QoS
- For Desktop Security, select IPSec VPN and Policy Server
- 5. On the **Installation targets** page, select the gateways the policy will be installed on:
 - All gateways
 - Specific gateways For each gateway, click the [+] sign and select it from the list.

To install Policy Packages correctly and eliminate errors, each Policy Package is associated with a set of appropriate installation targets.

- 6. Click OK.
- 7. Click Close.

The new policy shows on the Security Policies page.

Adding a Policy Type to an Existing Policy Package

1. From the Menu, select Manage policies and layers.

The Manage policies and layers window opens.

- 2. Select a policy package and click the Edit button.
- 3. The **New Policy** package window opens.
- 4. On the General > Policy types page, select the policy type to add:
 - Access Control & HTTPS Inspection
 - Threat Prevention
 - QoS, select Recommended or Express
 - Desktop Security
- 5. Click OK.

Installing a Policy Package

1. On the Global Toolbar, click **Install Policy**.

The **Install Policy** window opens and shows the installation targets (Security Gateways).

- 2. From the **Select a policy** menu, select a policy package.
- 3. Select one or more policy types that are available in the package.
- 4. Select the Install Mode:
 - Install on each selected gateway independently Install the policy on each target gateway independently of others, so that if the installation fails on one of them, it doesn't affect the installation on the rest of the target gateways.

Note - If you select For Gateway clusters install on all the members, if fails do not install at all, the Security Management Server makes sure that it can install the policy on all cluster members before it begins the installation. If the policy cannot be installed on one of the members, policy installation fails for all of them.

- Install on all selected gateways, if it fails do not install on gateways of the same version - Install the policy on all the target gateways. If the policy fails to install on one of the gateways, the policy is not installed on other target gateways.
- 5. Click Install.

Installing the User Database

When you make changes to user definitions through SmartConsole, they are saved to the user database on the Security Management Server. User authentication methods and encryption keys are also saved in this database. The user database does **not** contain information about users defined externally to the Security Gateway (such as users in external User Directory groups), but it does contain information about the external groups themselves (for example, on which Account Unit the external group is defined). Changes to external groups take effect only after the policy is installed, or the user database is downloaded from the Security Management Server.

You must choose to install the policy or the user database, based on the changes you made:

- Install the policy, if you modified additional components of the Policy Package (for example, added new Security Policy rules) that are used by the installation targets
- Install the user database, if you only changed the user definitions or the administrator definitions from the Menu, select Install Database

The user database is installed on:

- Security Gateways during policy installation
- Check Point hosts with one or more Management Software Blades enabled during database installation

You can also install the user database on Security Gateways and on a remote server, such as a Log Server, from the command line interface on the Security Management Server.

To install user database from the command line interface:

On the Security Management Server, run in the Expert mode:

```
fwm dbload <Main IP address of Name of Security Gateway Object>
```

For more information, see the <u>R82 CLI Reference Guide</u> - Chapter Security Management Server Commands - Section fwm - Sub-section fwm dbload.

Note - Check Point hosts that do not have active Management Software Blades do not get the user database installed on them.

Uninstalling the Access Control Policy

You can uninstall the Access Control policy using the command line interface on the Security Gateway.

To uninstall the Access Control policy

- 1. Connect to the command line on the Security Gateway.
- 2. Log in to the Expert mode.
- 3. Run:

fw	unloadlocal
ΤW	unioaulocal

🐌 Warning

- The "fw unloadlocal" command prevents all traffic from passing through the Security Gateway (Cluster Member), because it disables the IP Forwarding in the Linux kernel on the Security Gateway (Cluster Member).
- The "fw unloadlocal" command removes all policies from the Security Gateway (Cluster Member). This means that the Security Gateway (Cluster Member) accepts all incoming connections destined to all active interfaces without any filtering or protection enabled.

For more information, see the <u>R82 CLI Reference Guide</u> - Chapter Security Gateway Commands - Section fw - Sub-section fw unloadlocal.

For uninstalling other Security Policies, check the relevant Administration Guides.

Viewing Rule Logs

You can search for the logs that are generated by a specific rule, from the Security Policy or from the Logs & Events > Logs tab.

To see logs generated by a rule (from the Security Policy)

- 1. In SmartConsole, go to the **Security Policies** view.
- 2. In the Access Control Policy or Threat Prevention Policy, select a rule.
- 3. In the bottom pane, click one of these tabs to see:
 - Logs By default, shows the logs for the *Current Rule*. You can filter them by Source, Destination, Blade, Action, Service, Port, Source Port, Rule (Current rule is the default), Origin, User, or Other Fields.
 - History (Access Control Policy only) List of rule operations (Audit logs) related to the rule in chronological order, with the information about the rule type and the administrator that made the change.

To see logs generated by a rule (by Searching the Logs)

- 1. In SmartConsole, go to the Security Policies view.
- 2. In the Access Control Policy or Threat Prevention Policy, select a rule.
- 3. Right-click the rule number and select Copy Rule UID.
- 4. In the Logs & Events > Logs tab, search for the logs in one of these ways:
 - Paste the Rule UID into the query search bar and press Enter.
 - For faster results, use this syntax in the query search bar:

layer_uuid_rule_uuid:*_<UID>

For example, paste this into the query search bar and press Enter:

layer_uuid_rule_uuid:*_46f0ee3b-026d-45b0-b7f0-5d71f6d8eb10

Policy Installation History

How to work with the policy installation history

In the Installation History you can choose a Security Gateway, a date and time when the Policy was installed, and:

- See the revisions that were installed on the Security Gateway and who installed the Policy.
- See the changes that were installed and who made the changes.
- Revert to a specific version, and install the last "good" Policy.

To work with the Policy installation history:

- 1. In SmartConsole, go to Security Policies.
- 2. From the Access Tools or the Threat Prevention Tools, select Installation History.
- 3. In the **Gateways** section, select a Security Gateway.
- 4. In the **Policy Installation History** section, select an installation date.
- 5. Perform the applicable action:
 - To see the revisions that were installed and who made them:
 Click View installed changes.
 - To see the changes that were installed and who made them : Click View.
 - To revert to a specific version of the policy:

Click Install specific version.

Concurrent Install Policy

Starting from R81, one administrator or more can run *different* policy installation tasks on multiple gateways at the same time. In earlier versions, you can only run the *same* policy installation task on multiple gateways at the same time.

Concurrent Install Policy only supports the Access Control and Threat Prevention policies. It does not support the Desktop and QoS policies.

The maximum number of policy installation tasks (of different policies) that can run at the same time is 5. If more than 5 policy installation requests are sent, any request beyond the first 5 gets in a queue.

The running and the queued tasks appear in the **Recent Tasks** window at the bottom left of your screen.

Note - In the first installation, you cannot install both the Access Control and Threat Prevention policies on the same gateway at the same time. You must install one and then the other.

Accelerated Install Policy

R81 introduces the Accelerated Install Policy feature for the Access Control policy. When the Access Control policy installation is accelerated, the installation duration is decreased significantly.

Policy installation is accelerated depending on the changes that were made to the Access Control policy since the last installation.

For example, creating a Host object and adding it to an Access Control rule triggers *accelerated* policy installation.

For more information about accelerated install policy and a detailed list on the events that trigger accelerated policy installation, see $\frac{sk169096}{sk169096}$.

Creating an Access Control Policy

This section provides the instructions for working with Access Control Policies.

Introducing the Unified Access Control Policy

Define one, unified Access Control Policy. The Access Control Policy lets you create a simple and granular Rule Base that combines all these Access Control features:

- Firewall Control access to and from the internal network.
- Application & URL Filtering Block applications and sites.
- Content Awareness Restrict the Data Types that users can upload or download.
- IPsec VPN and Mobile Access Configure secure communication with Site-to-Site and Remote Access VPN.
- Identity Awareness Identify users, computers, and networks.

There is no need to manage separate Rule Bases. For example, you can define one, intuitive rule that: Allows users in specified networks, to use a specified application, but prevents downloading files larger than a specified size. You can use all these objects in one rule:

- Security Zones
- Services
- Applications and URLs
- Data Types
- Access Roles

Information about these features is collected in one log:

- Network
- Protocol
- Application
- User
- Accessed resources
- Data Types

The Columns of the Access Control Rule Base

These are the columns of the rules in the Access Control policy. Not all of these are shown by default. To select a column that does not show, right-click on the header of the Rule Base, and select it.

Column	Description
No	Rule number in the Rule Base Layer.
Hits	Number of times that connections match a rule. See "Analyzing the Rule Base Hit Count" on page 400.
Name	Name that the system administrator gives this rule.
Source Destination	 Network objects that define: Where the traffic starts The destination of the traffic See "Source and Destination Column" on the next page.
VPN	The VPN Community to which the rule applies. See "VPN Column" on the next page.
Services & Applications	Services, Applications, Categories, and Sites. If Application & URL Filtering is not enabled, only Services show. See "Services & Applications Column" on page 330.
Content	The data asset to protect, for example, credit card numbers or medical records. You can set the direction of the data to Download Traffic (into the organization), Upload Traffic (out of the organization), or Any Direction. See "Content Column" on page 334.
Action	Action that is done when traffic matches the rule. Options include: Accept, Drop, Ask, Inform (UserCheck message), Inline Layer, and Reject. See "Actions" on page 336.
Track	Tracking and logging action that is done when traffic matches the rule. See " <i>Tracking Column</i> " on page 338.
Install On	Network objects that will get the rule(s) of the policy. See "Installing the Access Control Policy" on page 396.
Time	Time period that this rule is enforced.

Column	Description
Comment	An optional field that lets you summarize the rule.

Source and Destination Column

In the Source and Destination columns of the Access Control Policy Rule Base, you can add **Network** objects including groups of all types.

Here are some of the Network objects you can include:

- Network (see "Networks" on page 284 and "Network Groups" on page 285)
- Host
- Zones (see "Security Zones" on page 305)
- Dynamic Objects (see "Dynamic Objects" on page 302)
- Domain Objects (see "Domains" on page 294)
- Access Roles
- Updatable Objects (see "Updatable Objects" on page 295)

To Learn More About Network Objects

You can add network objects to the **Source** and **Destination** columns of the Access Control Policy. See "*Managing Objects*" on page 279.

VPN Column

You can configure rules for Site-to-Site VPN, Remote Access VPN, and the Mobile Access Portal and clients.

To make a rule for a VPN Community, add a Site-to-Site Community or a Remote Access VPN Community object to this column, or select **Any** to make the rule apply to all VPN Communities.

When you enable Mobile Access on a Security Gateway, the Security Gateway is automatically added to the **RemoteAccess** VPN Community. Include that Community in the **VPN** column of the rule or use **Any** to make the rule apply to Mobile Access Security Gateways. If the Security Gateway was removed from the VPN Community, the **VPN** column must contain **Any**.

IPsec VPN

The IPsec VPN solution lets the Security Gateway encrypt and decrypt traffic to and from other Security Gateways and clients. Use SmartConsole to easily configure VPN connections between Security Gateways and remote devices.

For Site-to-Site Communities, you can configure Star and Mesh topologies for VPN networks, and include third-party gateways.

The VPN tunnel guarantees:

- Authenticity Uses standard authentication methods
- Privacy All VPN data is encrypted
- Integrity Uses industry-standard integrity assurance methods

IKE and IPsec

The Check Point VPN solution uses these secure VPN protocols to manage encryption keys, and send encrypted packets. IKE (Internet Key Exchange) is a standard key management protocol that is used to create the VPN tunnels. IPsec is protocol that supports secure IP communications that are authenticated and encrypted on private or public networks.

Mobile Access to the Network

Check Point Mobile Access lets remote users easily and securely use the Internet to connect to internal networks. Remote users start a standard HTTPS request to the Mobile Access Security Gateway, and authenticate with one or more secure authentication methods.

The Mobile Access Portal lets mobile and remote workers connect easily and securely to critical resources over the internet. Check Point Mobile Apps enable secure encrypted communication from unmanaged smartphones and tablets to your corporate resources. Access can include internal apps, email, calendar, and contacts.

To include access to Mobile Access applications in the Rule Base, include the **Mobile Application** in the **Services & Applications** column.

To give access to resources through specified remote access clients, create Access Roles for the clients and include them in the **Source** column of a rule.

To Learn More About VPN

To learn more about Site-to-Site VPN and Remote Access VPN, see these guides:

- R82 Site to Site VPN Administration Guide
- <u>R82 Remote Access VPN Administration Guide</u>
- <u>R82 Mobile Access Administration Guide</u>

Services & Applications Column

In the **Services & Applications** column of the Access Control Rule Base, define the applications, sites, and services that are included in the rule. A rule can contain one or more:

- Services
- Applications
- Mobile Applications for Mobile Access
- Web sites
- Default categories of Internet traffic
- Custom groups or categories that you create, that are not included in the Check Point Application Database.

Service Matching

The Security Gateway identifies (*matches*) a service according to *IP protocol*, TCP and UDP *port number*, and *protocol signature*.

To make it possible for the Security Gateway to match services by protocol signature, you must enable **Application & URL Filtering** on the Security Gateway and on the Ordered Layer (see "*Enabling Access Control Features*" *on page 363*).

You can configure TCP and UDP services to be matched by source port.

Application Matching

If an application is *allowed* in the policy, the rule is matched only on the **Recommended** services of the application. This default setting is more secure than allowing the application on all services. For example: a rule that allows Facebook, allows it only on the Application Control **Web Browsing Services**: http, https, HTTP_proxy, and HTTPS_proxy.

If an application is *blocked* in the policy, it is blocked on all services. It is therefore blocked on all ports.

You can change the default match settings for applications.

Configuring Matching for an Allowed Application

You can configure how a rule matches an application or category that is *allowed* in the policy. You can configure the rule to match the application in one of these ways:

- On any service
- On a specified service

To do this, change the **Match Settings** of the application or category. The application or category is changed everywhere that it is used in the policy.

To change the matched services for an allowed application or category:

- 1. In a rule which has applications or categories in the **Services & Applications** column, double-click an application or category.
- 2. Select Match Settings.
- 3. Select an option:
 - The default is **Recommended** services. The defaults for Web services are the Application Control **Web Browsing Services**.
 - To match the application with all services, click **Any**.
 - To match the application on specified services, click Customize, and add or remove services.
 - To match the application with all services and exclude specified services, click Customize, add the services to exclude, and select Negate.
- 4. Click OK.

Configuring Matching for Blocked Applications

By default, if an application is *blocked* in the policy, it is blocked on all services. It is therefore blocked on all ports.

You can configure the matching for blocked applications so that they are matched on the recommended services. For Web applications, the recommended services are the *Application Control Web browsing services*.

If the match settings of the application are configured to **Customize**, the blocked application is matched on the customized services service. *It is not matched on all ports.*

To configure matching for blocked applications:

- In SmartConsole, go to Manage & Settings > Blades > Application & URL Filtering > Advanced Settings > Application Port Match
- 2. Configure Match application on 'Any' port when used in 'Block' rule:
 - Selected This is the default. If an application is *blocked* in the Rule Base, the application is matched to *Any* port.
 - Not selected If an application is *blocked* in the Rule Base, the application is matched to the services that are configured in the application object of the application. However, some applications are still matched on Any. These are applications (Skype, for example) that do not limit themselves to a standard set of services.

Application - Match Setting	Checkbox: Match web application on 'Any' port when used in 'Block' rule	Blocked Application is Matched on Service
Recommended services (default)	Selected (default)	Any
Recommended services (default)	Not selected	Recommended services
Customize	Not relevant	Customized
Any	Not relevant	Any

Summary of Application Matching in a "Block" Rule

Adding Services, Applications, and Sites to a rule

You can add services, applications and sites to a rule.

Note - Rules with applications or categories do not apply to connections from or to the Security Gateway.

To add services, applications or sites to a rule:

- 1. In the Security Policies view of SmartConsole, go to the Access Control Policy.
- 2. To add applications to a rule, select a Layer with **Applications and URL Filtering** enabled.
- 3. Right-click the Services & Applications cell for the rule and select Add New Items.
- 4. Search for the services, sites, applications, or categories.
- 5. Click the + next to the ones you want to add.

Creating Custom Applications, Categories, and Groups

You can create custom applications, categories or groups, which are not included in the Check Point Application Database.

To create a new application or site:

- 1. In the Security Policies view of SmartConsole, go to the Access Control Policy.
- 2. Select a Layer with Applications and URL Filtering enabled.
- 3. Right-click the Services & Applications cell for the rule and select Add New Items.

The Application viewer window opens.

- 4. Click New > Custom Applications/Site > Application/Site.
- 5. Enter a name for the object.
- The default matched services for a custom application or site are Web Browsing Services. Starting from <u>R82 SmartConsole Releases</u> Build 1055 or higher, you can change the matched services for a custom application or site:
 - a. In the Match Settings tab, go to Services and select Customize.
 - b. Click the + sign.
 - c. From the list that opens, select the required services.
- 7. Enter one or more URLs.

If you used a regular expression in the URL, click **URLs are defined as Regular Expressions**.

Note - If the application or site URL is defined as a regular expression you must use the correct syntax. See <u>sk165094</u>.

8. Click OK.

To create a custom category

- 1. In the Security Policies view of SmartConsole, go to the Access Control Policy.
- 2. Select a Layer with Applications and URL Filtering enabled.
- 3. Right-click the Services & Applications cell for the rule and select Add New Items.

The Application viewer window opens.

- 4. Click New > Custom Applications/Site > User Category.
- 5. Enter a name for the object.
- 6. Enter a description for the object.
- 7. Click OK.

Content Column

You can add Data Types to the Content column of rules in the Access Control Policy.

To use the Content column, you must enable **Content Awareness**, in the General Properties page of the Security Gateway, and on the Layer.

A Data Type is a classification of data. The Security Gateway classifies incoming and outgoing traffic according to Data Types, and enforces the Policy accordingly.

You can set the direction of the data in the Policy to **Download Traffic** (into the organization), **Upload Traffic** (out of the organization), or **Any Direction**.

There are two kinds of Data Types: *Content Types* (classified by analyzing the file content) and *File Types* (classified by analyzing the file ID).

Content Type examples:

- PCI credit card numbers
- HIPAA Medical Records Number MRN
- International Bank Account Numbers IBAN
- Source Code JAVA
- U.S. Social Security Numbers According to SSA
- Salary Survey Terms

File type examples:

- Viewer File PDF
- Executable file
- Database file
- Document file
- Presentation file
- Spreadsheet file



- The Content Awareness Software Blade supports HTTP, HTTPS, SMTP, and FTP protocols on all ports. It is fully integrated with the Access Control unified Rule Base.
- The Content Awareness Software Blade does not match Binary Certificate *.cer files to the 'Certificates and Private Keys' Data Type.
- Content Awareness and Data Loss Prevention (DLP) both use Data Types. However, they have different features and capabilities. They work independently, and the Security Gateway enforces them separately.
- If an inline layer has Archive File in the content column of the parent rule, and another value in the content column in one of the sub-rules (for example: Presentation File), then if the matched archive includes the other value (in this example: a presentation file), the rule is not matched. Use a regular rule for both content types.
- If a content column of a rule includes the Compound Data Type Group or Traditional Data Type Group with an Archive File Data Type and another Data Type (for example: PCI - Credit Card Numbers), then if an archive file which contains a file with credit cards is uploaded or downloaded, the rule is not matched.
- If a rule with Archive File in the content column is matched, and a lower rule in the Rule Base has a Data Type which is contained in the archive file, then the lower rule in the Rule Base is matched as well.

Limitations:

- Content Awareness supports more than 60 character sets (charsets) for text files, including Japanese, Korean, Greek, and Arabic. If the inspected traffic does not include a supported charset, Content Awareness uses UTF-8 for decoding. To see the list of supported charsets, and to learn how to change the default charset, see <u>sk116155</u>.
- Content Awareness supports Data Types based on file name. For specific HTTP traffic where the file name is not part of the URL or content-disposition header, the file name may be incorrect.

To learn more about the Data Types, open the Data Type object in SmartConsole and press the **?** button (or **F1** key) to see the Help.

To learn more about DLP, see the <u>R82 Data Loss Prevention Administration Guide</u>.

Actions

Action	Meaning
Accept	Accepts the traffic

Action	Meaning
Drop	Drops the traffic. The Security Gateway does not send a response to the originating end of the connection and the connection eventually does a time-out. If no UserCheck object is defined for this action, no page is displayed.
Ask	Asks the user a question and adds a confirmatory check box, or a reason box. Uses a UserCheck object.
Inform	Sends a message to the user attempting to access the application or the content. Uses a UserCheck object.

To see these actions, right-click and select More:

Reject	Rejects the traffic. The Security Gateway sends an RST packet to the originating end of the connection and the connection is closed.		
UserCheck Frequency	Configure how often the user sees the configured message when the action is ask, inform, or block.		
Confirm UserCheck	 Select the action that triggers a UserCheck message: Per rule - UserCheck message shows only once when traffic matches a rule. Per category - UserCheck message shows for each matching category in a rule. Per application/Site - UserCheck message shows for each matching application/site in a rule. Per Data type - UserCheck message shows for each matching data type. 		
Limit	 Limits the bandwidth that is permitted for a rule. Add a Limit object to configure a maximum throughput for uploads and downloads. Important: After policy installation, a bandwidth limit is not enforced on a connection that is matched to an Access Control rule with the Action "Limit" in one of these scenarios: The 'Keep all connections' option is selected in the security object The 'Keep connections open after the policy has been installed' option is selected in the Service object used in this rule 		

Action	Meaning
Enable Identity Captive Portal	 Redirects HTTP traffic to an authentication (captive) portal. After the user is authenticated, new connections from this source are inspected without requiring authentication. Important - A rule that drops traffic, with the Source and Destination parameters defined as Any, also drops traffic to and from the Captive Portal.

Tracking Column

These are some of the **Tracking** options:

- None Do not generate a log.
- Log -This is the default Track option. It shows all the information that the Security Gateway used to match the connection.
- Accounting Select this to update the log at 10 minute intervals, to show how much data has passed in the connection: Upload bytes, Download bytes, and browse time.

To Learn More About Tracking

To learn more about Tracking options, see the <u>*R82 Logging and Monitoring Administration</u></u> <u><i>Guide*.</u></u>

Rule Matching in the Access Control Policy

The Security Gateway determines the rule to apply to a connection. This is called *matching* a connection. Understanding how the Security Gateway matches connections will help you:

- Get better performance from the Rule Base.
- Understand the logs that show a matched connection.

Examples of Rule Matching

These example Rule Bases show how the Security Gateway matches connections.

Note that these Rule Bases intentionally do not follow the best practices for Access Control Rules (see *"Best Practices for Access Control Rules" on page 371*). This is to make the explanations of rule matching clearer.

Rule Base Matching - Example 1

For this Rule Base:

No	Source	Destination	Services & Applications	Content	Action
1	InternalZone	Internet	ftp-pasv	Download executable file	Drop
2	Any	Any	Any	Executable file	Accept
3	Any	Any	Gambling (Category)	Any	Drop
4	Any	Any	Any	Any	Accept

This is the matching procedure for an FTP connection:

Part of connection	Security Gateway action	Inspection result
SYN	Run the Rule Base: Look for the first rule that matches: Rule 1 - Match.	Final match (drop on rule 1). Shows in the log. The Security Gateway does not turn on the inspection engines for the other rules.

Rule Base Matching - Example 2

Services & No. Source Destination Content Action Applications 1 InternalZone Internet Download Drop Any executable file 2 Any Any Gambling Drop Any (category) 3 Any Any ftp Any Drop 4 Any Any Any Any Accept

For this Rule Base:

This is the matching procedure when browsing to a file sharing Web site. Follow the rows from top to bottom. Follow each row from left to right:

Part of connection	Security Gateway action	Inspection result
SYN	Run the Rule Base. Look for the first rule that matches: Rule 1 - Possible match. Rule 2 - Possible match. Rule 3 - No match. Rule 4 - Match.	Possible match (Continue to inspect the connection).
HTTP Header	 The Security Gateway turns on inspection engines to examine the data in the connection. In this example turn on the: URL Filtering engine - Is it a gambling site? Content Awareness engine - Is it an executable file? 	Application: File sharing (category). Content: Don't know yet.

Part of connection	Security Gateway action	Inspection result	
	Optimize the Rule Base matching. Look for the first rule that matches: Rule 1 - Possible match. Rule 2 - No match. Rule 3 - No match. Rule 4 - Match.	Possible match (Continue to inspect the connection).	
HTTP Body	Examine the file.	Data: PDF file.	
	Optimize the Rule Base matching. Look for the first rule that matches: Rule 1 - No match. Rule 2 - No match. Rule 3 - No match. Rule 4 - Match.	Final match (accept on rule 4). Shows in the log.	

Rule Base Matching - Example 3

For this Rule Base:

No.	Source	Destination	Services & Applications	Content	Action
1	InternalZone	Internet	Any	Download executable file	Drop
2	Any	Any	Gambling (Category)	Any	Drop
3	Any	Any	Any	Any	Accept

This is the matching procedure when downloading an executable file from a business Web site. Follow the rows from top to bottom. Follow each row from left to right:

Part of connection	Security Gateway action	Inspection result
SYN	Run the Rule Base. Look for the first rule that matches: Rule 1 - Possible match. Rule 2 - Possible match. Rule 3 - Match.	Possible match (Continue to inspect the connection).
HTTP Header	 The Security Gateway turns on inspection engines to examine the content in the connection. In this example turn on the: URL Filtering engine - Is it a gambling site? Content Awareness engine - Is it an executable file? 	Application: Business (Category). Content: Don't know yet.
	Optimize the Rule Base matching. Look for the first rule that matches: Rule 1 - Possible match. Rule 2 - No match. Rule 3 - Match.	Possible match (Continue to inspect the connection).
HTTP Body	Examine the file.	Content: Executable file.
	Optimize the Rule Base matching. Look for the first rule that matches: Rule 1 - Match. Rule 2 - No match. Rule 3 - Match.	Final match (drop on rule 1). Shows in the log.

The matching examples show that:

The Security Gateway sometimes runs the Rule Base more than one time. Each time it runs, the Security Gateway optimizes the matching, to find the first rule that applies to the connection.

- If the rule includes an application, or a site, or a service with a protocol signature (in the Application and Services column), or a Data Type (in the Content column), the Security Gateway:
 - Turns on one or more inspection engines.
 - Postpones making the final match decision until it has inspected the body of the connection.
- The Security Gateway searches for the first rule that applies to (*matches*) a connection. If the Security Gateway does not have all the information it needs to identify the matching rule, it continues to inspect the traffic.

Creating a Basic Access Control Policy

A Security Gateway controls access to computers, clients, servers, and applications using a set of rules that make up an Access Control Rule Base. You need to configure a Rule Base with secure Access Control and optimized network performance.

A strong Access Control Rule Base:

- Allows only authorized connections and prevents vulnerabilities in a network.
- Gives authorized users access to the correct internal resources.
- Efficiently inspects connections.

Basic Rules

Best Practice - These are basic Access Control rules we recommend for all Rule Bases:

- Stealth rule that prevents direct access to the Security Gateway
- Cleanup rule that drops all traffic that is not matched by the earlier rules in the policy

Use Case - Basic Access Control

This use case shows a Rule Base for a simple Access Control security policy. (The **Hits**, **VPN** and **Content** columns are not shown.)

No	Name	Source	Destinatio n	Services & Applicatio ns	Action	Track	Install On
1	Admin Access to Security Gateway s	Admins (Access Role)	Group of Security Gateways	Any	Accept	Log	Policy Targets
2	Stealth	Any	Group of Security Gateways	Any	Drop	Alert	Policy Targets
3	Critical subnet	Internal	Finance HR R&D	Any	Accept	Log	CorpGW
4	Tech support	TechSuppo rt	Remote1- web	HTTP	Accept	Alert	Remote1G W

No	Name	Source	Destinatio n	Services & Applicatio ns	Action	Track	Install On
5	DNS server	Any	DNS	Domain UDP	Accept	None	Policy Targets
6	Mail and Web servers	Any	DMZ	HTTP HTTPS SMTP	Accept	Log	Policy Targets
7	SMTP	Mail	NOT Internal net group	SMTP	Accept	Log	Policy Targets
8	DMZ & Internet	IntGroup	Any	Any	Accept	Log	Policy Targets
9	Cleanup rule	Any	Any	Any	Drop	Log	Policy Targets

Explanations for rules:

Rule	Explanation
1	Admin Access to Gateways - SmartConsole administrators are allowed to connect to the Security Gateways.
2	Stealth - All internal traffic that is NOT from the SmartConsole administrators to one of the Security Gateways is dropped. When a connection matches the Stealth rule, an alert window opens in SmartView Monitor.
3	Critical subnet - Traffic from the internal network to the specified resources is logged. This rule defines three subnets as critical resources: Finance, HR, and R&D.
4	Tech support - Allows the Technical Support server to access the Remote-1 web server which is behind the Remote-1 Security Gateway. Only HTTP traffic is allowed. When a packet matches the Tech support rule, the Alert action is done.
5	DNS server - Allows UDP traffic to the external DNS server. This traffic is not logged.
6	Mail and Web servers - Allows incoming traffic to the mail and web servers that are located in the DMZ. HTTP, HTTPS, and SMTP traffic is allowed.

Rule	Explanation
7	SMTP - Allows outgoing SMTP connections to the mail server. Does not allow SMTP connections to the internal network, to protect against a compromised mail server.
8	DMZ and Internet - Allows traffic from the internal network to the DMZ and Internet.
9	Cleanup rule - Drops all traffic that does not match one of the earlier rules.

Use Case - Inline Layer for Each Department

This use case shows a basic Access Control Policy with a sub-policy for each department. The rules for each department are in an Inline Layer. An Inline Layer is independent of the rest of the Rule Base. You can delegate ownership of different Layers to different administrators.

No	Name	Source	Destinati on	Services & Applicatio ns	Conten t	Action	Track
1	Critical subnet	Internal	Finance HR	Any	Any	Accept	Log
2	SMTP	Mail	NOT internal network (Group)	smtp	Any	Accept	Log
3	R&D departme nt	R&D Roles	Any	Any	Any	TechSupp ort Layer	N/A
3.1	R&D servers	Any	R&D servers (Group) QA network	Any	Any	Accept	Log
3.2	R&D source control	InternalZo ne	Source control servers (Group)	ssh http https	Any	Accept	Log

No	Name	Source	Destinati on	Services & Applicatio ns	Conten t	Action	Track
3.X	Cleanup rule	Any	Any	Any	Any	Drop	Log
4	QA departme nt	QA network	Any	Any	Any	QA Layer	N/A
4.1	Allow access to R&D servers	Any	R&D Servers (Group)	Web Services	Any	Accept	Log
4.Y	Cleanup rule	Any	Any	Any	Any	Drop	Log
5	Allow all users to access employee portal	Any	Employee portal	Web Services	Any	Accept	None
9	Cleanup rule	Any	Any	Any	Any	Drop	Log

Explanations for rules:

Rules	Explanation
1 2	General rules for the whole organization.

Rules	Explanation
3 3.1 3.2 3.X	An Inline Layer for the R&D department. Rule 3 is the parent rules of the Inline Layer. The Action is the name of the Inline Layer. If a packet does not match on parent rule 3: Matching continues to the next rule outside the Inline Layer (rule 4). If a packet matches on parent rule 3: Matching continues to 3.1, first rule inside the Inline Layer. If a packet matches on this rule, the rule action is done on the packet. If a packet does not match on rule 3.1, continue to the next rule inside the Inline Layer, rule 3.2. If there is no match, continue to the remaining rules in the Inline Layer means one or more rules. The packet is matched only inside the inline layer. It never leaves the inline layer, because the inline layer has an implicit cleanup rule. It is not matched on rules 4, 5 and the other rules in the Ordered Layer. Rule 3.X is a cleanup rule. It drops all traffic that does not match one of the earlier rules in the Inline Layer. This is a default explicit rule. You can change or delete it. Best Practice - Have an explicit cleanup rule as the last rule in each Inline Layer and Ordered Layer.
4 4.1 4.Y	Another Inline Layer, for the QA department.
5	More general rules for the whole organization.
	One or more rules.
9	Cleanup rule - Drop all traffic that does not match one of the earlier rules in the Ordered Layer. This is a default explicit rule. You can change or delete it. Best Practice - Have an explicit cleanup rule as the last rule in each Inline Layer and Ordered Layer.

Default Cell Values

Starting from R81.10:

The default value for the Source, Destination, and Services & Applications columns in a new rule is "None".

In versions R81 and lower, the default value for these columns in a new rule is "Any".

• The default value a cell gets after removing the last object from the cell is "None".

The "last object" is the object that remained the last object in the cell after all other objects were removed.

In versions R81 and lower, the default value for the last object deleted from a cell is "Any".

To configure the default values for the Source, Destination, and Services & Applications columns:

- 1. In the Manage & Settings view > Policy Settings > Rule Base Cell Settings.
- 2. In Security Access Defaults, select the values for the Source, Destination and Services & Applications columns.

To configure the value for the Source, Destination, and Services & Applications columns after removing the last object from a cell:

- 1. In the Manage & Settings view > Policy Settings > Rule Base Cell Settings.
- 2. In the After removing the last object in a cell section, select one of these options:
 - Add 'None' to the cell After removing the last object from a cell, the value in the cell becomes "None".
 - Add the object according to the Rule Base cell default After removing the last object in a cell, the value in the cell becomes as configured in the Security Access Defaults section.

Note - Right-click a cell to switch between "Any" and "None".

Enforcement of Rules with the Value "None"

On Security Gateways with versions from R80.10 to R81, the policy is installed without rules that contain the value "**None**" in one or more cells.

To configure the message which appears when a rule has "None":

Go to Manage & Settings > Policy Settings > Rule Base Cell Settings > 'None' object behavior

Upgrading of a Management Server from R81 and Lower Versions

During an upgrade from R81 and lower versions:

- Default value for the Source, Destination, and Services & Applications columns remains "Any".
- Default value after the last object in a cell is removed becomes "None".

Creating Application Control and URL Filtering **Rules**

Create and manage the Policy for Application Control and URL Filtering in the Access Control Policy, in the Access Control view of SmartConsole. Application Control and URL Filtering rules define which users can use specified applications and sites from within your organization and what application and site usage is recorded in the logs.

To learn which applications and categories have a high risk, look through the Application Wiki in the Access Tools part of the Security Policies view. Find ideas for applications and categories to include in your Policy.

To see an overview of your Access Control Policy and traffic, see the Access Control view in Logs & Events > New Tab > Views.



Best Practice - Do not use Application Control and URL Filtering in the same rule, this may lead to wrong rule matching. Use Application Control and URL Filtering in separate rules. This makes sure that the URL Filtering rule is used as soon as the category is identified. For more information, see sk174045.

If your Security Gateways / Cluster Members are not connected to the Internet directly, they use the Management Server as a proxy server to update the Application Control package and URL Filtering package.

The feature is enabled by default.

To disable the feature, run in the Expert mode on the Security Gateway / each Cluster Member

cpprod util FwSetParam CP BLADE UPDATE PROXY MGMT DISABLE 1

To enable the feature again, run in the Expert mode on the Security Gateway / each Cluster Member:

cpprod util FwSetParam CP BLADE UPDATE PROXY MGMT DISABLE 0

Monitoring Applications

Scenario: I want to monitor all Facebook traffic in my organization. How can I do this?

To monitor all Facebook application traffic:

- 1. In the Security Policies view of SmartConsole, go to the Access Control Policy.
- 2. Select a Layer with Applications and URL Filtering enabled.

- 3. Click one of the **Add rule** toolbar buttons to add the rule in the position that you choose in the Rule Base. The first rule matched is applied.
- 4. Create a rule that includes these components:
 - Name Give the rule a name, such as Monitor Facebook.
 - Source Keep it as Any so that it applies to all traffic from the organization.
 - **Destination** Keep it as **Internet** so that it applies to all traffic going to the internet or DMZ.
 - Services & Applications Click the plus sign to open the Application viewer. Add the Facebook application to the rule:
 - a. Start to type "face" in the Search field. In the Available list, see the **Facebook** application.
 - b. Click each item to see more details in the description pane.
 - c. Select the items to add to the rule.
 - Note Applications are matched by default on their **Recommended** services. You can change this (see *"Configuring Matching for an Allowed Application" on page 331*). Each service runs on a specific port. The recommended **Web Browsing Services** are http, https, HTTP_proxy, and HTTPS_proxy.
 - Action Select Accept
 - Track Select Log
 - Install On Keep it as Policy Targets for or all Security Gateways, or choose specific Security Gateways, on which to install the rule

The rule allows all Facebook traffic but logs it. You can see the logs in the Logs & Events view, in the Logs tab. To monitor how people use Facebook in your organization, see the Access Control view (SmartEvent Server required).

Blocking Applications and Informing Users

Scenario: I want to block pornographic sites in my organization, and tell the user about the violation. How can I do this?

To block an application or category of applications and tell the user about the policy violation:

- 1. In the Security Policies view of SmartConsole, go to the Access Control Policy.
- 2. Choose a Layer with **Applications and URL Filtering** enabled.
- 3. Create a rule that includes these components:

- Services & Applications Select the Pornography category.
- Action Drop, and a UserCheck Blocked Message Access Control

The message informs users that their actions are against company policy and can include a link to report if the website is included in an incorrect category.

Track - Log

Note - This Rule Base example contains only those columns that are applicable to this subject.

Name	Source	Destinatio n	Services & Application s	Action	Track	Install On
Block Porn	Any	Internet	Pornograph y (category)	Drop Blocked Messag e	Log	Policy Targets

The rule blocks traffic to pornographic sites and logs attempts to access those sites. Users who violate the rule receive a UserCheck message that informs them that the application is blocked according to company security policy. The message can include a link to report if the website is included in an incorrect category.

Important - A rule that blocks traffic, with the Source and Destination parameters defined as Any, also blocks traffic to and from the Captive Portal.

Limiting Application Traffic

Scenario: I want to limit my employees' access to streaming media so that it does not impede business tasks.

If you do not want to block an application or category, there are different ways to set limits for employee access:

- Add a Limit object to a rule to limit the bandwidth that is permitted for the rule.
- Add one or more **Time** objects to a rule to make it active only during specified times.

The example rule below:

- Allows access to streaming media during non-peak business hours only.
- Limits the upload throughput for streaming media in the company to 1 Gbps.

To create a rule that allows streaming media with time and bandwidth limits:

- 1. In the Security Policies view of SmartConsole, go to the Access Control Policy.
- 2. Choose a Layer with Applications and URL Filtering enabled.
- 3. Click one of the **Add Rule** toolbar buttons to add the rule in the position that you choose in the Rule Base.
- 4. Create a rule that includes these components:
 - Services & Applications Media Streams category.
 - Note Applications are matched on their Recommended services, where each service runs on a specific port, such as the default Application Control Web browsing Services: http, https, HTTP_ proxy, HTTPS_proxy and quic. To change this, see "Services & Applications Column" on page 330.
 - Action Click More and select Action: Accept, and a Limit object.
 - Time Add a Time object that specifies the hours or time period in which the rule is active.

Note - The **Time** column is not shown by default in the Rule Base table. To see it, right-click on the table header and select **Time**.

Name	Sourc e	Destinati on	Services and Applicati ons	Action	Trac k	Insta II On	Tim e
Limit Streami ng Media	Any	Internet	Media Streams (Categor y)	Accept Uploa d_ 1Gbps	Log	All	Off- Wor k

Important:

- In ClusterXL Load Sharing modes, the specified bandwidth limit is divided between all configured Cluster Members, regardless of the cluster state. For example, if a maximum limit requirement is 30 Gbps, and there are three Cluster Members, you must configure the Limit object in the rule to 30 Gbps / 3 = 10 Gbps.
- In a Scalable Platform Security Group, the specified bandwidth limit is divided between all Security Group Members, regardless of their state. For example, if a maximum limit requirement is 30 Gbps, and there are three Security Group Members, you must configure the Limit object in the rule to 30 Gbps / 3 = 10 Gbps.

Using Identity Awareness Features in Rules

Scenario: I want to allow a Remote Access application for a specified group of users and block the same application for other users. I also want to block other Remote Access applications for everyone. How can I do this?

If you enable Identity Awareness on a Security Gateway, you can use it together with Application Control to make rules that apply to an *access role*. Use access role objects to define users, machines, and network locations as one object.

In this example:

- You have already created an Access Role Identified_Users that represents all identified users in the organization. You can use this to allow access to applications only for users who are identified on the Security Gateway.
- You want to allow access to the Radmin Remote Access tool for all identified users.
- You want to block all other Remote Access tools for everyone within your organization. You also want to block any other application that can establish remote connections or remote control.

To do this, add two new rules to the Rule Base:

- 1. Create a rule and include these components:
 - Source The Identified_Users access role
 - Destination -Internet
 - Services & Applications Radmin
 - Action -Accept
- 2. Create another rule below and include these components:
 - Source Any
 - Destination Internet

- Services & Applications The category: Remote Administration
- Action Block

Name	Source	Destination	Services & Application s	Action	Track	Install On
Allow Radmin to Identified Users	Identified_ Users	Internet	Radmin	Allow	Log	All
Block other Remote Admins	Any	Internet	Remote Administration	Block	Log	All

Notes on these rules:

- Because the rule that allows Radmin is above the rule that blocks other Remote Administration tools, it is matched first.
- The Source of the first rule is the Identified_Users access role. If you use an access role that represents the Technical Support department, then only users from the technical support department are allowed to use Radmin.
- Applications are matched on their Recommended services, where each service runs on a specific port, such as the default Application Control Web browsing services: http, https, HTTP_proxy, HTTPS_proxy, and quic. To change this see Changing Services for Applications and Categories.

For more about Access Roles and Identity Awareness, see the <u>*R82 Identity Awareness</u></u> <u>Administration Guide</u>.</u>*

Blocking Sites

Scenario: I want to block sites that are associated with categories that can cause liability issues. Most of these categories exist in the Application Database but there is also a custom defined site that must be included. How can I do this?

You can do this by creating a *custom group* and adding all applicable categories and the site to it. If you enable Identity Awareness on a Security Gateway, you can use it together with URL Filtering to make rules that apply to an *access role*. Use access role objects to define users, machines, and network locations as one object.

In this example:

- You have already created
 - An Access Role that represents all identified users in the organization (*Identified_Users*).
 - A custom application for a site named *FreeMovies*.

- You want to block sites that can cause liability issues for everyone within your organization.
- You will create a custom group that includes Application Database categories as well as the previously defined custom site named *FreeMovies*.

To create a custom group

- In the Object Explorer, click New > More > Custom Application/Site > Application/Site Group.
- 2. Give the group a name. For example, *Liability_Sites*.
- 3. Click + to add the group members:
 - Search for and add the custom application *FreeMovies*.
 - Select Categories, and add the ones you want to block (for example Anonymizer, Critical Risk, and Gambling)
 - Click Close
- 4. Click OK.

You can now use the *Liability_Sites* group in the Access Control Rule Base.

In the Rule Base, add a rule similar to this

In the Security Policies view of SmartConsole, go to the Access Control Policy.

- Source The Identified_Users access role
- Destination Internet
- Services & Applications Liability_Sites
- Action Drop

Note - Applications are matched on their Recommended services, where each service runs on a specific port, such as the default Application Control Web Browsing Services: http, https, HTTP_proxy, and HTTPS_proxy. To change this see Changing Services for Applications and Categories.

Name	Source	Destination	Services & Applications	Action	Track
Block sites that may cause a liability	Identified_ Users	Internet	Liability_Sites	Drop	Log

Blocking URL Categories

Scenario: I want to block pornographic sites. How can I do this?

You can do this by creating a rule that blocks all sites with pornographic material with the *Pornography category*. If you enable Identity Awareness on a Security Gateway, you can use it together with URL Filtering to make rules that apply to an *access role*. Use access role objects to define users, machines, and network locations as one object.

In this example:

- You have already created an Access Role (*Identified_Users*) that represents all identified users in the organization.
- You want to block sites related to pornography.

The procedure is similar to "Blocking Applications and Informing Users" on page 352.

Ordered Layers and Inline Layers

A policy is a set of rules that the Security Gateway enforces on incoming and outgoing traffic. There are different policies for Access Control and for Threat Prevention.

You can organize the Access Control rules in more manageable subsets of rules using Ordered Layers and Inline Layers.

The Need for Ordered Layers and Inline Layers

Ordered Layers and Inline Layers helps you manage your cyber security more efficiently. You can:

- Simplify the Rule Base, or organize parts of it for specific purposes.
- Organize the Policy into a hierarchy, using Inline Layers, rather than having a flat Rule Base.

An Inline Layer is a *sub-policy* which is independent of the rest of the Rule Base.

- Reuse Ordered Layers in multiple Policy packages, and reuse Inline Layers in multiple Layers.
- Simplify the management of the Policy by delegating ownership of different Layers to different administrators.
- Improve performance by reducing the number of rules in a Layer.

Order of Rule Enforcement in Inline Layers

The Ordered Layer can contain Inline Layers.

This is an example of an Inline Layer:

No.	Source	Destination	VPN	Services	Action
1					
2	Lab_network	Any	Any	Any	Lab_rules
2.1	Any	Any	Any	https http	Allow
2.2	Any	Any	Any	Any	Drop
3					

The Inline Layer has a parent rule (Rule 2 in the example), and sub rules (Rules 2.1 and 2.2). The Action of the parent rule is the name of the Inline Layer.

If the packet does not match the parent rule of the Inline Layer, the matching continues to the next rule of the Ordered Layer (Rule 3).

If a packet matches the parent rule of the Inline Layer (Rule 2), the Security Gateway checks it against the sub rules:

- If the packet matches a sub rule in the Inline Layer (Rule 2.1), no more rule matching is done.
- If none of the higher rules in the Ordered Layer match the packet, the explicit Cleanup Rule is applied (Rule 2.2). If this rule is missing, the Implicit Cleanup Rule is applied (see "Types of Rules in the Rule Base" on page 365). No more rule matching is done.


Important:

- Always add an explicit Cleanup Rule at the end of each Inline Layer, and make sure that its Action is the same as the Action of the Implicit Cleanup Rule.
- For Security Gateways R80.10 and lower, the second layer behaves like an Application Control policy.

Order of Rule Enforcement in Ordered Layers

When a packet arrives at the Security Gateway, the Security Gateway checks it against the rules in the first Ordered Layer, sequentially from top to bottom, and enforces the first rule that matches a packet.

If the **Action** of the matching rule is **Drop**, the Security Gateway stops matching against later rules in the Policy Rule Base and drops the packet. If the **Action** is **Accept**, the Security Gateway continues to check rules in the next Ordered Layer.



Rem	Description
1	Ordered Layer 1

ltem	Description
2	Ordered Layer 2
3	Ordered Layer 3

If none of the rules in the Ordered Layer match the packet, the explicit **Default Cleanup Rule** is applied. If this rule is missing, the **Implicit Cleanup Rule** is applied (see *"Types of Rules in the Rule Base" on page 365*).

Every Ordered Layer has its own implicit cleanup rule. You can configure the rule to *Accept* or *Drop* in the **Layer settings** (see *"Configuring the Implicit Cleanup Rule" on page 367*).

Important - Always add an explicit **Cleanup Rule** at the end of each Ordered Layer, and make sure that its **Action** is the same as the **Action** of the **Implicit Cleanup Rule**.

Creating an Inline Layer

An Inline Layer is a *sub-policy*, which is independent of the rest of the Rule Base.

The workflow for making an Inline Layer is:

- 1. Create a *parent* rule for the Inline Layer. Make a rule that has one or more properties that are the same for all the rules in the Inline Layer. For example, rules that have the same source, or service, or group of users.
- 2. Create *sub-rules* for the Inline Layer. These are rules that define in more detail what to do if the Security Gateway matches a connection to the parent rule. For example, each sub-rule can apply to specified hosts, or users, or services, or Data Types.

To create an Inline Layer

- 1. Add a rule to the Ordered Layer. This is the *parent* rule.
- 2. In the **Source**, **Destination**, **VPN**, and **Services & Applications** cells, define the match conditions for the Inline Layer.
- 3. Click the Action cell of the rule. Instead of selecting a standard action, select Inline Layer > New Layer.
- 4. The Layer Editor window opens.
- 5. Configure the properties of the Inline Layer:

- a. Enable one or more of these Blades for the rules of Inline Layer:
 - Firewall
 - Application & URL Filtering
 - Content Awareness
 - Mobile Access
- b. **Optional**: It is a best practice to share Layers with other Policy packages when possible. To enable this, select **Multiple policies can use this layer**.
- c. Click Advanced.
- d. Configure the **Implicit Cleanup Rule** to *Drop* or *Accept* (see "*Types of Rules in the Rule Base*" on page 365).
- e. Click OK.

The name of the Inline Layer shows in the Action cell of the rule.

- 6. Under the parent rule of the Inline Layer, add *sub-rules*.
- 7. Make sure there is an explicit cleanup rule as the last rule of the Inline Layer (see *"Types of Rules in the Rule Base" on page 365*).
- Note A Remote Access VPN community object is not supported in the parent rule of an Inline Layer if the action is "Inline Layer".
 To resolve this issue: Use "*Any" in the parent rule instead of the Remote Access VPN community object. You can use the Remote Access VPN community object in the rules in the inline layer.

Creating an Ordered Layer

To create an Ordered Layer

- 1. In SmartConsole, click Menu > Manage Policies and Layers.
- 2. In the left pane, click Layers.

You will see a list of the Layers. You can select **Show only shared Layers**.

- 3. Click the **New** icon in the upper toolbar.
- 4. Configure the settings in the Layer Editor window.
- 5. **Optional**: It is a best practice to share Layers with other Policy packages when possible. To enable this select **Multiple policies can use this layer**.
- 6. Click OK.
- 7. Click Close.

8. Publish the SmartConsole session.

This Ordered Layer is not yet assigned to a Policy Package.

To add an Ordered Layer to the Access Control Policy

- 1. In SmartConsole, click Security Policies.
- 2. Right-click a Layer in the Access Control Policy section and select Edit Policy.

The **Policy** window opens.

3. In the Access Control section, click the plus sign.

You will see a list of the Layers that you can add. These are Layers that have **Multiple policies can use this layer** enabled.

- 4. Select the Layer.
- 5. Click OK.
- 6. Publish the SmartConsole session.

Enabling Access Control Features

Before creating the Access Control Policy, you must enable the Access Control features that you will use in the Policy.

Enable the features on the:

- Security Gateways, on which you will install the Policy.
- Ordered Layers and Inline Layers of the Policy. Here you can enable:
 - Firewall. This includes VPN (see "VPN Column" on page 329).
 - Application & URL Filtering (see "Services & Applications Column" on page 330).
 - Content Awareness (see "Content Column" on page 334).
 - Mobile Access (see "Mobile Access to the Network" on page 489).

Enabling Access Control Features on a Security Gateway

1. In SmartConsole, from the left navigation panel, click **Gateways & Servers** and double-click the Security Gateway object.

The General Properties window of the Security Gateway opens.

- 2. From the navigation tree, click General Properties.
- 3. In the Network Security tab, select one or more of these Access Control features:

- IPsec VPN
- Mobile Access
- Application Control
- URL Filtering
- Content Awareness
- Identity Awareness
- 4. Click OK.

Enabling Access Control Features on a Layer

To enable the Access Control features on an Ordered Layer:

- 1. In SmartConsole, click Security Policies.
- 2. Under Access Control, right-click Policy and select Edit Policy.
- 3. Click options \equiv for the Layer.
- 4. Click Edit Layer.

The Layer Editor window opens and shows the General view.

- 5. Enable the **Blades** that you will use in the Ordered Layer:
 - Firewall.
 - Application & URL Filtering
 - Content Awareness
 - Mobile Access
- 6. Click OK.

To enable the Access Control features on an Inline Layer

- 1. In SmartConsole, click Security Policies.
- 2. Select the Ordered Layer.
- 3. In the parent rule of the Inline Layer, right-click the Action column, and select Inline Layer > Edit Layer.
- 4. Enable the **Blades** that you will use in the Inline Layer:
 - Firewall
 - Application & URL Filtering

- Content Awareness
- Mobile Access

1 Note - Do not enable a Blade that is not enabled in the Ordered Layer.

5. Click OK.

Types of Rules in the Rule Base

There are three types of rules in the Rule Base- explicit, implied and implicit.

Explicit rules

The rules that the administrator configures explicitly, to allow or to block traffic based on specified criteria.

Important - The default Cleanup rule is an explicit rule that is added by default to every new layer. You can change or delete the default Cleanup rule. We recommend that you have an explicit Cleanup rule as the last rule in each layer.

Implied rules

The default rules that are available as part of the **Global properties** configuration and cannot be edited. You can only select the implied rules and configure their position in the Rule Base:

- First Applied first, before all other rules in the Rule Base explicit or implied
- Last Applied last, after all other rules in the Rule Base explicit or implied, but before the Implicit Cleanup Rule
- Before Last Applied before the last explicit rule in the Rule Base

Implied rules are configured to allow connections for different services that the Security Gateway uses. For example, the **Accept Control Connections** rules allow packets that control these services:

- Installation of the security policy on a Security Gateway
- Sending logs from a Security Gateway to the Security Management Server
- Connecting to third party application servers, such as RADIUS and TACACS authentication servers

Implicit cleanup rule

The default "catch-all" rule for the Layer that deals with traffic that does not match any explicit or implied rules in the Layer. It is made automatically when you create a Layer.

Implicit cleanup rules do not show in the Rule Base.

For Security Gateways R80.10 and higher, the default implicit cleanup rule action is **Drop**. This is because most Policies have Allow List rules (the Accept action). If the Layer has Blacklist rules (the Drop action), you can change the action of the implicit cleanup rule to **Accept** in the Layer Editor.

For Security Gateways R77.30 and lower, the action of the implicit rule depends on the Ordered Layer:

- Drop for the Network Layer
- Accept for a Layer with Applications and URL Filtering enabled
- Note If you change the default values, the policy installation fails on Security Gateway R77.30 or lower.

Order in which the Security Gateway applies the rules

- 1. First Implied Rule No explicit rules can be placed before it.
- 2. Explicit Rules These are the rules that you create.
- 3. Before Last Implied Rules Applied before the last explicit rule.
- 4. Last Explicit Rule We recommend that you use a Cleanup rule as the last explicit rule.

Note - If you use the Cleanup rule as the last explicit rule, the Last Implied Rule
 and the Implicit Cleanup Rule are not enforced.

- 5. Last Implied Rule Remember that although this rule is applied after all other explicit and implied rules, the Implicit Cleanup Rule is still applied last.
- 6. **Implicit Cleanup Rule** The default rule that is applied if none of the rules in the Layer match.

Configuring the Implied Rules

Some of the implied rules are enabled by default. You can change the default configuration as necessary.

To configure the implied rules:

- 1. In SmartConsole, select the Access Control Policy.
- 2. From the toolbar above the policy, select **Actions > Implied Rules**.

The Implied Policy window opens.

- 3. In the left pane, click **Configuration**.
- 4. Select a rule to enable it, or clear a rule to disable it.

- 5. For the enabled rules, select the position of the rules in the Rule Base: **First**, **Last**, or **Before Last** (see *"Types of Rules in the Rule Base" on page 365*).
- 6. Click **OK** and install the policy.

Showing the Implied Rules

In SmartConsole, from the Security Policies View, select Actions > Implied Rules.

The Implied Policy window opens.

It shows only the implied rules, not the explicit rules.

Configuring the Implicit Cleanup Rule

To configure the Implicit Cleanup Rule:

- 1. In SmartConsole, click Menu > Manage Policies and Layers.
- 2. In the left pane, click Layers.
- 3. Select a Layer and click Edit.

The Layer Editor opens.

- 4. Click Advanced
- 5. Configure the Implicit Cleanup Rule to Drop or Accept.
- 6. Click OK.
- 7. Click Close.
- 8. Publish the SmartConsole session.

Administrators for Access Control Layers

You can create administrator accounts dedicated to the role of Access Control, with their own installation and SmartConsole Read/Write permissions.

You can also delegate ownership of different Layers to different administrators. See "Configuring Permissions for Access Control Layers" on page 119.

Sharing Layers

You may need to use the same rules in different parts of a Policy, or have the same rules in multiple Policy packages.

There is no need to create the rules multiple times. Define an Ordered Layer or an Inline Layer one time, and mark it as shared. You can then reuse the Inline Layer or Ordered layer in multiple policy packages or use the Inline Layer in multiple places in an Ordered Layer. This is useful, for example, if you are an administrator of a corporation and want to share some of the rules among multiple branches of the corporation:

- It saves time and prevents mistakes.
- To change a shared rule in all of the corporation's branches, you must only make the change once.

To mark a Layer as shared

- 1. In SmartConsole, click Menu > Manage policies and layers.
- 2. In the left pane, click Layers.
- 3. Select a Layer in Access Control or in Threat Prevention.
- 4. Right-click and select Edit Layer.
- 5. Configure the settings in the Layer Editor window.
- 6. In General, select Multiple policies and rules can use this layer.
- 7. Click OK.
- 8. Click Close.
- 9. Publish the SmartConsole session.

To reuse a Threat Prevention Ordered Layer

- 1. In SmartConsole, go to Menu > Manage policies and layers > Policies.
- 2. Right-click the required policy and click **Edit**. The policy properties window opens.
- 3. In the Threat Prevention box, click the + sign.
- 4. Select the layer you want to include in this policy package.
- 5. Click OK.
- 6. Close the policy properties window.
- 7. In SmartConsole, install the policy.
- 8. Repeat this procedure for all policy packages.

For examples of Inline Layers and Ordered Layer, see "Use Cases for the Unified Rule Base" on page 373.

Visual Division of the Rule Base with Sections

To better manage a policy with a large number of rules, you can use **Sections** to divide the Rule Base into smaller, logical components. The division is only visual and does not make it possible to delegate administration of different **Sections** to different administrators.

Exporting Layer Rules to a .CSV File

You can export Layer rules to a .CSV file. You can open and change the .CSV file in a spreadsheet application such as Microsoft Excel.

To export Layer rules to a .CSV file:

1. In SmartConsole, click Menu > Manage Policies and Layers.

The Manage Layers window opens.

- 2. Click Layers.
- 3. Select a Layer, and then click **Actions > Export selected Layer**.
- 4. Enter a path and file name.

Managing Policies and Layers

To work with Ordered Layers and Inline Layers in the Access Control Policy, select **Menu > Manage policies and layers** in SmartConsole.

The Manage policies and layers window shows.

To see the Layer in the policy package and their attributes:

In the Layers pane of the window, you can see:

- Name Layer name
- Number of Rules Number of rules in the Layer
- Modifier The administrator who last changed the Layer configuration.
- Last Modified -Date the Layer was changed.
- Show only Shared Layers A shared Layer has the Multiple policies and rules can use this Layer option selected (see "Sharing Layers" on page 367).
- Layer Details

- Used in policies Policy packages that use the Layer
- Mode:
 - Ordered An Ordered Layer. In a Multi-Domain Security Management environment, it includes global rules and a placeholder for local, Domain rules.
 - Inline An Inline Layer, also known as a Sub-Policy.
 - Not in use A Layer that is not used in a Policy package.

To see the rules in the Layer:

- 1. Select a Layer.
- 2. Right-click and select Open layer in policy.

Best Practices for Access Control Rules

- 1. Make sure you have these rules:
 - Stealth rule that prevents direct access to the Security Gateway.
 - Cleanup rule that drops all traffic that is not allowed by the earlier rules in the policy.
- 2. Use Layers to add structure and hierarchy of rules in the Rule Base.
- 3. Add all rules that are based only on source and destination IP addresses and ports, in a Firewall/Network Ordered Layer at the top of the Rule Base.
- 4. Create Firewall/Network rules to explicitly accept safe traffic, and add an *explicit cleanup rule* at the bottom of the Ordered Layer to drop everything else.
- 5. Create an Application Control Ordered Layer after the Firewall/Network Ordered Layer. Add rules to explicitly drop unwanted or unsafe traffic. Add an explicit cleanup rule at the bottom of the Ordered Layer to accept everything else.

Alternatively, put Application Control rules in an Inline Layer as part of the Firewall/Network rules. In the parent rule of the Inline Layer, define the Source and Destination.

- 6. Share Ordered Layers and Inline Layers when possible.
- 7. If you have one Ordered Layer for Firewall/Network rules, and another Ordered Layer for Application Control - Add all rules that examine applications, Data Type, or Mobile Access elements, to the Application Control Ordered Layer, or to an Ordered Layer after it.
- Turn off the XFF inspection, unless the Security Gateway is behind a proxy server. For more, see <u>sk92839</u>.
- 9. Disable a rule when working on it. Enable the rule when you want to use it.

Disabled rules do not affect the performance of the Security Gateway.

To disable a rule, right-click in the **No.** column of the rule and select **Disable**.

Best Practices for Efficient rule Matching

1. Place rules that check the source, destination, and port (network rules) higher in the Rule Base.

Reason: Network rules are matched sooner, and turn on fewer inspection engines.

2. Place rules that check applications and content (Data Types) below network rules.

3. Do not define a rule with "Any" in the **Source** column and in the **Destination** column and with an Application or a Data Type.

Source	Destination	Services & Applications	Content
Any	Any	Facebook	
Any	Any		Credit Card numbers

For example, these rules are **not** recommended:

Instead, define one of these recommended rules:

Source	Destination	Services & Applications	Content
Any	Internet	Facebook	
Any	Object that represents the relevant server		Credit Card numbers

Reason for 2 and 3: Application Control and Content Awareness rules require content inspection.

Therefore, they:

- Allow the connection until the Security Gateway has inspected connection header and body.
- May affect performance.
- 4. For rules with Data Types:

Place rules that check File Types higher in the Rule Base than rules that check for Content Types. See "*Content Column*" on page 334.

Reason: File Types are matched sooner than Content Types.

 Do not use Application Control and URL Filtering in the same rule, this may lead to wrong rule matching. Use Application Control and URL Filtering in separate rules. This makes sure that the URL Filtering rule is used as soon as the category is identified. For more information, see sk174045.

To see examples of some of these best practices, see the "Use Cases for the Unified Rule Base" on page 373 and "Creating a Basic Access Control Policy" on page 344.

Use Cases for the Unified Rule Base

Here are some use cases that show examples of rules that you can define for the Access Control Policy.

Use Case - Application Control and Content Awareness Ordered Layer

This use case shows an example unified Access Control Policy. It controls applications and content in one Ordered Layer.

N o.	Name	Source	Destin ation	VPN	Services & Applicati ons	Conten t	Actio n	Tra ck
Gen	eral complia	nce (1)						
1	Block categorie s	Any	Internet	Any	Anonymi zer Critical Risk	Any	Drop Bloc k Mess age	Log
Bloc	k risky exec	utables (2)						
2	Block downloa d of executab le files from uncatego rized and high risk sites	Internal Zone	Internet	Any	Uncateg orized High Risk	Downlo ad Traffic Execut able File	Drop	Log
Cree	dit card data	(3-4)	1		1	1	1	

N o.	Name	Source	Destin ation	VPN	Services & Applicati ons	Conten t	Actio n	Tra ck
3	Allow uploadin g of credit cards number s, by finance, and only over HTTPS	Finance (Access Role)	Web Servers	Any	https	Upload Traffic PCI - Credit Card Number s	Acce pt	Log
4	Block other credit cards from company Web servers	Any	Web Servers	Any	Any	Any Directio n PCI - Credit Card Number s	Drop	Log
Info	rm about ser	nsitive data	over VPN	(5)	I	I	I	
5	Inform the user about sensitive data from VPN sites	Any	Any	RemoteA ccess	Any	Any Directio n Salary Survey Report	Infor m	Log
Clea	anup (6)							
6	Cleanup rule	Any	Any	Any	Any	Any	Acce pt	Log

Explanations for rules:

Rule	Explanation
1	General Compliance section - Block access to unacceptable Web sites and applications.
2	Block risky executables section - Block downloading of high risk executable files.
3-4	Credit card data section - Allow uploading of credit cards numbers only by the finance department, and only over HTTPS. Block other credit cards.
5	Block sensitive data over VPN section - A remote user that connects over the organization's VPN sees an informational message.
6	cleanup rule - Accept all traffic that does not match one of the earlier rules.

Use Case - Inline Layer for Web Traffic

This use case shows an example Access Control Policy that controls Web traffic. The Web server rules are in an Inline Layer.

No	Name	Source	Destinati on	Services & Applicatio ns	Content	Action	Trac k
1	Headquart er WEB traffic - via proxy	HQ	Proxy	Web Proxy	Any	Ask Web Access Policy Access Noti once a day per applic	Log
2	Allow Proxy to the Internet	Proxy	Internet	Web	Any	Accept	None

No	Name	Source	Destinati on	Services & Applicatio ns	Content	Action	Trac k
3	Allow local branch to access the internet directly	Local Branch	Internet	Web	Any	Ask Web Access Policy Access Noti once a day per applic	Log
4	Web Servers	InternalZo ne	Web Servers	Web	Any	Web Servers protecti on	N/A
4.1	Block browsing with unapprove d browsers	Any	Any	NEGATE D Google Chrome Internet Explorer 11 Firefox Safari	Any	Drop	Log
4.2	Inform user when uploading Credit Cards only over HTTPS	Any	Any	https	Upload Traffic PCI - Credit Card Number s	Inform Access Noti once a day per applic	Log

No	Name	Source	Destinati on	Services & Applicatio ns	Content	Action	Trac k
4.3	Block Credit Cards	Any	Any	Any	Any Directio n PCI - Credit Card Number s	Drop Block Messag e	Log
4.4	Block downloadi ng of sensitive content	Any	Any	Any	Downlo ad Traffic HIPAA - Medical Record Headers	Drop	Log
4.5	Cleanup rule	Any	Any	Any	Any	Accept	None
5	Ask user when sending credit cards to PayPal	InternalZo ne	Internet	PayPal	Any Directio n PCI - Credit Card Number s	Ask Compan y Policy Access Noti once a day per applic	Log
6	Cleanup rule	Any	Any	Any	Any	Drop	Log

Explanations for rules:

Rule	Explanation
4	This is the parent rule of the Inline Layer. The Action is the name of the Inline Layer. If a packet matches on the parent rule, the matching continues to rule 4.1 of the Inline Layer. If a packet does not match on the parent rule, the matching continues to rule 5.

Rule	Explanation
4.1 -4.4	If a packet matches on rule 4.1, the rule action is done on the packet, and no more rule matching is done. If a packet does not match on rule 4.1, continue to rule 4.2. The same logic applies to the remaining rules in the Inline Layer.
4.5	If none of the higher rules in the Ordered Layer match the packet, the explicit <i>Cleanup Rule</i> is applied. The <i>Cleanup rule</i> is a default explicit rule. You can change or delete it. We recommend that you have an explicit cleanup rule as the last rule in each Inline Layer and Ordered Layer.

Use Case - Content Awareness Ordered Layer

This use case shows a Policy that controls the upload and download of data from and to the organization.

There is an explanation of some of the rules below the Rule Base.

No	Name	Source	Destinati on	Services & Applicatio ns	Content	Action	Trac k
Reg	ulatory complia	ince					
1	Block the download of executable files	InternalZo ne	Internet	Any	Downloa d Traffic Executa ble file	Drop	Log
2	Allow uploading of credit cards numbers by finance users, only over HTTPS	Finance (Access Role)	Web Servers	https	Upload Traffic PCI - Credit Card Numbers	Accept	Log

No	Name	Source	Destinati on	Services & Applicatio ns	Content	Action	Trac k
3	Block other credit cards from company Web servers	InternalZo ne	Web Servers	Any	Any Direction PCI - Credit Card Numbers	Drop Block Messag e	Log
Pers	onally Identifia	ble Informatio	on				
4	Matches U.S. Social Security Numbers (SSN) allocated by the U.S. Social Security Administrat ion (SSA).	InternalZo ne	Internet	Any	Upload Traffic U.S. Social Security Numbers - Accordin g to SSA	Inform Access Notifi once a day per applicat i	Log
5	Block downloadin g of sensitive medical information	InternalZo ne	Internet	Any	Downloa d Traffic HIPAA - Medical Records Headers	Drop Block Messag e	Log
Hum	an Resources					l	
6	Ask user when uploading documents containing salary survey reports.	InternalZo ne	Internet	Any	Upload Traffic Salary Survey Report	Ask Compa ny Policy once a day per applicat i	Log
Intell	ectual Propert	y					

No	Name	Source	Destinati on	Services & Applicatio ns	Content	Action	Trac k
7	Matches data containing source code	InternalZo ne	Internet	Any	Any Direction Source Code	Restrict source code	N/A
7.1		Any	Any	Any	Downloa d Traffic Source Code	Accept	Log
7.2		Any	Any	Any	Upload Traffic Source Code	Ask Compan y Policy once a day per applicat i	Log
7.3	Cleanup Inline Layer	Any	Any	Any	Any	Drop Block Messag e	Log

Explanations for rules:

Rule	Explanation
1-3	 Regulatory Compliance section - Controls the upload and download of executable files and credit cards. You can set the direction of the Content. In rule 1 it is Download Traffic, in rule 2 it is Upload Traffic, and in rule 3 it is Any Direction. Rule 1 controls executable files, which are File Types. The File Type rule is higher in the Rule Base than rules with Content Types (Rules 2 to 7). This improves the efficiency of the Rule Base, because File Types are matched sooner than Content Types.

Rule	Explanation
4-5	Personally Identifiable Information section - Controls the upload and download of social security number and medical records. The rule Action for rule 4 is Inform. When an internal user uploads a file with a social security number, the user sees a message.
6	Human resources section - Controls the sending of salary survey information outside of the organization. The rule action is Ask. If sensitive content is detected, the user must confirm that the upload complies with the organization's policy.
7	 Intellectual Property section - A group of rules that control how source code leaves the organization. Rule 7 is the parent rule of an Inline Layer (see "Ordered Layers and Inline Layers" on page 359). The Action is the name of the Inline Layer. If a packet matches on rule 7.1, matching stops. If a packet does not match on rule 7.1, continue to rule 7.2. In a similar way, if there is no match, continue to 7.3. The matching stops on the last rule of the Inline Layer. We recommend that you have an explicit cleanup rule as the last rule in each Inline Layer

Use Case - Application & URL Filtering Ordered Layer

This use case shows some examples of URL Filtering and Application Control rules for a typical policy that monitors and controls Internet browsing. (The **Hits, VPN** and **Install On** columns are not shown.)

No.	Name	Source	Destinatio n	Services & Applications	Action	Track	Time
1	Liability sites	Any	Internet	Potential liability (group)	Drop Blocked Message	Log	Any
2	High risk application s	Any	Internet	High Risk iTunes Anonymizer (category)	Drop Blocked Message	Log	Any
3	Allow IT departmen t Remote Admin	IT (Acces s Role)	Any	Radmin	Allow	Log	Work- Hours

No.	Name	Source	Destinatio n	Services & Applications	Action	Track	Time
4	Allow Facebook for HR	HR (Acces s Role)	Internet	Facebook	Allow Downloa d_1Gbps	Log	Any
5	Block these categories	Any	Internet	Streaming Media Protocols Social Networking P2P File Sharing Remote Administrati on	Drop Blocked Message	Log	Any
6	Log all application s	Any	Internet	Any	Allow	Log	Any

Explanations for rules:

Rule	Explanation				
1	Liability sites - Blocks traffic to sites and applications in the custom <i>Potential_liability</i> group. The UserCheck <i>Blocked Message</i> is shown to users and explains why their traffic is blocked. See " <i>Blocking Sites</i> " on page 356. <i>Scenario: I want to block sites that are associated with categories that can cause liability issues. Most of these categories exist in the Application Database but there is also a custom defined site that must be included. How can I do this?</i> You can do this by creating a <i>custom group</i> and adding all applicable categories and the site to it. If you enable Identity Awareness on a Security Gateway, you can use it together with URL Filtering to make rules that apply to an <i>access role.</i> Use access role objects to define users, machines, and network locations as one object. In this example:				
	 You have already created An Access Role that represents all identified users in the organization (<i>Identified_Users</i>). A custom application for a site named <i>FreeMovies</i>. You want to block sites that can cause liability issues for everyone within your organization. You will create a custom group that includes Application Database categories as well as the previously defined custom site named <i>FreeMovies</i>. 				
	 To create a custom group: 1. In the Object Explorer, click New > More > Custom Application/Site > Application/Site Group. 2. Give the group a name. For example, <i>Liability_Sites</i>. 3. Click + to add the group members: Search for and add the custom application <i>FreeMovies</i>. Select Categories, and add the ones you want to block (for example <i>Anonymizer, Critical Risk</i>, and <i>Gambling</i>) Click Close 4. Click OK. 				
	You can now use the <i>Liability_Sites</i> group in the Access Control Rule Base. In the Rule Base, add a rule similar to this:				
	 In the Nule Dase, and a rule similar to this. In the Security Policies view of SmartConsole, go to the Access Control Policy. Source - The Identified_Users access role Destination - Internet Services & Applications - Liability_Sites Action -Drop 				

Rule	Explanation					
	Note - Applications are matched on their Recommended services, where each service runs on a specific port, such as the default Application Control Web Browsing Services: http, https, HTTP_ proxy, and HTTPS_proxy. To change this see Changing Services for Applications and Categories.					
	Name	Source	Destination	Services & Applications	Action	Track
	Block sites that may cause a liability	Identified_ Users	Internet	Liability_Sites	Drop	Log
2	High risk applications - Blocks traffic to sites and applications in the <i>High Risk</i> category and blocks the <i>iTunes</i> application. The UserCheck <i>Block Message</i> is shown to users and explains why their traffic is blocked.					
3	Allow IT department Remote Admin - Allows the computers in the IT department network to use the <i>Radmin</i> application. Traffic that uses <i>Radmin</i> is allowed only during the <i>Work-Hours</i> (set to 8:00 through 18:30, for example).					
4	Allow Facebook for HR - Allows computers in the HR network to use Facebook. The total traffic downloaded from Facebook is limited to 1 Gbps, there is no upload limit.					
5	 Block these categories - Blocks traffic to these categories: Streaming Media, Social Networking, P2P File Sharing, and Remote Administration. The UserCheck Blocked Message is shown to users and explains why their traffic is blocked. Note - The Remote Administration category blocks traffic that uses the Radmin application. If this rule is placed before rule 3, then this rule can also block Radmin for the IT department. 					
6	Log all applications - Logs all traffic that matches any of the URL Filtering and Application Control categories.					

Self-Managed Security Gateways

Introduction

R82 introduced a new Dynamic Layer in the Access Control policy to assist customers with highly automated network environments.

This Policy Layer serves as a container for rules created directly on the Security Gateway using the Gaia API call "set-dynamic-content", catering to environments where provisioning, configuration, and other IT processes are regularly managed through the distribution of JSON files.

Workflow:

- 1. On the Management Server, in the Access Control, you create a new Policy Layer and configure it as a Dynamic Layer.
- 2. On the Security Gateway, you configure the required Access Control rules in this Dynamic Layer with the Gaia API call "set-dynamic-content" (in the JSON format).

The Dynamic Layer works only as a container for rules that you configure on the Security Gateway. After you run the Gaia API command on the Security Gateway, it ignores all rules in this Dynamic Layer that were configured in SmartConsole. If permanent rules are needed (for example, to allow access from a remote API client), you must configure them in the main policy on the Management Server and not in Dynamic Layers.

For additional information, refer to <u>sk182252</u>.

Requirements

- 1. Management Server R82 and higher:
 - Security Management Server
 - Multi-Domain Security Management Server
- 2. Security Gateway R82 and higher:
 - Single Security Gateway
 - ElasticXL Cluster
 - ClusterXL
 - Security Group in Maestro or Scalable Chassis
- 3. On the Security Gateway, the user that runs the Gaia API must have this configuration in Gaia OS:
 - a. **Role**: adminRole.
 - b. Access Mechanism: Gaia API.
 - c. Shell:/etc/cli.sh or /bin/bash

See the <u>Gaia Administration Guide</u> for your version > User Management chapter> Users and Roles sections.

Limitations

• This feature was designed for the JSON format.

Use a 3rd-party REST API client that allows you to paste the required API body in the JSON format.

Do not use the Check Point CLI API client "mgmt_cli".

- It is not supported to edit or delete individual dynamic rules on the Security Gateway after you add them.
 - To change an individual dynamic rule, you must run the Gaia API call "setdynamic-content" with the updated API body that contains the complete Access Control rules and the updated parameters and values for that individual rule.
 - To delete an individual dynamic rule, you must run the Gaia API call "setdynamic-content" with the updated API body that contains the complete Access Control rules without that individual rule.



- To see the current rules and to copy the current complete JSON, run the Gaia API call "show-dynamic-layer" on the Security Gateway.
- If necessary, you can delete all rules in the Dynamic Layer on the Security Gateway. See "*Resetting a Dynamic Layer*" on page 394.
- VSNext Virtual Gateway is not supported.
- Traditional VSX Virtual System (on a VSX Gateway or VSX Cluster) is not supported.
- Traditional VSX Virtual Router (on a VSX Gateway or VSX Cluster) is not supported.

Notes

- Each Policy Package supports more than one Dynamic Layer as an Inline Layer or as an Ordered Layer. For example, different administrators can use different Policy Layers.
- The Security Gateway applies the Access Control rules in the order of the Policy Layers in the Policy Package.
- Rules that you configure in the Dynamic Layer apply until you run the Gaia API call "set-dynamic-content" for the first time on the Security Gateway.
- If you delete the Dynamic Layer from the Policy Package (or clear the checkbox Set as a Dynamic Layer in the Dynamic Layer) and install the Access Control policy, then the Security Gateway removes all dynamic rules and applies only the static rules configured in SmartConsole.
- SmartConsole does not show rules in the Dynamic Layer that you configure on the Security Gateway.
- To see the list of the supported objects in the Dynamic Layer, refer to the API call "setdynamic-content" > section "Request Body" > parameter "objects".

Configuration

- 1. Connect with SmartConsole to the Security Management Server / Domain Management Server.
- 2. Add a new Policy Layer and configure it as a Dynamic Layer.

Notes:

- You can configure a new Policy Layer directly in a specific policy, or as a shared Policy Layer for several policies.
- You can configure an Inline Layer (within a specific rule), or an Ordered Layer (a separate set of rules in a dedicated Policy Layer).

See "Ordered Layers and Inline Layers" on page 359.

You can add a new Policy Layer and configure it as a Dynamic Layer either in SmartConsole (described below) or with the Management API call "add-accesslayer dynamic-layer true" (see <u>Check Point Management API Reference</u> v1.8 and higher).

Procedure in SmartConsole:

To configure an Ordered Layer in a specific Access Control policy

- a. In the top left corner, click Menu > Manage policies and layers.
- b. In the left panel, click **Policies**.

- c. Right-click the applicable Policy Package and click Edit.
- d. In the Access Control section, click the + icon.
- e. In the top right corner, click New Layer.
- f. Enter the name for this Policy Layer.
- g. On the General page:

In the Blades section, select the supported blades:

- i. Mandatory: Firewall
- ii. Optional: Application & URL Filtering
- h. On the Advanced page:
 - i. In the Implicit Cleanup Action section, select the option Drop (default).

This **Drop** rules makes sure to drop all traffic that matches this Ordered Layer until you run the Gaia API call "set-dynamic-content" on the Security Gateway.

You can change it later in SmartConsole.

- ii. In the Dynamic Layer section, select Set as a Dynamic Layer.
- On the Permissions page, select the permission profiles that can edit the Dynamic Layer. This is essential when multiple Dynamic Layers are used, each configured by different users. Only the profiles shown here can edit the Layer. To add additional profiles that can edit the Layer, go to the bottom of the Permissions page.

To create a new permission profile, in SmartConsole, go to the Manage & Settings view > Permissions & Administrators > Permission Profiles. In the profile editor, go to Access Control > Policy, and make sure Edit layers by the selected profile in a layer editor is selected.

- j. Click **OK** to close the Layer Editor window.
- k. In the policy, to the right of the Access Control section, you now see the Layer called **Network** (default name) and the new Dynamic Layer.

Important - You can change the order of these Policy Layers.

I. Click OK to close the Policy window.

To configure an Inline Layer in a specific Access Control policy in a specific rule

- a. From the left navigation panel, click Security Policies.
- b. If you need to open a different Security Policy:
 - i. At the top, click the [+] tab.
 - ii. Click the required policy.
- c. In the Access Control section, click Policy.
- d. Locate the applicable rule.
- e. In the rule, click in the Action cell > click Inline Layer > click New Layer.
- f. Enter the name for this **Policy Layer**.
- g. On the General page, in the Blades section, select the supported blades:
 - Mandatory: Firewall
 - Optional: Application & URL Filtering
 - Optional: In the Sharing section, select Multiple policies and rules can use this layer.
- h. On the Advanced page:
 - i. In the Implicit Cleanup Action section, select the option Accept.

This makes sure to accept traffic that matches this Inline Layer until you run the Gaia API call "set-dynamic-content" on the Security Gateway.

You can change it later in SmartConsole.

- ii. In the Dynamic Layer section, select Set as a Dynamic Layer.
- On the Permissions page, select the permission profiles that can edit the Dynamic Layer. This is essential when multiple Dynamic Layers are used, each configured by different users. Only the profiles shown here can edit the Layer. To add additional profiles that can edit the Layer, go to the bottom of the Permissions page.

To create a new permission profile, in SmartConsole, go to the Manage & Settings view > Permissions & Administrators > Permission Profiles. In the profile editor, go to Access Control > Policy, and make sure Edit layers by the selected profile in a layer editor is selected.

- j. Click **OK** to close the **Layer Editor** window.
- k. In the rule, you now see the new Inline Layer.

To configure a shared Ordered Layer to use in several Access Control Policies

- a. In the top left corner, click Menu > Manage policies and layers.
- b. In the left panel, click Layers > Access Control.
- c. From the top tool bar, click New.
- d. Enter the name for this Policy Layer.
- e. On the General page, in the Blades section, select the supported blades:
 - Mandatory: Firewall
 - Optional: Application & URL Filtering
 - Optional: In the Sharing section, select Multiple policies and rules can use this layer.
- f. On the Advanced page:
 - i. In the Implicit Cleanup Action section, select the option Drop.

This **Drop** rules makes sure to drop all traffic that matches this Ordered Layer until you run the Gaia API call "set-dynamic-content" on the Security Gateway.

You can change it later in SmartConsole.

- ii. In the Dynamic Layer section, select Set as a Dynamic Layer.
- g. On the **Permissions** page, select the permission profiles that can edit the Dynamic Layer. This is essential when multiple Dynamic Layers are used, each configured by different users. Only the profiles shown here can edit the Layer. To add additional profiles that can edit the Layer, go to the bottom of the **Permissions** page.

To create a new permission profile, in SmartConsole, go to the **Manage &** Settings view > Permissions & Administrators > Permission Profiles. In the profile editor, go to Access Control > Policy, and make sure Edit layers by the selected profile in a layer editor is selected.

- h. Click OK to close the Layer Editor window.
- i. In the left panel, click **Policies**.
- j. Right-click the applicable Policy Package and click Edit.
- k. In the Access Control section, click the + icon.
- I. Click the new Dynamic Layer.

m. In the policy, to the right of the Access Control section, you now see the Layer called Network (default name) and the new Dynamic Layer.

8 Important - You can change the order of these Policy Layers.

- n. Click **OK** to close the **Policy** window.
- o. Click Close to close the Manage policies and layers window.
- 3. If you run Gaia API calls on the Security Gateway from a remote API client (and not locally on the Security Gateway), make sure your Access Control policy allows such connection to the Security Gateway.



Best Practice - To avoid losing connectivity loss for the API client, add the applicable rule only in a static Policy Layer (that is not configured as a Dynamic Layer).

- 4. Install this Access Control Policy on the Security Gateway / Cluster object.
- 5. Run the Gaia API call "set-dynamic-content" on the Security Gateway / each Cluster Member / Security Group to configure the required dynamic Access Control rules.



Marning - Pay close attention to the rules you configure on the Security Gateway.

There is **no** verification of possible conflicts between the rules configured on the Security Gateway and the rules configured in SmartConsole.

Notes:

Refer to the online Check Point Gaia API Reference (v1.8 and higher) > section System > sub-section Dynamic Content.

To see the local Gaia API Reference, go to this URL on a Management Server or Security Gateway (R82 or higher):

```
https://<IP Address of Gaia Management
Interface>/gaia docs/#web/set-dynamic-content
```

At the top of the Gaia API Reference, click the Web Services tab.

- Because you run Gaia API calls from a remote API client, make sure your Access Control policy allows such connection to the Security Gateway.
 - Best Practice To avoid losing connectivity loss for the API client, add the applicable rule only in a static Policy Layer (that is not configured as a Dynamic Layer).

Workflow for a remote REST API client (based on the Postman application)

- a. Install the Postman application.
- b. Get the Gaia REST API collection from sk143612.

- c. Import the Gaia REST API collection into the Postman application (first, you must create a Postman account). Refer to the Postman documentation about the import methods.
- d. Configure the required API variables:
 - i. In the left panel, in the Gaia REST API collection, click the top folder Gaia API.
 - ii. Add these variables:

Variable Name	Variable Value	Comment
username	Username of the applicable user in the Gaia OS on the Security Gateway.	The default user is admin. You can create other users (see the Requirements section).
password	Password of the applicable user in the Gaia OS on the Security Gateway.	You configure this password.
ip	IP Address of the Gaia Management Interface on the Security Gateway / each Cluster Member / Security Group.	This is the IP address on the Security Gateway / each Cluster Member / Security Group, to which the API client connects.
sid	Initially, empty.	Use this variable to contain the required SID after running the Gaia API call "login".

- e. Get the Login Session ID (SID):
 - i. In the left pane, open the folder Session Management.
 - ii. Click the API call "login".
 - iii. In the top right corner, click Send.
 - iv. In the bottom panel, copy the value of the parameter "sid".

- f. Configure the SID variable:
 - i. In the left panel, click the top folder Gaia API.
 - ii. In the sid variable, enter the copied value in the column Current Value.
 - iii. In the top right corner, click Save.
- g. Run the API call "set-dynamic-content" on the Security Gateway / each Cluster Member / Scalable Platform Security Group:
 - i. In the left panel, click the API "set-dynamic-content".
 - ii. At the top, click the Body tab.
 - iii. Configure the required parameters and values in the JSON format.
 - iv. In the top right corner, click **Send**.
 - v. In the bottom panel, copy the entire response with a Task ID.
 - vi. In the left panel, open the Misc folder, and click the API call "show task".
 - vii. At the top, click the **Body** tab and click the **raw** option.
 - viii. Paste the entire response with the Task ID.
 - ix. In the top right corner, click **Send**.
 - x. In the bottom panel, see the API response for the API call "set-dynamic-content".
- 6. **Optional**: Examine the configured dynamic Access Control rules.
 - To see the configured dynamic Access Control rules in a specific Dynamic Layer, run the Gaia API call "show-dynamic-layer" on the Security Gateway / each Cluster Member / Security Group.
 - To see the configured dynamic Access Control rules in all configured Dynamic Layers, run the Gaia API call "show-dynamic-layers" on the Security Gateway / each Cluster Member / Security Group.

Resetting a Dynamic Layer

To remove all dynamic rules, you must reset the Dynamic Layer that contains these rules on the Security Gateway.

Procedure

```
Run the Gaia API call "set-dynamic-content" on the Security Gateway and use "operation": "reset".
```

Syntax part for a remote REST API client

```
f'access-layers-content": [f'
    {f'
        "name": "<Name_of_Dynamic_Layer>",f'
        "operation": "reset",f'
        "rulebase": []f'
    }f'
    [f'
```

Installing the Access Control Policy

- Important With the "fw up_execute" command, you can examine the Security Gateway behavior (R82 and above) for a specified traffic before you make changes to your Access Control Policy. See the <u>R82 CLI Reference Guide</u> > Chapter "Security Gateway Commands" > Section "fw" > Section "fw up_execute".
 - 1. On the Global Toolbar, click **Menu** > **Verify Access Control Policy** > select the required policy > click **Verify**.

Alternatively, click the left **Security Policies** view > **Access Control** > from the top toolbar, click **Actions** > **Verify Access Policy**.

Note - Starting from R82, it is possible to verify the Access Control policy before you publish the session.

Make the required changes.

- 2. On the top Global Toolbar, click Publish session.
- 3. On the top Global Toolbar, click Install Policy.

The Install Policy window opens showing the Security Gateways.

- 4. If there is more than one Policy package: From the **Policy** drop-down list, select a policy package.
- 5. Select Access Control. You can also select other Policies.
- 6. If there is more than one Security Gateway: Select the Security Gateways, on which to install the policy.
- 7. Select the Install Mode:
 - Install on each selected gateway independently Install the policy on each target Security Gateway independently of others, so that if the installation fails on one of them, it doesn't affect the installation on the rest of the target Security Gateways.
 - Note If you select For Gateway Clusters, if installation on a cluster member fails, do not install on that cluster, the Security Management Server makes sure that it can install the policy on all cluster members before it begins the installation. If the policy cannot be installed on one of the members, policy installation fails for all of them.
 - Install on all selected gateways, if it fails do not install on gateways of the same version - Install the policy on all the target Security Gateways. If the policy fails to install on one of the Security Gateways, the policy is not installed on other target Security Gateways.
- 8. Click Install.

Policy Insights

The Policy Insights feature in R82 SmartConsole helps administrators analyze and optimize the policy Rule Base, by offering detailed insights and visualizations. The Check Point Cloud Services analyze traffic and policies and provide suggestions to changing the Rule Base based on this information. The suggestions are generated according to internal scheduling. A cleaner and more efficient Rule Base makes it easier to manage the security policies, and helps reduce vulnerabilities.

Supported Objects

Policy Insights supports these objects:

- In the Source and Destination columns:
 - Hosts
 - Networks
 - Groups
- Service and Service Groups:
 - icmp
 - icmp6
 - rpc
 - tcp
 - udp
 - dce-rpc

Prerequisites

Connect your Security Management Server to the Infinity Portal.

See "To connect your Security Management Server and Security Gateway objects from SmartConsole to the Infinity Portal" on page 538.

1 Note - There is no need to enable Log Sharing or Configuration Sharing.

Working with Policy Insights

To access the Policy Insights window

- 1. In SmartConsole, go to the **Security Policies** view > **Access Control** > **Policy**.
- 2. Above the Rule Base, click the **Insights** button.

The **Policy Insights** window opens.

Components of the Policy Insights Window

The Policy Insights window is comprised of 3 sections:

The Suggestions section

This section provides you with actionable recommendations to optimize your Security Policy Rule Base. The **Suggestions** section is divided into categories, such as: **Remove unmatched objects**, **Replace existing objects** and so on. Hover over each.

You can filter the suggestions based on these categories:

- Show only top suggestions Suggestions with the highest security impact.
- Show suggestions (default) Valuable suggestions.
- Include low confidence suggestions Suggestions for new rules, rules that changed recently, or other cases when data is limited.

For each suggestion, you can select one of these options:

- Apply Make the suggested change in the Rule Base.
- **Decline** Reject the change. The suggestion is moved to the **Declined** suggestions section.
- **Decide later** Move the suggestion to the **Decide later** section. The suggestion remains available for use in the future.

After you select an option, publish your changes and install policy.

The Decide later section

This section includes suggestions which were originally in the suggestions section and which you moved to the Suggestions section.

To use a suggestion from the Decide later section

- 1. Select the required suggestion and click the **Move back** button.
- 2. In the Suggestions section, select the required suggestion and click Apply.
- 3. Publish your changes and **Install Policy**.
- The Declined suggestions section

This section includes suggestions which were originally in the suggestions section and which you moved to the **Suggestions** section.

To use a suggestion from the Declined suggestions section

- 1. Select the required suggestion and click the **Undo decline** button.
- 2. In the **Suggestions** section, select the required suggestion and click **Apply**.
- 3. Publish your changes and Install Policy.

In each category in the Policy Insights window, you can see the latest date on which the presented information is based.

The number in each category represents the number of suggestions for this category.

Next to each suggestion, one of these options appears:

- Recommended Suggestions with high security impact and high confidence.
- No icon Suggestions with security impact but no conclusive confidence due to limited data.
- Low Confidence Not enough logs and time to have conclusive confidence. For example, new rules, rules that changed recently, or other cases when data is limited.

You can export the information in the Policy Insights window as a CSV file. To do so, click the **Export to CSV** button, at the bottom left corner of the Policy Insights window.

To see suggestions for a specific rule

- 1. In the Access Control policy, select the required rule.
- 2. In the bottom pane, click the **Insights** tab.
- 3. Click the **Open** button to open the **Policy Insights** window.
- 4. In the Policy Insights window, select the required action.
- 5. Publish your changes and Install Policy.

Analyzing the Rule Base Hit Count

Use the Hit Count feature to show the number of connections that each rule matches.

Use the Hit Count data to:

- Analyze a Rule Base You can delete rules that have no matching connection
 - Note If you see a rule with a zero Hit Count it only means that in the Security Gateways enabled with Hit Count there were no matching connections. There can be matching connections on other Security Gateways.
- Better understand the behavior of the Access Control Policy

The Hit Count value appears as:

- The percentage of the rule hits from total hits
- The indicator level (very high, high, medium, low, or zero)

The percentage and indicator level are configured in the Access Control Policy Rule Base.

When you enable Hit Count, the Security Management Server collects the data from supported Security Gateways (version R75.40 and higher).

Hit Count works independently from logging and tracks the hits even if the **Track** option is **None**.

Note - From R81, Hit Count is also supported in the NAT Rule Base (requires Security Gateways R81 and higher).

Enabling or Disabling Hit Count

By default, Hit Count is globally enabled for all supported Security Gateways. The timeframe setting that defines the data collection time range is configured globally. If necessary, you can disable Hit Count for one or more Security Gateways.

After you enable or disable Hit Count you must install the Policy for the Security Gateway to start or stop collecting data.

To enable or disable Hit Count globally

- 1. In SmartConsole, click Menu > Global properties.
- 2. Select Hit Count from the tree.
- 3. Select the options:
 - Enable Hit Count Select to enable or clear to disable all Security Gateways to monitor the number of connections each rule matches.

- Keep Hit Count data up to Select one of the time range options. The default is 3 months. Data is kept in the Security Management Server database for this period and is shown in the Hits column.
- 4. Click OK.
- 5. Install the Policy.

To enable or disable Hit Count on each Security Gateway:

- 1. From the **Gateway Properties** for the Security Gateway, select **Hit Count** from the navigation tree.
- 2. Select Enable Hit Count to enable the feature or clear it to disable Hit Count.
- 3. Click OK.
- 4. Install the Policy.

Hit Count Display

Configuring the Hit Count Display

These are the options you can configure for how matched connection data is shown in the **Hits** column:

- Value Shows the number of matched hits for the rule from supported Security Gateways. Connection hits are not accumulated in the total Hit Count for:
 - Security Gateways that are not supported
 - Security Gateways that have disabled the Hit Count feature

The values are shown with these letter abbreviations:

- K = 1,000
- M = 1,000,000
- G = 1,000,000,000
- T = 1,000,000,000,000

For example, 259K represents 259 thousand connections, and 2M represents 2 million connections.

- Percentage Shows the percentage of the number of matched hits for the rule from the total number of matched connections. The percentage is rounded to a tenth of a percent.
- Level The Hit Count level is a label for the range of hits according to the table.

The Hit Count range = Maximum hit value - Minimum hit value (does not include zero hits)

Hit Count Level	lcon	Range
Zero		0 hits
Low	-	Less than 10 percent of the Hit Count range
Medium	-	Between 10 - 70 percent of the Hit Count range
High	_	Between 70 - 90 percent of the Hit Count range
Very High		Above 90 percent of the Hit Count range

To show the Hit Count in the Rule Base:

Right-click the heading row of the Rule Base and select Hits.

To configure the Hit Count in a rule

- 1. Right-click the rule number of the rule.
- 2. Select **Hit Count** and one of these options (you can repeat this action to configure more options):
 - Timeframe Select All, 1 day, 7 days, 1 month, or 3 months
 - Display Select Percentage, Value, or Level

To update the Hit Count in a rule

- 1. Right-click the rule number of the rule.
- 2. Select **Hit Count > Refresh**.


Preventing IP Spoofing

IP spoofing replaces the untrusted source IP address with a fake, trusted one, to hijack connections to your network. Attackers use IP spoofing to send malware and bots to your protected network, to execute DoS attacks, or to gain unauthorized access.

Anti-Spoofing detects if a packet with an IP address that is behind a certain interface, arrives from a different interface. For example, if a packet from an external network has an internal IP address, Anti-Spoofing blocks that packet.

Example:

The diagram shows a Security Gateway with interfaces 2 and 3, and 4, and some example networks behind the interfaces.



For the Security Gateway, Anti-Spoofing makes sure that:

- All incoming packets to 2 come from the Internet (1)
- All incoming packets to 3 come from 192.168.33.0
- All incoming packets to 4 come from 192.0.2.0 or 10.10.10.0

If an incoming packet to 2 has a source IP address in network 192.168.33.0, the packet is blocked, because the source address is spoofed.

When you configure Anti-Spoofing protection on a Check Point Security Gateway interface, the Anti-Spoofing is done based on the interface topology. The interface topology defines where the interface Leads To (for example, External (Internet) or Internal), and the Security Zone of interface.

Configuring Anti-Spoofing

Make sure to configure Anti-Spoofing protection on all the interfaces of the Security Gateway, including internal interfaces.

To configure Anti-Spoofing for an interface:

1. In SmartConsole, from the left navigation panel, click **Gateways & Servers** and double-click the Security Gateway object.

The Gateway Properties window opens.

- 2. From the navigation tree, select Network Management.
- 3. Click Get Interfaces.
- 4. Click Accept.

The Security Gateway network topology shows. If SmartConsole fails to automatically retrieve the topology, make sure that the details in the **General Properties** section are correct and the Security Gateway, the Security Management Server, and the SmartConsole can communicate with each other.

5. Select an interface and click Edit.

The interface properties window opens.

- 6. From the navigation tree, click **General**.
- 7. In the **Topology** section of the page, click **Modify**.

The Topology Settings window opens.

- 8. In the Leads To section, select the type of network, to which this interface leads:
 - Internet (External) This is the default setting. It is automatically calculated from the topology of the Security Gateway. To update the topology of an internal network after changes to static routes, click Network Management > Get Interfaces in the Gateway Properties window.
 - **Override** Override the default setting.

If you Override the default setting:

- Internet (External) All external/Internet addresses
- This Network (Internal) -
 - Not Defined All IP addresses behind this interface are considered a part of the internal network that connects to this interface
 - Network defined by the interface IP and Net Mask Only the network that directly connects to this internal interface
 - Network defined by routes The Security Gateway dynamically calculates the topology behind this interface. If the network of this interface changes, there is no need to click Get Interfaces and install a policy. For more, see "Dynamically Updating the Security Gateway Topology" on page 230.
 - **Specific** A specific object (a Network, a Host, an Address Range, or a Network Group) behind this internal interface
 - Interface leads to DMZ The DMZ that directly connects to this internal interface
- 9. Optional: In the Security Zone section, select User defined, check Specify Security Zone and choose the zone of the interface.
- 10. Configure Anti-Spoofing options (see "Anti-Spoofing Options" on the next page). Make sure that Perform Anti-Spoofing based on interface topology is selected.
- 11. Select an Anti-Spoofing action:
 - Prevent Drops spoofed packets
 - Detect Allows spoofed packets. To monitor traffic and to learn about the network topology without dropping packets, select this option together with the Spoof Tracking Log option.
- 12. Configure Anti-Spoofing exceptions (optional). For example, configure addresses, from which packets are not inspected by Anti-Spoofing:
 - a. Select Don't check packets from.
 - b. Select an object from the drop-down list, or click New to create a new object.
- 13. Configure **Spoof Tracking** select the tracking action that is done when spoofed packets are detected:
 - Log Create a log entry (default)
 - Alert Show an alert
 - None Do not log or alert
- 14. Click **OK** twice to save Anti-Spoofing settings for the interface.

For each interface, repeat the configuration steps. When finished, install the Access Control policy.

Anti-Spoofing Options

- Perform Anti-Spoofing based on interface topology Select this option to enable spoofing protection on this external interface.
- Anti-Spoofing action is set to Select this option to define if packets will be rejected (the Prevent option) or whether the packets will be monitored (the Detect option). The Detect option is used for monitoring purposes and should be used in conjunction with one of the tracking options. It serves as a tool for learning the topology of a network without actually preventing packets from passing.
- Don't check packets from Select this option to make sure anti-spoofing does not take place for traffic from internal networks that reaches the external interface. Define a network object that represents those internal networks with valid addresses, and from the drop-down list, select that network object. The anti-spoofing enforcement mechanism disregards objects selected in the Don't check packets from drop-down menu.
- **Spoof Tracking -** Select a tracking option.

Configuring the NAT Policy

This chapter outlines the process of configuring NAT64 (Network Address Translation from IPv6 to IPv4) on a Check Point Security Gateway.

NAT64 is a technology that enables communication between IPv6-only clients and IPv4-only servers. The configuration involves defining rules on a Check Point Security Gateway to translate packet headers using the IPv4/IPv6 Translation Algorithm (RFC 6145). The Security Gateway performs N:M translation, supporting scenarios like Hide NAT behind a single IPv4 address or a range of addresses.

Getting Started with NAT

- 1. Learn about types of NAT Rules and types of NAT Methods (below in this topic).
- 2. Follow the applicable procedure:
 - *"Working with Automatic NAT Rules" on page 415* (for IPv4 or IPv6 translation)
 - *"Working with Manual NAT Rules" on page 425* (for IPv4 or IPv6 translation)
 - "Working with NAT46 Rules" on page 432 (for IPv4-to-IPv6 translation)
 - "Working with NAT64 Rules" on page 447 (for IPv6-to-IPv4 translation)
- 3. Configure the applicable NAT advanced settings (see "Advanced NAT Settings" on page 468).
- 4. Install the Access Control Policy.

Introduction

NAT (Network Address Translation) is a feature of the Firewall Software Blade and replaces IPv4 and IPv6 addresses to add more security. NAT protects the identity of a network and does not show internal IP addresses to the Internet.

The Security Gateway can change:

- The source IP address in a packet.
- The destination IP address in a packet.
- The TCP / UDP port in a packet.

Example flow

- 1. An internal computer sends a packet to an external computer
- 2. The Security Gateway translates the source IP address to a new one.
- 3. The packet comes back from the external computer

- 4. The Security Gateway translates the new IP address back to the original IP address.
- 5. The packet from the external computer goes to the correct internal computer.

Types of NAT Rules

In SmartConsole, you can create these types of NAT rules:

NAT Rules	How to create these NAT rules?	How to change these NAT rules?
Automatic NAT Rules	Management Server creates these rules automatically based on the NAT settings you configure in objects' properties (on the NAT page)	You must change the NAT settings in objects' properties on the NAT page.
Manual NAT Rule	You create these rules, select all objects and the NAT method.	You change these rules.

Important - A Security Management Server / Domain Management Server supports a maximum of 16384 NAT rules in one policy. <u>See sk82220</u>.

Types of NAT Methods

You can configure one of these NAT methods for Automatic NAT Rules and in Manual NAT Rules:

Hide

The Security Gateway changes the source IP address of all connections from a source to the same IP address - either that of the Security Gateway's outgoing interface, or an IP address you configure.

Hide > Hide behind gateway

The Security Gateway changes the source IP address of all connections from a source to the same IP address of the Security Gateway's outgoing interface.

Hide > Hide behind IP address

The Security Gateway changes the source IP address of all connections from a source to the same IP address your configure.

Notes:

 When you configure Hide NAT, connections can only start from internal computers.

The Security Gateway does **not** allow external traffic to access internal resources.

- If you enable this configuration in an object that represents one IP address (a Host object), then this gives you a one-to-one address translation.
- If you enable this configuration in an object that represents many IP addresses (a Network object, an Address Range object), then this gives you a many-to-one address translation.
- The Security Gateway uses port numbers to translate all specified internal IP addresses to a single external IP address port numbers from 600 to 1023, and from 10,000 to 60,000.

The Security Gateway can translate up to 50,000 connections at the same time.

- You cannot use Hide NAT for these configurations:
 - Traffic that uses protocols where the port number cannot be changed.
 - An external server that uses IP addresses to identify different computers and clients.


Example diagram



Item	Description
1	Internal computers
2	Security Gateway configured with Hide NAT
3	External computers and servers on the Internet

Sample Hide NAT Workflow

- 1. Internal computer A (10.10.0.26) sends a packet to an external computer.
- 2. The Security Gateway intercepts the packet and translates the source IP address from (10.10.0.26) to 192.0.2.1, and port 11000.
- 3. The external computer sends back a packet to 192.0.2.1, to port 11000.
- 4. The Security Gateway translates the packet's IP address from 192.0.2.1 to 10.10.0.26 and sends it to internal computer A.



Static

The Security Gateway changes the source IP address of all connections from a source to the IP address your configure.

Notes:

- When you configure Static NAT, the Security Gateway allows external traffic to access internal resources.
- If you enable this configuration in an object that represents one IP address (a Host object), then this gives you a one-to-one address translation.
- If you enable this configuration in an object that represents many IP addresses (a Network object, an Address Range object), then this gives you a many-to-one address translation.

The Security Gateway translates each internal IP address to a different external IP address.

Important - The range of the translated IP addresses is the same as the range of the source IP addresses.


Example diagram



Item	Description
1	Internal computers
2	Security Gateway configured with Static NAT
3	External computers and servers on the Internet

Example traffic flow with Static NAT

- 1. An external computer on the Internet sends a packet to 192.0.2.5.
- 2. The Security Gateway translates the IP address from 192.0.2.5 to 10.10.0.26 and sends the packet to internal computer A.
- 3. Internal computer A (10.10.0.26) sends back a packet to the external computer.
- 4. The Security Gateway intercepts the packet and translates the source IP address from 10.10.0.26 to 192.0.2.5.
- 5. Internal computer B (10.10.0.37) sends a packet to an external computer.
- 6. The Security Gateway intercepts the packet translates the source IP address from 10.10.0.37 to 192.0.2.16.



NAT Rules in SmartConsole

The NAT Rule Base has two sections in that specify how the IP addresses and Ports are translated:

- Original with columns Source, Destination, and Services
- Translated with columns Source, Destination, and Services

Example of Automatic NAT Rules

No	Origin al Sourc e	Original Destinat ion	Origin al Servic es	Translat ed Source	Translat ed Destinat ion	Translat ed Service s	Insta II On	Comme nts
Autom	atic Generated	Rules						
NAT R	ules for X (Y-Z)	,						
1	Object1	Object2	Any	= Original	= Original	= Original	Policy Target s	
2	Object3	Object4	Any	_S Object5	_S Object6	= Original	Policy Target s	
3	Object7	Object8	Any	_H Object9	_H Object10	= Original	Policy Target s	

Example of a Manual NAT rule

No	Origin al Sourc e	Original Destinat ion	Origin al Servic es	Translat ed Source	Translat ed Destinat ion	Translat ed Service s	Insta II On	Comme nts
Autom	atic Generated	Rules						
Manua	al Lower Rules							

4	Object11	Object12	Any	_S Object13	= Original	= Original	Policy Target s	
5	Object14	Object15	Any	= Original	_S Object16	= Original	Policy Target s	

Order of NAT Rule Enforcement

The Security Gateway enforces the NAT Rule Base in a sequential manner - in the order you place the rules in the NAT Policy (see the **No.** column).

The Security Gateway enforces Automatic NAT and Manual NAT rules in different ways.

Explanation

- Manual NAT rules The Security Gateway enforces the first Manual NAT rule that matches a connection. The Security Gateway does not examine other Manual NAT rules.
- Automatic NAT rules The Security Gateway can enforce two Automatic NAT rules that match a connection - one rule for the Source and one for the Destination. When a connection matches two Automatic NAT rules, the Security Gateway enforces those rules.
 - **Note** SmartConsole organizes the Automatic NAT rules in this order:
 - 1. Static NAT rules for the Security Gateway, or Host (computer or server) objects
 - 2. Hide NAT rules for the Security Gateway, or Host objects
 - 3. Static NAT rules for Network or Address Range objects
 - 4. Hide NAT rules for Network or Address Range objects

Working with Automatic NAT Rules

You can create Automatic NAT rules for these objects:

- Security Gateways
- Hosts
- Networks
- Address Ranges

The Management Server creates two Automatic NAT rules for Static NAT, to translate the source and the destination of the packets.

For Hide NAT, one rule translates the source of the packets.

For Network and Address Range objects, the Management Server creates a different rule to NOT translate intranet traffic. IP addresses for computers on the same object are not translated.

This table summarizes the Automatic NAT rules:

Type of Traffic	Automatic NAT - Static	Automatic NAT - Hide
Internal to external	Rule translates source IP address	Rule translates source IP address
External to internal	Rule translates destination IP address	N/A (External connections are not allowed)
Intranet (for network and address range objects)	Rule does not translate IP address	Rule does not translate IP address

Example of Automatic NAT Rules

Static NAT for a Network object

N o	Origin al Sourc e	Original Destinat ion	Origin al Servic es	Transla ted Source	Translat ed Destinat ion	Transla ted Service s	Install On	Comme nts	
--------	----------------------------	-----------------------------	------------------------------	--------------------------	-----------------------------------	--------------------------------	---------------	--------------	--

Automatic Generated Rules

NAT Rules for HR (1-3)

N o	Origin al Sourc e	Original Destinat ion	Origin al Servic es	Transla ted Source	Translat ed Destinat ion	Transla ted Service s	Install On	Comme nts
1	HR	HR	Any	= Origin al	= Origin al	= Origin al	Polic y Targe ts	
2	HR	Any	Any	_S HR (Valid Addres s)	= Origin al	= Origin al	Polic y Targe ts	
3	Any	HR (Valid Addres s)	Any	= Origin al	_S HR	= Origin al	Polic y Targe ts	

1. Intranet connections in the HR network are not translated.

The Security Gateway does not translate a connection between two computers that are part of the HR object.

The Security Gateway does not apply rules 2 and 3 to traffic that matches rule 1.

- 2. Connections from IP addresses from the HR network to any IP address (usually external computers) are translated to the Static NAT IP address.
- 3. Connections from any IP address (usually external computers) to the HR are translated to the Static NAT IP address.

Hide NAT for an Address Range object

N o	Origin al Sourc e	Original Destinat ion	Origin al Servic es	Transla ted Source	Translat ed Destinat ion	Transla ted Service s	Install On	Comme nts
		enerated Ru r Sales (1-2						
1	Sales	Sales	Any	= Origin al	= Origin al	= Origin al	Polic y Targe ts	

N o	Origin al Sourc e	Original Destinat ion	Origin al Servic es	Transla ted Source	Translat ed Destinat ion	Transla ted Service s	Install On	Comme nts
2	Sales	Any	Any	_H Sales (Hiding Addres s)	= Origin al	= Origin al	Polic Y Targe ts	

1. Intranet connections in the Sales address range are not translated.

The Firewall does not translate a connection between two computers that use IP addresses that are included in the Sales object.

The Firewall does not apply rule 2 to traffic that matches rule 1.

2. Connections from IP addresses from the Sales address range to any IP address (usually external computers) are translated to the Hide NAT IP address.

Configuring Automatic NAT


Configure the NAT settings in each object, for which you need to create Automatic NAT rules, and configure the Access Control rules to allow traffic to the applicable objects.

Procedure

- 1. From the left navigation panel, click Gateways & Servers.
- 2. Double-click the Security Gateway object.

The General Properties window of the gateway opens.

- 3. From the navigation tree, select **NAT > Advanced**.
- 4. Select Add automatic address translation rules to hide this Gateway behind another Gateway.
- 5. Select the Translation method: Hide or Static.
- 6. Configure the NAT IP address for the object.
 - Hide behind Gateway Uses the IP address of the corresponding Security Gateway's interface
 - Hide behind IP address Enter the IP address.
- 7. Click **Install on Gateway** and select **All** or the Security Gateway that translates the IP address.
- 8. Click OK.
- 9. Install the Access Control Policy.



Example Deployment


Example

The goal for this sample deployment is to configure:

Static NAT for the Email server and the Web server on the internal network.

These servers can be accessed from the Internet using public addresses.

Hide NAT for the users on the internal network that gives them Internet access.
 This network cannot be accessed from the Internet.



Item	Description
1	Internal computers (Alaska_LAN, IPv6 2001:db8::/64)
2	Web server (Alaska_Web, IPv6 2001:db8:0:10::5 is translated to IPv6 2001:db8:0:a::5)
3	Mail server (Alaska_Mail , IPv6 2001:db8:0:10::6 is translated to IPv6 2001:db8:0:a::6)
4	Security Gateway (Alaska_GW, external IPv6 2001:db8:0:a::1)
5	External computers and servers in the Internet

Configuration Procedure:

- 1. Configure Automatic Static NAT for the Web server:
 - a. Double-click the Alaska_Web object.
 - b. From the left, click **NAT**.
 - c. Select Add Automatic Address Translation Rules.
 - d. In Translation method, select Static.
 - e. Select Hide behind IP Address and enter 2001:db8:0:a::5.
 - f. Click OK
- 2. Enable Automatic Static NAT for the EMail server:
 - a. Double-click the Alaska_Mail object.
 - b. From the left, click **NAT**.
 - c. Select Add Automatic Address Translation Rules.

- d. In Translation method, select Static.
- e. Select Hide behind IP Address and enter 2001:db8:0:a::6.
- f. Click OK.
- 3. Enable Automatic Hide NAT for the internal computers:
 - a. Double-click the Alaska_LAN object.
 - b. From the left, click **NAT**.
 - c. Select Add Automatic Address Translation Rules.
 - d. In Translation method, select Hide.
 - e. Select Hide behind Gateway.
- 4. Click OK.
- 5. Install the Access Control Policy.

The Management Server creates these Automatic NAT rules in **Security Policies** view > **Access Control > NAT**:

N o	Origin al Sourc e	Original Destinat ion	Origin al Servic es	Transla ted Source	Translat ed Destinat ion	Transla ted Service s	Install On	Comme nts
--------	----------------------------	-----------------------------	------------------------------	--------------------------	-----------------------------------	--------------------------------	---------------	--------------

Automatic Generated Rules

NAT	NAT Rules for Sales (1-2)							
1	Alask a_ Web	Alaska_ Web	Any	= Origin al	= Origin al	= Origin al	Polic y Targe ts	
2	Alask a_ Web	Any	Any	S Alaska_ Web (Valid Addres s)	= Origin al	= Origin al	Polic y Targe ts	

N o	Origin al Sourc e	Original Destinat ion	Origin al Servic es	Transla ted Source	Translat ed Destinat ion	Transla ted Service s	Install On	Comme nts
3	Any	Alaska_ Web	Any	= Origin al	S Alaska_ Web (Valid Addres s)	= Origin al	Polic y Targe ts	
4	Alask a_ Mail	Alaska_ Mail	Any	= Origin al	= Origin al	= Origin al	Polic y Targe ts	
5	Alask a_ Mail	Any	Any	S Alaska_ Mail (Valid Addres s)	= Origin al	= Origin al	Polic y Targe ts	
6	Any	Alaska_ Mail	Any	= Origin al	S Alaska_ Mail (Valid Addres s)	= Origin al	Polic Y Targe ts	
7	Alask a_ LAN	Alaska_ LAN	Any	= Origin al	= Origin al	= Origin al	Polic Y Targe ts	
8	Alask a_ LAN	Any	Any	H Alaska_ LAN (Hiding Addres s)	= Origin al	= Origin al	Polic y Targe ts	


Automatic Hide NAT to External Networks

For large and complex networks, it can be impractical to configure the Hide NAT settings for all the internal IP addresses.

Explanation

An easy alternative is to enable a Security Gateway to automatically Hide NAT for all traffic with external networks. The Security Gateway translates all traffic that goes through an external interface to the valid IP address of that interface.

In this sample configuration, computers in internal networks open connections to external servers on the Internet. The source IP addresses of internal clients are translated to the IP address of an external interface.



Item	Description
1	Internal networks
2	Security Gateway is configured with Automatic Hide NAT.
2A and 2B	Two external interfaces 192.0.2.1 and 192.0.2.100.
1>3	External computers and servers on the Internet

Source IP addresses are translated to the applicable external interface IP address: **192.0.2.1** or **192.0.2.100**.

Note - If a connection matches a regular NAT rule and a NAT-for-internal-networks rule, the regular NAT rule takes precedence.

To enable Automatic Hide NAT:

- 1. From the left navigation panel, click Gateways & Servers.
- 2. Double-click the Security Gateway object.
- 3. From the navigation tree, click **NAT**.
- 4. Select Hide internal networks behind the Gateway's external IP.
- 5. Click OK.
- 6. Install the Access Control Policy.

Working with Manual NAT Rules

For some deployments, it is necessary to manually define the NAT rules.

For example:

- Rules that are restricted to specific destination IP addresses and to specific source IP addresses
- Translating both source and destination IP addresses in the same packet.
- Static NAT in only one direction
- Translating services (destination ports)
- Rules that only use specified services (ports)
- Translating IP addresses for dynamic objects

General workflow when working with manual NAT rules:

- 1. Create SmartConsole objects that use the valid (NATed) IP addresses.
- Create Manual NAT rules to translate the original IP addresses of the objects to valid IP addresses.
- 3. Configure the Access Control Policy to allow traffic to the applicable translated objects with the valid IP addresses.

Note - For Manual NAT rules, it is necessary to configure Proxy ARP entries to associate the translated IP address. See "Automatic and Proxy ARP" on page 468.

Example of a Manual NAT Rule

No	Origin al Sourc e	Original Destinat ion	Origin al Servic es	Translat ed Source	Translat ed Destinat ion	Translat ed Service s	Install On	Comme nts
1	HTT P_ Client	Web_ Server	http	= Origin al	_S Web_ Server	= Origin al	Polic y Targe ts	

Configuring Manual NAT

Procedure

- 1. From the left navigation tree, click Security Policies.
- 2. Click Access Control > NAT.
- 3. Add a new rule in one of these ways:
 - From the top toolbar, click the **Add Rule** icon (the leftmost icon).
 - If there are existing Manual NAT rules, then right-click in the No. column of the applicable rule > in the line New Rule, click Above or Below.
- 4. In the new rule, select the required objects and configure the required translation.

If the required objects do not exist, you can create them in the selection window (in the top right corner, click **New**).

5. Install the Access Control Policy.

Configuring Hide NAT behind Address Range

By default, when an administrator configures a Hide NAT rule and in the **Translated Source** column selects an Address Range object, the Security Gateway selects a Hide IP address from this range based only on the connection's source IP address.

You can configure the Security Gateway to select a Hide IP address from the configured range based on the connection's source IP address and source port:

- 1. Connect to the command line on the Security Gateway / each Cluster Member.
- 2. Enable the corresponding kernel parameter. Run:

fw ctl set -f int fwx hide range with port 1

3. Reboot the Security Gateway / each Cluster Member.




Note - In a cluster, this can cause a failover.

Example Deployment

Example

This example configuration shows how to let external computers access an internal web server and an internal mail server in a DMZ network from one IP address.

To do this, you must configure Hide NAT for the DMZ network object and create manual NAT rules for the servers.



Item	Description
1	External computers and servers on the Internet
2	Security Gateway (Alaska_GW, external IPv6 2001:db8:0:c::1)
3	DMZ network (Alaska_DMZ, IPv6 2001:db8:a::/128)
4	Web server (Alaska_DMZ_Web, IPv6 2001:db8:a::35:5 is translated to IPv6 2001:db8:0:c::1)
5	Mail server (Alaska_DMZ_Mail, IPv6 2001:db8:a::35:6 is translated to IPv6 2001:db8:0:c::1)

Configuration Procedure:

- 1. Configure Automatic Hide NAT for the DMZ network:
 - a. Double-click the Network object Alaska_DMZ.
 - b. From the left, click NAT.
 - c. Select Add Automatic Address Translation Rules.
 - d. In Translation method, select Hide.
 - e. Select Hide behind Gateway.
 - f. Click OK.

The Management Server creates these Automatic NAT rules in **Security Policies** view **> Access Control > NAT**:

N o.	Origi nal Sour ce	Origina I Destina tion	Origi nal Servi ces	Transl ated Source	Transla ted Destina tion	Transl ated Servic es	Install On	Comm ents
1	Alask a_ DMZ	Alaska_ DMZ	Any	= Origi nal	= Origi nal	= Origi nal	Poli cy Targ ets	
2	Alask a_ DMZ	Any	Any	H Alask a_DMZ (Hiding Addres s)	= Origi nal	= Origi nal	Poli cy Targ ets	

2. Create a Manual NAT rule to translate incoming HTTP traffic to the internal Web server:

- a. In SmartConsole, go to **Security Policies** view > **Access Control** > **NAT**.
- b. Add a new rule (#3) below the existing Automatic NAT rules.
- c. Select these objects:

N o.	Origi nal Sour ce	Origin al Destin ation	Origi nal Servi ces	Transl ated Sourc e	Transl ated Destin ation	Transl ated Servic es	Instal I On	Comm ents
1	Alas ka_ DMZ	Alask a_DMZ	Any	= Origi nal	= Origi nal	= Origi nal	Poli cy Targ ets	
2	Alas ka_ DMZ	Any	Any	H Alask a_ DMZ (Hidin g Addre ss)	= Origi nal	= Origi nal	Poli cy Targ ets	
3	Any	Alask a_GW	http	= Origi nal	S Alask a_ DMZ_ Web	= Origi nal	Poli cy Targ ets	

3. Create a Manual NAT rule to translate incoming SMTP traffic to the internal Mail server:

- a. Add a new rule (#4) below the existing NAT rules.
- b. Select these objects:

N o.	Origi nal Sour ce	Origin al Destin ation	Origi nal Servi ces	Transl ated Sourc e	Transl ated Destin ation	Transl ated Servic es	Instal I On	Comm ents
1	Alas ka_ DMZ	Alask a_DMZ	Any	= Origi nal	= Origi nal	= Origi nal	Poli cy Targ ets	
2	Alas ka_ DMZ	Any	Any	H Alask a_ DMZ (Hidin g Addre ss)	= Origi nal	= Origi nal	Poli cy Targ ets	
3	Any	Alask a_GW	http	= Origi nal	S Alask a_ DMZ_ Web	= Origi nal	Poli cy Targ ets	
4	Any	Alask a_GW	smtp	= Origi nal	S Alask a_ DMZ_ Mail	= Origi nal	Poli cy Targ ets	

4. Create an Access Control rule to allow the incoming HTTP and SMTP traffic to the internal servers:

- a. In SmartConsole, go to Security Policies > Access Control > NAT.
- b. Add a new rule.
- c. Select these objects:

N o	Name	Sour ce	Destina tion	VP N	Services & Applicati ons	Actio n	Tra ck	Install On
	Incomi ng HTTP and SMTP traffic to intern al server s	Any	Alaska_ DMZ	An Y	http smtp	Acce pt	Log	Polic y Targe ts

5. Install the Access Control Policy.

Working with NAT46 Rules



Note - NAT46 rules are only supported on Security Gateways and Cluster Members R80.20 and higher.

Overview

NAT46 rules translate IPv4 traffic to IPv6 traffic without maintaining any session information on a Security Gateway.

Properties of Stateless NAT46

- Performs 1:1 IP address mapping.
- The system generates the translated source IPv6 address as a combination of these two parts:
 - 1. A user-defined Network object with an IPv6 address defined with the 96-bit prefix.
 - 2. The source IPv4 address, which is added as a 32-bit suffix.

NAT46 use case scenarios

- [IPv4 Network] --- (Internet) --- [Security Gateway] --- [IPv6 Network] Common use case for Content Providers.
- [IPv4 Network] --- [Security Gateway] --- (Internet) --- [IPv6 Network]

Common use case for Enterprises.

Example of NAT46 Translation Flow

Example topology:

[IPv4 Client] --- (internal) [Security Gateway] (external) --- [IPv6 Server]

Where:

Item	Description
IPv4 Client	IPv4 real address is 192.168.2.55 IPv6 NATed address is 2001:DB8:90::192.168.2.55/ 96
Security Gateway internal interface	IPv4 address is 192.168.2.1/24
Security Gateway external interface	IPv6 address is 2001:DB8:5001::1/ 96

ltem	Description
IPv6 Server	IPv6 real address is 2001:DB8:5001::30/96 IPv4 NATed address is 1.1.1.66/24
IPv6 NATed network	IPv6 address of the network on the external Security Gateway side is 2001:DB8:90::/96 These IPv6 addresses are used to translate the IPv4 address of the IPv4 Client to IPv6 address
IPv4 NATed network	IPv4 address of the network on the internal Security Gateway side is 1.1.1.0/24 These IPv4 addresses are used to translate the IPv6 address of the IPv6 Server to IPv4 address

Traffic flow:

1. IPv4 Client opens an IPv4 connection to the NATed IPv4 address of the IPv6 Serve

From IPv4 address 192.168.2.55 to IPv4 address 1.1.1.66

- 2. Security Gateway performs these NAT translations:
 - a. From the source IPv4 address 192.168.2.55 to the source IPv6 address 2001:DB8:90::192.168.2.55/96
 - b. From the destination IPv4 address 1.1.1.66 to the destination IPv6 address 2001:DB8:5001::30
- 3. IPv6 Server receives this request connection as from the IPv6 address 2001:DB8:90::192.168.2.55/96 to the IPv6 address 2001:DB8:5001::30
- 4. IPv6 Server replies to this connection from the IPv6 address 2001:DB8:5001::30 to the IPv6 address 2001:DB8:90::192.168.2.55/96
- 5. Security Gateway performs these NAT translations:
 - a. From the source IPv6 address 2001:DB8:5001::30 to the source IPv4 address 1.1.1.66
 - b. From the destination IPv6 address 2001:DB8:90::192.168.2.55/96 to the destination IPv4 address 192.168.2.55
- 6. IPv4 Client receives this reply connection as from the IPv4 address 1.1.1.66 to the IPv4 address 192.168.2.55

To summarize:

Request: [IPv4 Client] ---> [Security Gateway] ---> [IPv6 Server]

Field in packet	Original IPv4 packet	NATed IPv6 packet
Source IP	192.168.2.55 / 24	2001:DB8:90::192.168.2.55/96
Destination IP	1.1.1.66/24	2001:DB8:5001::30 / 96

Reply: [IPv4 Client] <--- [Security Gateway] <--- [IPv6 Server]</p>

Field in packet	Original IPv6 packet	NATed IPv4 packet
Source IP	2001:DB8:5001::30 / 96	192.168.2.55 / 24
Destination IP	2001:DB8:90::192.168.2.55 / 96	1.1.1.66 / 24

Known Limitations for NAT46

- NAT46 rules are only supported on Security Gateways and Cluster Members R80.20 and higher.
- NAT46 does not support VoIP traffic.
- NAT46 does not support FTP traffic.
- NAT46 does not support protocols that require state information between Control and Data connections.

Configuring NAT46

Ð

Step 1 - Prepare Security Gateway / Cluster Members for NAT46

Note - In a Cluster, you must configure all the Cluster Members in the same way.

Step	Instructions
1	Make sure that an IPv6 address is assigned to the interface that connects to the destination IPv6 network, and the IPv6 network prefix length is equal to 96. Note - This can be any valid IPv6 address with the IPv6 network prefix length equal to 96.
	 In Gaia Portal: Click Network Management > Network Interfaces. In Gaia Clish: Run:
	show interface <name interface="" of=""> ipv6-address</name>
	If such IPv6 address is not assigned yet, assign it now. For details, see the <u>R82 Gaia Administration Guide</u> - Chapter Network Management - Section Network Interfaces - Section Physical Interfaces.

Step	Instructions						
2	Make sure that the routing is configured to send the traffic that is destined to the NATed IPv4 addresses (defined in the <i>Translated Destination</i> column in the NAT46 rule) through the interface that connects to the destination IPv6 network.						
	 In Gaia Portal: Click Advanced Routing > Routing Monitor. In Gaia Clish: Run: 						
	show route						
	If such route does not already exist, add it in Gaia Clish. For details, see the <u><i>R82 Gaia Administration Guide</i></u> . Run these commands in Gaia Clish: 1. Add the static route:						
	set static route <nated destination="" ipv4<br="">Addresses>/<nated ipv4="" mask="" net=""> nexthop gateway logical <name connects="" interface="" of="" that="" the<br="" to="">real IPv6 Network> on</name></nated></nated>						
	Example topology: [IPv4 Client] (NATed IPv4 of IPv6 side are 1.1.1.0/24) [Security Gateway] (eth3) [IPv6 Server] In such case, configure the IPv4 route using this command: set static route 1.1.1.0/24 nexthop gateway logical eth3 on						
	2. Save the configuration:						
	save config						

Step	nstructions							
3	ke sure that the number of IPv6 CoreXL Firewall instances is equal to the mber of IPv4 CoreXL Firewall instances.							
	 Connect to the command line on the Security Gateway. Log in to Gaia Clish, or Expert mode. Show the number of IPv6 CoreXL Firewall instances: 							
	 fw6 ctl multik stat 4. Show the number of IPv4 CoreXL Firewall instances. Run: fw ctl multik stat 							
	 5. If the number of IPv6 CoreXL Firewall instances is less than the number of IPv4 CoreXL Firewall instances, then do these steps: a. Run: 							
	 cpconfig b. Select Check Point CoreXL c. Select Change the number of IPv6 firewall instances d. Configure the number of IPv6 CoreXL Firewall instances to be the same as the number of IPv4 CoreXL Firewall instances e. Select Exit f. Reboot the Security Gateway 6. Connect to the command line on the Security Gateway. 7. Log in to Gaia Clish, or Expert mode. 8. Show the number of IPv6 CoreXL Firewall instances. Run: 							
	<pre>fw6 ctl multik stat 9. Show the number of IPv4 CoreXL Firewall instances. Run: fw ctl multik stat</pre>							
	Example output:							

[Expert@GW:0]# fw6 ctl multik stat									
-			ık stat nections Pe 	ak					
0 Yes	3		0	0					
1 Yes	2		0	4					
2 Yes	1		0	2					
[Expert@GW	:0]#								
[Expert@GW	:0]# fw c	tl multi	k stat						
ID Activ	e CPU	Con	nections Pe	ak					
0 Yes	3		10	14					
1 Yes	2		6	15					
2 Yes	1	I	7	15					

Step 2 - Configure NAT46 Rules

Configure NAT46 rules as Manual NAT rules in the Access Control Policy.

Make sure that you add Access Control rules that allow this NAT traffic.

 Configure an applicable source IPv4 object (IPv4 Host, IPv4 Address Range, or IPv4 Network).

To configure a source IPv4 Host object

- a. Click **Objects** menu > **New Host**.
- b. In the **Object Name** field, enter the applicable name.
- c. In the **Comment** field, enter the applicable text.
- d. Click the General page of this object.
- e. In the IPv4 address field, enter the source IPv4 address.
- f. In the IPv6 section:

Do not enter anything

g. On the NAT page of this object:

Do not configure anything.

- h. Configure the applicable settings on other pages of this object.
- i. Click OK.

To configure a source IPv4 Network object

- a. Click **Objects** menu > **New Network**.
- b. In the **Object Name** field, enter the applicable name.
- c. In the **Comment** field, enter the applicable text.
- d. Click the General page of this object.
- e. In the IPv4 section:
 - i. In the **Network address** field, enter the IPv4 address of your source IPv4 network.
 - ii. In the **Net mask** field, enter the net mask of your source IPv4 network.
- f. In the IPv6 section:

Do not enter anything.

g. On the NAT page of this object:

Do not configure anything.

h. Click OK.

To configure a source IPv4 Address Range object

- a. Click Objects menu > More object types > Network Object > Address Range > New Address Range.
- b. In the **Object Name** field, enter the applicable name.
- c. In the **Comment** field, enter the applicable text.
- d. Click the General page of this object.
- e. In the IPv4 section:
 - i. In the **First IP address** field, enter the first IPv4 address of your IPv4 addresses range.
 - ii. In the Last IP address field, enter the last IPv4 address of your IPv4 addresses range.
- f. In the **IPv6** section:

Do not enter anything.

g. On the NAT page of this object:

Do not configure anything.

h. Click OK.

2. Configure a destination IPv4 Host object.

This object represents the destination IPv4 address, to which the IPv4 sources connect.

To configure a translated destination IPv4 Host object

- a. Click Objects menu > New Network.
- b. In the **Object Name** field, enter the applicable name.
- c. In the **Comment** field, enter the applicable text.
- d. Click the General page of this object.
- e. In the IPv4 section:
 - i. In the **Network address** field, enter the IPv4 address of your destination IPv4 network.
 - ii. In the **Net mask** field, enter the net mask of your destination IPv4 network.
- f. In the **IPv6** section:

Do not enter anything.

g. On the NAT page of this object:

Do not configure anything.

- h. Click OK.
- 3. Configure a translated source IPv6 Network object with an IPv6 address defined with the 96-bit prefix.

This object represents the translated source IPv6 addresses, to which you translate the source IPv4 addresses.

To configure a translated source IPv6 Network object with an IPv6 address defined with the 96-bit prefix

- a. Click **Objects** menu > **New Network**.
- b. In the **Object Name** field, enter the applicable name.
- c. In the **Comment** field, enter the applicable text.
- d. Click the General page of this object.
- e. In the **IPv4** section:

Do not enter anything.

- f. In the IPv6 section:
 - i. In the Network address field, enter the translated source IPv6 address.
 - ii. In the **Prefix** field, enter the number 96.
- g. On the NAT page of this object:

Do not configure anything.

- h. Click OK.
- 4. Configure a translated destination IPv6 Host object.

This object represents the translated destination IPv6 address, to which the translated IPv4 sources connect.

To configure a translated destination IPv6 Host object

- a. Click **Objects** menu > **New Host**.
- b. In the **Object Name** field, enter the applicable name.
- c. In the **Comment** field, enter the applicable text.
- d. Click the General page of this object.
- e. In the IPv4 section:

Do not enter anything.

f. In the **IPv6** section:

In the Network address field, enter the destination static IPv6 address.

g. On the NAT page of this object:

Do not configure anything.

- h. Configure the applicable settings on other pages of this object.
- i. Click OK.
- 5. Create a Manual NAT46 rule.

Procedure

2 : -	👕 Objects 🔹 🔮 Install Policy				â Dis	
	Standard +					
GATEWAYS	• Access Control		+	≣• × Ξ ⊕ ₫/	Actions • Search 1	
& SERVERS	- 🚛 Policy	No.	Original Source	Original Destination	Original Services	
	📚 Network	Automati	ic Generated Rules : Mach	ine Static NAT (No Rules)		
SECURITY	📚 Access Control - Layer 1	Automati	ic Generated Rules : Mach	ine Hide NAT (No Rules)		
POLICIES	📚 Access Control - Layer 2	Automatic Generated Rules : Address Range Static NAT (No Rules)				
~	IS NAT	Automati	ic Generated Rules : Netw	ork Static NAT (No Rules)		
LOGS &	Qo5	Automatic Generated Rules : Address Range Hide NAT (No Rules)				
MONITOR	<u> </u>	Automati	ic Generated Rules : Netw	ork Hide NAT (1-2)		
	 Threat Prevention 	Manual L	ower Rules (No Rules)	_		
÷	💵 Policy			New Rule	Above Below	
MANAGE & SETTINGS	Exceptions			New Section Title	Above Below	
				Paste	Above Below	
	Shared Policies			Delete		
	🕨 🧭 Geo Policy			Rename		
	HTTPS Inspection			Converting		
	🌽 Inspection Settings 🗖			Copy as Image		

<u>⊡</u> : -	😭 Objects 🔹 🔮 Install Policy	😍 Install Policy 🌐 Discard Session 👻 2 🥎 Publish							
	Standard +								
GATEWAYS	* Access Control		[,≣r × I≣ ÷II	Actions • Search		٩		
& SERVERS	- 🗓 Policy	No.	Original Source	Original Destination	Original Services	Translated Source	Translated Destination	Translated Services	
	📚 Network	Automatic	Generated Rules : Mad	chine Static NAT (No Rules)	1				
SECURITY	📚 Access Control - Layer 1	Automatic	Automatic Generated Rules : Machine Hide NAT (No Rules)						
POLICIES	Access Control - Laver 2	Automatic	Generated Rules : Add	dress Range Static NAT (No	Rules)				
	NAT	Automatic	Generated Rules : Net	work Static NAT (No Rules)				
~		Automatic	Generated Rules : Add	dress Range Hide NAT (No	Rules)				
LOGS & MONITOR	📀 QoS	Automatic	Automatic Generated Rules : Network Hilde NAT (1-2)						
	Threat Prevention	 Manual Lo 	wer Rules (3)						
٢	Policy	3	🔪 * Any	A IPv4-Destinations	* Any	Sup IPv6-NATed-Source	🐝 _s IPv6-Destinations	Original	
MANAGE &	Exceptions					10			

- a. From the left Navigation Toolbar, click Security Policies.
- b. In the top Access Control section, click NAT.

c. Right-click on the **Manual Lower Rules** section title, and near the **New Rule**, click **Above** or **Below**.

Original Source	Original Destinatio n	Original Service s	Translate d Source	Translated Destinatio n	Translate d Services
*Any or Source IPv4 Host object or Source IPv4 Addres s Range object or Source IPv4 Networ k object	IPv4 Host object	*Any	IPv6 Network object with an IPv6 address defined with the 96-bit prefix	IPv6 Host object	= Original

Configure this NAT46 rule:

Do these steps:

i. In the Original Source column, add the applicable IPv4 object.

In this rule column, NAT46 rules support only these types of objects:

- *Any
- Host with a static IPv4 address
- Address Range with IPv4 addresses
- Network with IPv4 address

ii. In the **Original Destination** column, add the IPv4 **Host** object that represents the destination IPv4 address, to which the IPv4 sources connect.

In this rule column, NAT46 rules support only IPv4 Host objects.

- iii. In the Original Services column, you must leave the default Any.
- iv. In the **Translated Source** column, add the IPv6 **Network object** with an IPv6 address defined with the 96-bit prefix.

In this rule column, NAT64 rules support only IPv6 Network objects with an IPv6 address defined with the 96-bit prefix.

v. In the **Translated Source** column, right-click the IPv6 **Network object** with the 96-bit prefix > click **NAT Method** > click **Stateless NAT46**.

The 46 icon shows in the Translated Source column.

vi. In the **Translated Destination** column, add the IPv6 **Host** object represents the translated destination IPv6 address, to which the translated IPv4 sources connect.

In this rule column, NAT46 rule supports only an IPv6 Host objects.

vii. In the **Translated Services** column, you must leave the default = **Original**.

To summarize, you must configure only these NAT46 rules (rule numbers are for convenience only):

#	ŧ	Origin al Source	Original Destinati on	Original Service s	Translat ed Source	Translate d Destinati on	Translat ed Services
-	1	*Any	IPv4 <i>Host</i> object	*Any	IPv6 <i>Network</i> object with an IPv6 address defined with the 96-bit prefix	IPv6 <i>Host</i> object	= Origina l

#	Origin al Source	Original Destinati on	Original Service s	Translat ed Source	Translate d Destinati on	Translat ed Services
2	IPv4 <i>Host</i> object with a static IPv4 addres s	IPv4 <i>Host</i> object	*Any	IPv6 <i>Network</i> object with an IPv6 address defined with the 96-bit prefix	IPv6 <i>Host</i> object	= Origina l
3	IPv4 <i>Addres</i> <i>s</i> <i>Range</i> object	IPv4 <i>Host</i> object	*Any	IPv6 <i>Network</i> object with an IPv6 address defined with the 96-bit prefix	IPv6 <i>Host</i> object	= Origina l
4	IPv4 <i>Networ</i> <i>k</i> object	IPv4 <i>Host</i> object	*Any	IPv6 <i>Network</i> object with an IPv6 address defined with the 96-bit prefix	IPv6 <i>Host</i> object	= Origina l

6. Install the Access Control Policy.

Logging of NAT46 Traffic

Explanation

In the Security Gateway log for NAT64 connection, the source and destination IPv6 addresses show in their original IPv6 format.

To identify a NAT46 entry, look in the **More** section of the **Log Details** window.

Field in Log	Description
Xlate (NAT) Source IP	Shows the translated source IPv6 address, to which the Security Gateway translated the original source IPv4 address
Xlate (NAT) Destination IP	Shows the translated destination IPv6 address, to which the Security Gateway translated the original destination IPv4 address
More	Identifies the entry as NAT46 traffic (Nat46 enabled)

Working with NAT64 Rules

Overview

NAT64 translation (<u>RFC 6146</u>) lets **IPv6-only client** communicate with **IPv4-only server** using **unicast** UDP, TCP, or ICMP.

Definition on an IPv6-only client

One of these:

- A host with a networking stack that implements only IPv6.
- A host with a networking stack that implements both IPv4 and IPv6 protocols, but with only IPv6 connectivity.
- A host that runs an IPv6-only client application.

Definition of an IPv4-only server

One of these:

- A host with a networking stack that implements only IPv4.
- A host with a networking stack that implements both IPv4 and IPv6 protocols, but with only IPv4 connectivity.
- A host that runs an IPv4-only server application.

The translation of IP addresses is done by translating the packet headers according to the IP/ICMP Translation Algorithm defined in <u>RFC 6145</u>. The IPv4 addresses of IPv4 hosts are translated to and from IPv6 addresses using the algorithm defined in <u>RFC 6052</u>, and an IPv6 prefix assigned to the stateful NAT64 for this specific purpose.

Note - For information about DNS64, see RFC 6147.

Properties of Stateful NAT64

ï

- Performs N:M translation:
 - N must be greater than M
 - If M=1, performs a Hide NAT behind a single IPv4 address.
 - If M>1, performs a Hide NAT behind a range of IPv4 addresses.
- Gives good IPv4 address preservation (multiplexed using ports).
- Saves connection states and binding.

- There are no requirements on the assignment of IPv6 addresses to IPv6 clients. Any mode of IPv6 address assignment is legitimate (Manual, DHCP6, SLAAC).
- It is a scalable solution.

NAT64 use case scenarios

- [IPv6 Network] --- (Internet) --- [Security Gateway] --- [internal IPv4 Network]
 Common use case for Content Providers. DNS64 is not needed.
- [internal IPv6 Network] --- [Security Gateway] --- (Internet) --- [IPv4 Network]
 Common use case for Carriers, ISPs, Enterprises. DNS64 is required.
- [IPv6 Network] --- [Security Gateway] --- [IPv4 Network]

Common use case for Enterprises. DNS64 is required.

Standards supported for NAT64

- <u>RFC 6144</u> Framework for IPv4/IPv6 Translation
- <u>RFC 6146</u> Stateful NAT64: Network Address and Protocol Translation from IPv6 Clients to IPv4 Servers
- RFC 6052 IPv6 Addressing of IPv4/IPv6 Translators
- <u>RFC 6145</u> IP/ICMP Translation Algorithm
- RFC 2428 FTP Extensions for IPv6 and NATs
- <u>RFC 6384</u> An FTP Application Layer Gateway (ALG) for IPv6-to-IPv4 Translation

Known Limitations for NAT64

NAT64 rules do not support:

- VoIP traffic.
- HTTPS Inspection.
- SSL de-multiplexer.
- Security Gateway in HTTP Proxy mode.
- IPS protection "HTTP Header Spoofing".

Example of NAT64 Translation Flow

Example topology

[IPv6 Client] --- (interface) [Security Gateway] (internal) --- [IPv4 Server]

Where:

Item	Description
IPv6 Client	IPv6 real address is 1111:1111::0100/96
Security Gateway external interface	IPv6 address is 1111:1111::1/96
Security Gateway internal interface	IPv4 address is 10.0.0.1/24 IPv6 address is 3333:4444::1/96
IPv4 Server	IPv4 real address is 10.0.0.100/24 IPv6 NATed address is 1111:2222::0A00:0064/96
IPv6 NATed network	IPv6 address of the network on the external Security Gateway side is 1111:2222::/96 These IPv6 addresses are used to translate the IPv4 address of the IPv4 Server to the IPv6 address
IPv4 NATed network	IPv4 address of the network on the internal Security Gateway side is 1.1.1.0/24 These IPv4 addresses are used to translate the IPv6 address of the IPv6 Client to the IPv4 address

Example traffic flow

1. IPv6 Client opens an IPv6 connection to the NATed IPv6 address of the IPv4 Server:

From the IPv6 Client's IPv6 real address 1111:1111::0100 to the IPv4 Server's NATed IPv6 address 1111:2222::0A00:0064

Where:

The "1111:2222::" part is the NATed IPv6 subnet

The "0A00:0064" part is 10.0.0.100

2. Security Gateway performs these NAT translations:

 Translate the IPv6 Client's *source* address from the real IPv6 address 1111:1111:0100 to the special concatenated *source* IPv6 address 0064:FF9B::0101:01X

Where:

The "0064:FF9B::" part is a well-known prefix reserved for NAT64 (as defined by the RFC)

The "0101:01XX" part is 1.1.1.X

- b. Translate the IPv6 Client's *source* address from the special concatenated *source* IPv6 address 0064:FF9B::0101:01XX to the *source* IPv4 address 1.1.1.X
- c. Translate the IPv6 Client's NATed *destination* address from the IPv6 address 1111:2222::0A00:0064 to the NATed destination IPv4 address 10.0.0.100
- 3. IPv4 Server receives this request connection as from the *source* IPv4 address 1.1.1.X to the *destination* IPv4 address 10.0.0.100
- 4. IPv4 Server replies to this connection from the *source* IPv4 address 10.0.0.100 to the *destination* IPv4 address 1.1.1.X
- 5. Security Gateway performs these NAT translations:
 - a. Translate the IPv4 Server's *source* real IPv4 address 10.0.0.100 to the *source* NATed IPv6 address 1111:2222::0A00:0064
 - b. Translate the IPv6 Client's NATed *destination* IPv4 address 1.1.1.X to the *destination* special concatenated IPv6 address 0064:FF9B::0101:01X

Where:

The "64:FF9B::" part is a well-known prefix reserved for NAT64 (as defined by the RFC)

The "0101:01XX" part is 1.1.1.X

- c. Translate the IPv6 Client's *destination* special concatenated IPv6 address 0064:FF9B::0101:01XX to the *destination* IPv6 real address 1111:1111::0100
- 6. IPv6 Client receives this reply connection as from the *source* IPv6 address 1111:2222::0A00:0064 to the *destination* IPv6 address 1111:1111::0100

Example summary

Request: [IPv6 Client] ---> [Security Gateway] ---> [IPv4 Server]

Field in packet	Original IPv6 packet	NATed IPv4 packet	
Source IP	1111:1111::0100/96	1.1.1.X/24	
Destination IP	1111:2222::0A00:0064/96	10.0.0.100 / 24	

Reply: [IPv6 Client] <--- [Security Gateway] <--- [IPv4 Server]</p>

Field in packet	Original IPv4 packet	NATed IPv6 packet	
Source IP	10.0.0.100 / 24	1111:2222::0A00:0064 / 96	
Destination IP	1.1.1.X / 24	1111:1111::0100 / 96	

Configuring NAT64

C

Step 1 - Prepare the Security Gateway for NAT64

Note - In a Cluster, you must configure all the Cluster Members in the same way.

Step	Instructions
1	 Make sure that an IPv6 address is assigned to the interface that connects to the destination IPv4 network, and the IPv6 network prefix length is equal to, or less than 96. Note - This can be any valid IPv6 address with the IPv6 network prefix length equal to, or less than 96.
	 In Gaia Portal: Click Network Management > Network Interfaces. In Gaia Clish: Run:
	show interface <name interface="" of=""> ipv6-address</name>
	If such IPv6 address is not assigned yet, assign it now. For details, see the <u>R82 Gaia Administration Guide</u> - Chapter Network Management - Section Network Interfaces - Section Physical Interfaces.

Step	Instru	Instructions			
2	to the	sure that the IPv6 routing is configured to send the traffic that is destined NATed IPv6 addresses (defined in the <i>Original Destination</i> column in the 64 rule) through the interface that connects to the destination IPv4 ork.			
		In Gaia Portal: Click Advanced Routing > Routing Monitor . In Gaia Clish: Run:			
		show ipv6 route			
	For d Run t	h route does not already exist, add it in Gaia Clish. etails, see the <u>R82 Gaia Administration Guide</u> . hese commands in Gaia Clish: Add the static route:			
	-	set ipv6 static-route <nated destination="" ipv6<br="">Addresses>/<96 or less> nexthop gateway <any ipv6<br="">Address from the IPv6 subnet of the Interface that connects to the destination real IPv4 network> on</any></nated>			
		Example topology: [IPv6 Client] (NATed IPv6 of IPv4 side are 1111:2222::/96) [Security Gateway] (eth3 with IPv6 3333:4444::1) [IPv4 Server] In such case, configure the IPv6 route using this command: set ipv6 static-route 1111:2222::/96 nexthop gateway 3333:4444::10 on			
	b.	Save the configuration:			
		save config			

Step	Instructions				
3	Make sure that the number of IPv6 CoreXL Firewall instances is equal to the number of IPv4 CoreXL Firewall instances.				
	 Connect to the command line on the Security Gateway. Log in to Gaia Clish, or Expert mode. Show the number of IPv6 CoreXL Firewall instances: 				
	fw6 ctl multik stat				
	4. Show the number of IPv4 CoreXL Firewall instances:				
	fw ctl multik stat				
	 If the number of IPv6 CoreXL Firewall instances is less than the number of IPv4 CoreXL Firewall instances, then do these steps: i. Run: 				
	cpconfig				
	 iii. Select Change the number of IPv6 firewall instances iv. Configure the number of IPv6 CoreXL Firewall instances to be the same as the number of IPv4 CoreXL Firewall instances v. Select Exit vi. Reboot the Security Gateway 6. Connect to the command line on the Security Gateway. 7. Log in to Gaia Clish, or Expert mode. 8. Show the number of IPv6 CoreXL Firewall instances: 				
	fw6 ctl multik stat				
	9. Show the number of IPv4 CoreXL Firewall instances: fw ctl multik stat Example output:				
	[Expert@GW:0]# fw ctl multik ID Active CPU Connections Peak				
	0 Yes 3 10 14 1 Yes 2 6 15 2 Yes 1 7 15 [Expert@GW:0]# [Expert@GW:0]# fw6 ctl multik stat ID Active CPU Connections Peak				
	0 Yes 3 0 0 1 Yes 2 0 4 2 Yes 1 0 2 [Expert@GW:0]#				

Step 2 - Configure NAT64 Rules

Define NAT64 rules as Manual NAT rules in the Access Control Policy.

Make sure that you add access rules that allow this NAT traffic.

1. Define a source IPv6 Network object.

This object represents the source IPv6 addresses, which you translate to source IPv4 addresses.

Procedure

- a. Click **Objects** menu > **New Network**.
- b. In the **Object Name** field, enter the applicable name.
- c. In the **Comment** field, enter the applicable text.
- d. Click the General page of this object.
- e. In the IPv4 section:

Do not enter anything.

- f. In the IPv6 section:
 - i. In the **Network address** field, enter the IPv6 address of your IPv6 network, which you translate to source IPv4 addresses.
 - ii. In the **Prefix** field, enter the prefix of your IPv6 network.
- g. On the NAT page of this object:

Do not configure anything.

h. Click OK.

New Network Q 😯 🗙						
.	IPv6-Sources	te IPv6 addresses				
General	IPv4					
NAT	Network address:					
	Net mask:					
	Broadcast address: Included					
	 Not included 					
	IPv6					
	Network address:	2001:db8::900d:f000				
	Prefix:	120				
	🥑 Add Tag					
		OK Cancel				

2. Define a translated destination IPv6 Network object with an IPv4-embedded IPv6 address, or a translated destination IPv6 Host object with a static IPv6 address.

This object represents the translated destination IPv6 address, to which the IPv6 sources connect.

Procedure

- a. Click **Objects** menu > **New Network**.
- b. In the **Object Name** field, enter the applicable name.
- c. In the **Comment** field, enter the applicable text.
- d. Click the General page of this object.
- e. In the IPv4 section:

Do not enter anything.

- f. In the IPv6 section:
 - i. In the **Network address** field, enter the destination *IPv4-embedded* IPv6 address (also called *IPv4-mapped* IPv6 address), to which the IPv6 sources connect.

Such IPv6 address contains (from left to right) 80 "zero" bits, followed by 16 "one" bits, and then the 32 bits of the IPv4 address - 0:0:0:0:0:FFFF:X.Y.Z.W, where X.Y.Z.W are the four octets of the destination IPv4 address.

For example, for IPv4 network 192.168.3.0, the IPv4-embedded IPv6 address is 0:0:0:0:0:FFFF:192.168.3.0, or 0:0:0:0:0:FFFF:C0A8:0300. For more information, see <u>RFC 6052</u>.

These IPv4-embedded IPv6 addresses are published by an external DNS64 server.

ii. In the **Prefix** field, enter the applicable IPv6 prefix.

Note - You can define IPv4-embedded IPv6 addresses only for these object types: Address Range, Network, and Host.

g. On the NAT page of this object:

Do not configure anything.

h. Click OK.

Network		Q, 🕑 X
.	IPv6-Destination	ons
General	IPv4	
NAT	Network address:	
	Net mask:	
	Broadcast address:	
	 Included Not included 	
	IPv6	
	Network address:	::ffff:C0A8:0300
	Prefix:	120
	🥑 Add Tag	
		OK Cancel

3. Define a translated source IPv4 Address Range object.

This object represents the translated source IPv4 addresses, to which you translate the original source IPv6 addresses.

Procedure

- a. Click Objects menu > More object types > Network Object > Address Range > New Address Range.
- b. In the **Object Name** field, enter the applicable name.
- c. In the **Comment** field, enter the applicable text.
- d. Click the General page of this object.

- e. In the IPv4 section:
 - i. In the **First IP address** field, enter the first IPv4 address of your IPv4 addresses range, to which you translate the source IPv6 addresses.
 - ii. In the **Last IP address** field, enter the last IPv4 address of your IPv4 addresses range, to which you translate the source IPv6 addresses.
 - Notes:
 - This IPv4 addresses range must not use private IPv4 addresses (see <u>RFC 1918</u> and <u>Menu > Global properties ></u> Non Unique IP Address Range
 - This IPv4 addresses range must not be used on the IPv4 side of the network.
 - We recommend that you define a large IPv4 addresses range for more concurrent NAT64 connections.
- f. In the IPv6 section:

Do not enter anything.

g. On the NAT page of this object:


Do not configure anything.

h. Click OK.

Address Rai	nge	୯ ଡ ଼ା ×
	IPv4-Range-to Address Range object fo	-Hide-IPv6-Sources or IPv4 addresses range
General	IPv4	
NAT	First IP address:	10.10.10.1
	Last IP address:	10.10.10.100
	IPv6	
	First IPv6 address:	
	Last IPv6 address:	
		OK Cancel

4. Create a Manual NAT64 rule.

Procedure



- a. From the left navigation tree, click Security Policies.
- b. In the top Access Control section, click NAT.

c. Right-click on the **Manual Lower Rules** section title, and near the **New Rule**, click **Above** or **Below**.

Configure this Manual NAT64 rule:

- **Important** Some combinations of object types are not supported in the *Original Source* and *Original Destination* columns. See the summary table with the supported NAT rules at the bottom of this section.
 - i. In the **Original Source** column, add the IPv6 object for your original source IPv6 addresses.

In this rule column, NAT64 rules support only these types of objects:

- *Any
- Host with a static IPv6 address
- Address Range with IPv6 addresses
- Network with IPv6 address
- ii. In the **Original Destination** column, add a translated destination IPv6 object with an IPv4-embedded IPv6 address.

In this rule column, NAT64 rules support only these types of objects:

- Host with a static IPv6 address
- Address Range with IPv4-embedded IPv6 addresses
- Network with an IPv4-embedded IPv6 address
- iii. In the Original Services column, you must leave the default Any.
- iv. In the **Translated Source** column, add the IPv4 **Address Range** object for your translated source IPv4 addresses range.

In this rule column, NAT64 rules support only these types of objects:

- Host with a static IPv4 address, only if in the Original Source column you selected a Host with a static IPv6 address
- Address Range with IPv4 addresses

- v. In the **Translated Source** column, right-click the IPv4 **Address Range** object > click **NAT Method** > click **Stateful NAT64**:
 - The Translated Packet Destination column shows = Embedded IPv4 Address.
 - The 64 icon shows in both the Translated Source and Translated Destination columns.

In this rule column, NAT64 rule supports only these types of objects:

- Host with a static IPv4 address, only if in the Original Source column you selected a Host with a static IPv6 address
- Embedded IPv4 Address
- vi. In the **Translated Services** column, you must leave the default = **Original**.
- d. Install the Access Control Policy.
- 5. Install the Access Control Policy.

To summarize, you must configure only these Manual NAT64 rules (rule numbers are for convenience only):

#	Original Source	Original Destination	Original Services	Translated Source	Translated Destination	Translated Services
1	*Any	IPv6 <i>Host</i> object with a static IPv6 address	*Any	IPv4 <i>Address</i> <i>Range</i> object	IPv4 <i>Host</i> object	= Original
2	*Any	IPv6 <i>Address</i> <i>Range</i> object with an IPv4- embedded IPv6 addresses	*Any	IPv4 <i>Address</i> <i>Range</i> object	Embedded IPv4 Address	= Original

#	Original Source	Original Destination	Original Services	Translated Source	Translated Destination	Translated Services
3	*Any	IPv6 <i>Network</i> object with an IPv4- embedded IPv6 address	*Any	IPv4 <i>Address</i> <i>Range</i> object	Embedded IPv4 Address	= Original
4	IPv6 <i>Host</i> object with a static IPv6 address	IPv6 <i>Host</i> object with a static IPv6 address	*Any	IPv4 <i>Host</i> object	IPv4 <i>Host</i> object	= Original
5	IPv6 <i>Host</i> object with a static IPv6 address	IPv6 Address Range object with IPv4- embedded IPv6 addresses	*Any	IPv4 <i>Address</i> <i>Range</i> object	Embedded IPv4 Address	= Original
6	IPv6 <i>Host</i> object with a static IPv6 address	IPv6 <i>Network</i> object with an IPv4- embedded IPv6 address	*Any	IPv4 <i>Address</i> <i>Range</i> object	Embedded IPv4 Address	= Original
7	IPv6 <i>Address</i> <i>Range</i> object	IPv6 <i>Host</i> object with a static IPv6 address	*Any	IPv4 <i>Address</i> <i>Range</i> object	IPv4 <i>Host</i> object	= Original

#	Original Source	Original Destination	Original Services	Translated Source	Translated Destination	Translated Services
8	IPv6 <i>Address</i> <i>Range</i> object	IPv6 Address Range object with IPv4- embedded IPv6 addresses	*Any	IPv4 <i>Address</i> <i>Range</i> object	Embedded IPv4 Address	= Original
9	IPv6 <i>Address</i> <i>Range</i> object	IPv6 <i>Network</i> object with an IPv4- embedded IPv6 address	*Any	IPv4 <i>Address</i> <i>Range</i> object	Embedded IPv4 Address	= Original
10	IPv6 <i>Network</i> object	IPv6 <i>Host</i> object with a static IPv6 address	*Any	IPv4 <i>Address</i> <i>Range</i> object	IPv4 <i>Host</i> object	= Original
11	IPv6 <i>Network</i> object	IPv6 Address Range object with IPv4- embedded IPv6 addresses	*Any	IPv4 <i>Address</i> <i>Range</i> object	Embedded IPv4 Address	= Original
12	IPv6 <i>Network</i> object	IPv6 <i>Network</i> object with an IPv4- embedded IPv6 address	*Any	IPv4 <i>Address</i> <i>Range</i> object	Embedded IPv4 Address	= Original

⊡ : -	📬 Objects 🔹 处 Install Policy		🏛 Discard Session 👻 3 🎙	Publish	
	Standard +				
GATEWAYS	↔ Access Control		🛓 🖆 Actions 🛛 Search for IP, object, action,	٩	· ^ Ţ
& SERVERS	- 🚺 Policy	No. Original Source Original Desti	ation Original Services Translated Source	Translated Destination	Translated Services Install On
	📚 Network	Automatic Generated Rules : Machine Static NAT (N	o Rules)		
SECURITY	📚 Access Control - Layer 1	Automatic Generated Rules : Machine Hide NAT (No	Rules)		
POLICIES	S Access Control - Layer 2	Automatic Generated Rules : Address Range Static	IAT (No Rules)		
	10 NAT	Automatic Generated Rules : Network Static NAT (N	o Rules)		
		Automatic Generated Rules : Address Range Hide N	AT (No Rules)		
LOGS & MONITOR	📀 QoS	Automatic Generated Rules : Network Hide NAT (1-2) Manual Lower Rules (3)			
	 Threat Prevention 				
Ö	🚺 Policy	3 🔨 👗 IPv6-Sources 👗 IPv6-Desti	ations * Any 😁 IPv4-Range-to-Hide-IPv6-S	iources = Embedded IPv4 Address	= Original * Policy Targets
MANAGE & SETTINGS	Exceptions		UT	UT.	

Step 3 - Configure additional settings for NAT64

You can configure the additional settings that control the NAT64 translation mechanism.

These settings are compliant with RFC 6145.

Best Practice - We recommend that you change the default settings only if you are familiar with the technology.

Procedure

- 1. Close all SmartConsole windows connected to the Management Server.
- 2. Connect with Database Tool (GuiDBEdit Tool) to the applicable Security Management Server or Domain Management Server.
- 3. In the top left section, click Table > Global Properties > properties.
- 4. In the top right section, click **firewall_properties**.
- 5. In the bottom section, scroll to these Field Names:
 - nat64 add UDP checksum
 - nat64 avoid PMTUD blackhole
 - nat64 copy type of service
 - nat64 error message on dropped packets

🛢 172.23.57.66 - Check Point Database	Tool					
File View Objects Fields Search Queries He	elp					
ි ච 📃 💷						
Tables Queries		Object Nam	ne 🛆	Class Name	1	Last Modify Time
	1	Carop_do	wn_mapping_container	drop_down	_mapping_container	Mon Mar 12 05:15:33 2018
		firewall_		firewall_pro	perties	Mon Mar 12 16:08:47 2018
Administrators Arti-Malware Cosktop Co	T	l∰span_po	rt_configuration	span_port_	properties	Mon Mar 12 05:15:33 2018
Field Name	Туре	Value	Valid Values	Default Value	Field description	
nac_pep_services	boolean	true		true	Accept PEPC connection	ns to PEP server
nac_pep_services_p	string	first	{first,last,before last}	first	PEP services Implied Ru	ule Position
nat64_add_UDP_checksum	boolean	false			NAT64: add udp checks	sum to IPv6 header
nat64_avoid_PMTUD_blackhole boolean		false			NAT64: set df and identification value on ipv4 header	
nat64_copy_type_of_service boolean		true		true	NAT64: Copy type of s	ervice.
nat64_error_message_on_dropped_packets boolean		true		true	NAT64: generate error	messages on dropped packets during translation
nat_automatic_arp boolean		true		true	Automatic ARP configur	ration
nat_automatic_ndp	boolean	true		true	Automatic Neighbour Di	iscovery Protocol configuration

6. Right-click the applicable parameter in the Field Name column and click Edit.

7.	Select the applicable Value	(true, or false)	and click OK.
----	-----------------------------	-------------------------	---------------

Field Name	Description
nat64_add_UDP_ checksum	This parameter controls whether the translator should calculate and add a valid UDP checksum value to a packet, if the packet checksum value is zero. This is important because, by default, an IPv4 UDP packet with a checksum value of zero is dropped on the IPv6 side. Default: false
nat64_avoid_ PMTUD_ blackhole	This parameter controls whether to allow packet fragmentation on the IPv4 (destination) side during PMTU discovery. Enable this setting if some equipment combinations cause PMTU discovery to fail. Default: false
nat64_copy_ type_of_ service	This parameter controls whether to copy the traffic Class Field to the Type Of Service field, and set the Type Of Service field in the translated packet to zero. Default: true

Field Name	Description
nat64_error_ message_on_ dropped_ packets	 This parameter controls whether to generate an audit log after a connection is closed. For each closed connection, the log shows: Connection information (source and destination IP address, source port, and service). Translated source IP address and source port. Start time and end time. If the connection was closed because the connection expired, log shows additional information in the TCP End Reason field. If this field does not show in the log, the connection was closed with a TCP RST, or with a TCP FIN, and did not expire. Default: true

- 8. Save the changes (click **File > Save All**).
- 9. Close the Database Tool (GuiDBEdit Tool).
- 10. Connect with the SmartConsole to the applicable Security Management Server or Domain Management Server.
- 11. Install the Access Control Policy.

Logging of NAT64 traffic

Explanation

In the Security Gateway log for NAT64 connection, the source and destination IPv6 addresses show in their original IPv6 format.

To identify a NAT64 entry, in the Log Details window, look at the More section.

Log Details					_	n x
Accept Traffic Acce	pted			^	~	ſ.
Log Info		~	NAT			~
Origin	📼 M2		Xlate (NAT) Source	1.1.1.3		
Time	💿 Today, 11:49:45 AM		Xlate (NAT) Destinat	orig_v4_src_1 (10.6.150.100)		
Blade	Firewall		Xlate (NAT) Source	0		
Product Family	o Access		NAT Rule Number	1		
Туре	Nation		NAT Additional Rule	1		
Traffic		~	Actions			~
Interface	🛓 eth1		Report Log	Report Log to Check Point		
Policy		~	More			~
Action	🕀 Accept		Nat64	enabled		
Policy Management	VK_NAT_MGMT					
Policy Name	Standard					
Policy Date	Today, 10:21:01 AM					


Field in Log	Description
Xlate (NAT) Source IP	Shows the translated source IPv4 address, to which the Security Gateway translated the original source IPv6 address
Xlate (NAT) Destination IP	Shows the translated destination IPv4 address, to which the Security Gateway translated the original destination IPv6 address
More	Identifies the entry as NAT64 traffic (Nat64 enabled)

Advanced NAT Settings

This section describes advanced NAT configuration in specific scenarios.

Automatic and Proxy ARP

Giving a computer on the internal network an IP address from an external network using NAT makes that computer appear on the external network. When NAT on the Security Gateway is configured automatically, the Security Gateway replies on behalf of translated network objects to ARP Requests that are sent from the external network for the IP address of the internal computer.



Item	Description
1	Computer on the internal network with IP address 10.1.1.3
2	Security Gateway with external interface IP address 192.168.0.2 responds to ARP Requests on behalf of translated internal objects
3	Translated IP Address 192.168.0.3 on the external network
4	External network

If you are using manual NAT rules, you must configure Proxy ARP entries to associate the translated IP address with the MAC address of the Security Gateway interface that is on the same network as the translated IP addresses.

See <u>sk30197</u> for more information about configuring:

- Proxy ARP for IPv4 Manual NAT.
- Proxy ARP for Scalable Platforms.

Proxy ARP entries are not generated automatically for CGNAT translated Address Ranges. To resolve this issue, configure the Proxy ARP entries manually. Refer to <u>sk30197</u>.

See <u>sk91905</u> for more about configuring Proxy NDP for IPv6 Manual NAT.

NAT and Anti-Spoofing

NAT is performed after Anti-Spoofing checks, which are performed only on the source IP address of the packet.

This means that spoofing protection is configured on the interfaces of the Security Gateway in the same way as NAT.

Disabling NAT in a VPN Tunnel

When communicating within a VPN, it is normally not necessary to perform NAT.

You can disable NAT in a VPN tunnel with a single click in the VPN community object.

Disabling NAT in a VPN tunnel by defining a NAT rule slows down the performance of the VPN.


Internal Communication with Overlapping Addresses

If two internal networks have overlapping (or partially overlapping) IP addresses, Security Gateway enables:

- Communication between the overlapping internal networks.
- Communication between the overlapping internal networks and the outside world.
- Enforcement of a different security policy for each overlapping internal network.

Example Network Configuration

Example topology:



For example, assume both Network 2A and Network 2B share the same address space (**192.168.1.0/24**).

Therefore, it is not possible to use standard NAT to enable communication between the two networks.

Instead, it is necessary to perform overlapping NAT on a per-interface basis.

- Users in Network 2A, who want to communicate with users in Network 2B, must use the 192.168.30.0/24 network as a destination.
- Users in Network 2B, who want to communicate with users in Network 2A, must use the 192.168.20.0/24 network as a destination.

The Security Gateway (4) translates the IP addresses in this way for each individual interface:

Interface	IP Address Translation on the Interface
4A	 Inbound source IP addresses are translated to the virtual network 192.168.20.0/24. Outbound destination IP addresses are translated to the network 192.168.1.0/24.

Interface	IP Address Translation on the Interface
4B	 Inbound source IP addresses are translated to the network 192.168.30.0/24. Outbound destination IP addresses are translated to the network 192.168.1.0/24.
4C	Overlapping NAT is not configured for this interface. Instead, use NAT Hide in the normal way (not on a per-interface basis) to hide source addresses behind the interface's IP address (192.168.4.1).

Communication Examples

Example 1 - Communication Between Internal Networks

If user 1A, at IP address **192.168.1.10** in Network 2A, wants to connect to user 1B, at IP address **192.168.1.10** (the same IP address) in Network 2B, user 1A opens a connection to the IP address **192.168.30.10**.

Communication Between Internal Networks

Step	Source IP address	Destination IP address
Interface 4A - before NAT	192.168.1.10	192.168.30.10
Interface 4A - after NAT	192.168.20.10	192.168.30.10
Security Gateway enforces the security policy for packets from network 192.168.20.0/24 to network 192.168.30.0/24 .		
Interface 4B - before NAT	192.168.20.10	192.168.30.10
Interface 4B - after NAT	192.168.20.10	192.168.1.10

Example 2 - Communication Between an Internal Network and the Internet

User 1A, at IP address **192.168.1.10** in Network 2A, connects to IP address **192.0.2.10** on the Internet (3).

Communication Between an Internal Network and the Internet

Step	Source IP address	Destination IP address
Interface 4A - before NAT	192.168.1.10	192.0.2.10

Communication Between an Internal Network and the Internet	(continued)	
	(containada)	

Step	Source IP address	Destination IP address
Interface 4A - after NAT	192.168.20.10	192.0.2.10
The Security Gateway (4) enforces the security policy for packets from network 192.168.20.0/24 to the Internet (3).		
Interface 4C - before NAT	192.168.20.10	192.0.2.10
Interface 4C - after NAT Hide	192.168.4.1	192.0.2.10

Routing Considerations

To allow routing from Network 2A to Network 2B (in our example above), you must configure the required routes on the Security Gateway:

Destination Network Address	Default Gateway
192.168.20.0 / 24	192.168.2.2
192.168.30.0 / 24	192.168.3.2

For configuration instructions, see the <u>R82 Gaia Administration Guide</u> > Chapter "Network Management" > Section "IPv4 Static Routes".

Object Database Configuration

To activate the overlapping NAT feature, use <u>Database Tool (GuiDBEdit Tool)</u>, or the dbedit command (see <u>skl3301</u>).

In our example network, the per-interface values for the interface 4A and the interface 4B are:

Parameter	Value
enable_overlapping_nat	true
overlap_nat_dst_ipaddr	The overlapping IP addresses (before NAT). In our example, 192.168.1.0 for both interfaces.
overlap_nat_src_ipaddr	The IP addresses after NAT. In our example:
	 192.168.20.0 for interface 4A. 192.168.30.0 for interface 4B.

Parameter	Value
overlap_nat_netmask	The net mask of the overlapping IP addresses. In our example, 255.255.255.0 .

Multicast Access Control

Multicast IP transmits one copy of each datagram (IP packet) to a multicast address, where each recipient in the group takes their copy. The routers in the network forward the datagrams only to routers and hosts with access to receive the multicast packets.

To configure multicast access control

- 1. Open a Security Gateway object.
- 2. On the Network Management page, select an interface and click Edit.
- 3. On Interface > Advanced, click Drop Multicast packets by the following conditions.
- 4. Select a multicast policy for the interface:
 - Drop multicast packets whose destination is in the list
 - Drop all multicast packets except those whose destination is in the list

When access is denied to a multicast group on an interface for outbound IGMP packets, inbound packets are also denied.

If you do not define access restrictions for multicast packets, multicast datagrams to one interface of the Security Gateway are allowed out of all other interfaces.

5. Click Add.

The Add Object window opens, with the Multicast Address Ranges object selected.

6. Click New > Multicast Address Range.

The Multicast Address Range Properties window opens.

- 7. Enter a name for this range.
- 8. Define an IP address Range or a Single IP Address in the range: 224.0.0.0 239.255.255.255.

Class D IP addresses are reserved for multicast traffic and are allocated dynamically. The multicast address range 224.0.0.0-239.255.255.255 is used only for the destination address of IP multicast traffic.

Every IP datagram whose destination address starts with 1110 is an IP multicast datagram. The remaining 28 bits of the multicast address range identify the group to which the datagram is sent.

The 224.0.0.0-224.0.0.255 range is reserved for LAN applications that are never forwarded by a router. These addresses are permanent host groups. For example: an ICMP request to 224.0.0.1 is answered by all multicast capable hosts on the network, 224.0.0.2 is answered by all routers with multicast interfaces, and 224.0.0.13 is answered by all PIM routers. To learn more, see the http://www.iana.org/assignments/multicast-addresses.

The source address for multicast datagrams is always the unicast source address.

- 9. Click OK.
- 10. In the Add Object window, Click OK.
- 11. In the Interface Properties window, Click OK.
- 12. In the Security Gateway window, Click OK.
- 13. In the Rule Base, add a rule that allows the multicast address range as the **Destination**.
- 14. In the Services of the rule, add the multicast protocols.
 - Multicast routing protocols For example: Protocol-Independent Multicast (PIM), Distance Vector Multicast Routing Protocol (DVMRP), and Multicast Extensions to OSPF (MOSPF).
 - Dynamic registration -Hosts use the Internet Group Management Protocol (IGMP) to let the nearest multicast router know they want to belong to a specified multicast group. Hosts can leave or join the group at any time.
- 15. Install the policy.

Security Management behind NAT


Overview

Explanation

The Security Management Server sometimes uses a private IP address (as listed in <u>RFC</u> <u>1918</u>), or some other non-routable IP address, because of the lack of public IP addresses.

NAT (Static or Hide) for the Security Management Server IP address can be configured in one click, while still allowing connectivity with managed Security Gateways. All Security Gateways can be controlled from the Security Management Server, and logs can be sent to the Security Management Server. NAT can also be configured for a Management High Availability server and a Log Server.

Example:



Item	Description
1	Primary Security Management Server.
	 Original IP address - 10.0.0.1 Translated IP address - 192.168.55.1
2	Local Security Gateway that is directly connected to the Security Management Server. The Remote Security Gateway connects to the Security Management Server through this Local Security Gateway.
3	Remote Security Gateway that must connect to the Security Management Server.

Configuring NAT for Control Connections on the Security Management Server

- 1. From the left navigation panel, click Gateways & Servers.
- 2. Double-click the Security Management Server object.

- 3. From the left navigation tree, click NAT.
- 4. Select Add Automatic Address Translation rules.
- 5. In the Translation method field, select Static.
- 6. Configure the applicable IP address.

In our example - 192.168.55.1

Note - In a High Availability environment, you must configure one static IP address for each Security Management Server.

- 7. Select one of these two options:
 - Install on Gateway The Security Gateway that performs this NAT. In our example, the local Security Gateway that is directly connected to the Security Management Server (item 2 in the diagram).
 - Do not create automatic NAT rules The Security Management Server is behind a non-Check Point device that handles the NAT.
- 8. Connections from Security Gateways to this server. Select one of these options:
 - Based on topology configuration (use the server's translated or original IP address).
 - Use this server's original IP address.
 - Use this server's translated IP address.
- Optional: Select Apply for Security Gateway control connections This option performs NAT on VPN control connections to and from the Security Management Server. This makes it possible to install a policy or collect logs across a NAT gateway.
- 10. Click OK.
- 11. Install the Access Control Policy on the applicable Security Gateways.

Configuration on the Security Gateway

For each Security Gateway, you can decide whether to use the definitions on the Management Server / Log Server or to override the settings of the Management Server / Log Serverand configure other settings for the specific Security Gateway.

To configure management behind NAT settings for a specific Security Gateway:

- 1. In SmartConsole, go to the Gateways & Servers view, and double-click the relevant Security Gateway object.
- In the Security Gateway object editor, from the left navigation menu, select NAT > Management / Log Servers.

- 3. The default option is Use Management Server / Log Server settings.
- 4. To override the default settings, select one of these options:
 - Use the remote server's original /translated IP address based on the topology
 - Use only the original IP address for the remote servers.
 - Use only the translated IP address for the remote servers.

Notes:

- Security Management Server behind NAT is not supported on a Standalone server (where the Security Management Server also acts as a Security Gateway) that receives connections from outside the NATed domain (for example, when it receives SAM commands).
- The procedure and instructions in this section apply to a Log Server behind NAT as well.

IP Pool NAT

Overview

An IP Pool is a range of IP addresses that are routable to the Security Gateway.

IP Pool NAT ensures proper routing for encrypted connections in these VPN connection scenarios:

- Remote Access Client to MEP (Multiple Entry Point) Security Gateways
- Security Gateway to MEP Security Gateways

When a connection is opened from a Remote Access Client or a client behind a Security Gateway, to a server behind the MEP Security Gateways, the packets are routed through one of the MEP Security Gateways.

Return packets in the connection must be routed back through the same Security Gateway in order to maintain the connection.

To ensure that this occurs, each of the MEP Security Gateways maintains a pool of IP addresses that are routable to the Security Gateway.

When a connection is opened to a server, the Security Gateway substitutes an IP address from the IP pool for the source IP address.

Reply packets from the server return to the Security Gateway, which restores the original source IP address and forwards the packets to the source.

NAT Priorities

IP Pool NAT can be used both for encrypted (VPN) and non-encrypted (decrypted by the Security Gateway) connections.

Note - To enable IP Pool NAT for clear connections through the Security Gateway, it is necessary to configure the required INSPECT settings in the applicable user.def file (see "Location of 'user.def' Files on the Management Server" on page 257). Contact <u>Check Point Support</u> for assistance.

For non-encrypted connections, IP Pool NAT has the following advantages over Hide NAT:

- New back connections (for example, X11) can be opened to the NATed host.
- User-to-IP server mapping of protocols that allow one connection per IP can work with a number of hosts instead of only one host.
- IPsec, GRE, and IGMP protocols can be NATed using IP Pool NAT (and Static NAT). Hide NAT works only with TCP, UDP, and ICMP protocols.

Because of these advantages, you can specify that IP Pool NAT has priority over Hide NAT, if both match the same connection. Hide NAT is only applied if the IP pool is used up.

The order of NAT priorities:

- 1. Static NAT
- 2. IP Pool NAT
- 3. Hide NAT

Because Static NAT has all of the advantages of IP Pool NAT and more, it has a higher priority than the other NAT methods.

IP Pool per Interface


You can define a separate IP address pool on one or more of the Security Gateway interfaces instead of defining a single pool of IP addresses for the Security Gateway.

Defining an IP pool per interface solves routing issues that occur when the Security Gateway has more than two interfaces.

Sometimes it is necessary that reply packets return to the Security Gateway through the same Security Gateway interface.

Example:

This example diagram shows one of the MEP Security Gateways in a Remote Access Client to a MEP Security Gateway deployment:



Item	Description
1	Packets from source host: Source: Original Destination:
2	VPN tunnel through the Internet
3	MEP Security Gateway
3A	IP Pool 1 packets: Source: 10.55.8.x Destination:
3B	IP Pool 2 packets: Source: 10.55.10.x Destination:
4	Internal network 10.8.8.0
5	Target host in internal network 10.10.10.0

If a remote client opens a connection to the internal network, reply packets from hosts inside the internal networks are routed to the correct Security Gateway interface through the use of static IP pool NAT addresses.

The remote client's IP address is NATed to an address in the IP pool on one of the Security Gateway interfaces. The addresses in the IP pool can be routed only through that Security Gateway interface so that all reply packets from the target host are returned only to that interface. Therefore, it is important that the IP NAT pools of the interfaces do **not** overlap.

When the packet returns to the Security Gateway interface, the Security Gateway restores the remote peer's source IP address.


The routing tables on the routers that lie behind the Security Gateway must be edited so that addresses from a Security Gateway IP pool are returned to the correct Security Gateway interface.

Switching between IP Pool NAT per Security Gateway and IP Pool NAT per interface and then installing the security policy deletes all IP Pool allocation and all NATed connections.

Reusing IP Pool Addresses for Different Destinations


IP Pool addresses can be reused for different destinations, which makes more efficient use of the addresses in the pool. If a pool contains N addresses, then any number of clients can be assigned an IP from the pool as long as there are no more than N clients per server.

Using IP Pool allocation per destination, two different clients can receive the same IP from the pool as long as they communicate with different servers (connections 1 and 2). When reusing addresses from the IP Pool, back connections are supported from the original server only (connection 3). This means that connections back to the client can be opened only from the specific server to which the connection was opened.



ltem	Description
1	Security Gateway with IP Pool addresses A to Z
2	Clients. Source: Original Destination:
3A	NATed packet from connection 3. Source: A Destination:
4A	NATed packet from connection 4. Source: A Destination:
5A	NATed packet from reply connection 5. Source: Original Destination: A
6A	This server cannot open a connection with Destination A back to the client.

The default **Do not reuse IP Pool NAT** behavior means that each IP address in the IP Pool is used once (connections 1 and 2 in the following illustration). In this mode, if an IP pool contains 20 addresses, up to 20 different clients can be NATed and back connections can be opened from any source to the client (connection 3).



ltem	Description
1	Security Gateway with IP Pool addresses A to Z.
2	Clients. Source: Original Destination:
3A	NATed packet from connection 3. Source: A Destination:
4A	NATed packet from connection 4. Source: Z Destination:
5	Connection. Source: Original Destination: A

Switching between the **Reuse** and **Do not reuse** modes and then installing the security policy, deletes all IP Pool allocations and all NATed connections.

IP Pool Configuration Procedure

- 1. Enable IP Pool NAT in Global Properties
 - a. From the SmartConsole Menu, click Global properties.
 - b. In the **Global properties** > **NAT** page, select **Enable IP Pool NAT** and the required tracking options.
 - c. Click OK.

2. For each Security Gateway or Security Gateway interface, create an object that represents its IP pool NAT addresses

This object can be a Network, Network Group, or Address Range.

- Important:
 - In a Cluster, you must configure separate IP Pool for each Cluster Member.
 - It is not possible to configure a separate IP Pool for each Cluster Member interface.

For example, for an Address Range, do the following:

- a. From the Objects Bar (F11), In the network objects tree, select New > More > Network Object > Address Range > Address Range.
- b. In the General tab, enter the first and last IP addresses of the range.
- c. Click OK.

3. Enable and configure IP Pool NAT in the Security Gateway object

- a. From the left navigation panel, click Gateways & Servers.
- b. Double-click the Security Gateway / Cluster object.
- c. From the left, expand NAT and click IP Pool NAT.
- d. In the IP Pool NAT page, select one of these options:

In a Security Gateway object:

- Allocate IP Addresses from and then select the address range you created to configure IP Pool NAT for the whole Security Gateway.
- Define IP Pool NAT on Gateway interfaces to configure IP Pool NAT per interface.

In a Cluster object:

- Define IP Pool NAT on each cluster member
- Define IP Pool NAT on cluster member interfaces to configure IP Pool NAT per interface.

- e. Optional: Select one or more of these options:
 - Use IP Pool NAT for VPN client connections
 - Use IP Pool NAT for gateway to gateway connections
 - Prefer IP Pool NAT over Hide NAT to specify that IP Pool NAT has priority over Hide NAT, if both match the same connection. Hide NAT is only applied if the IP pool was used up.
- f. Optional: Configure the applicable advanced settings.

Click Advanced and configure:

i. Return unused addresses to IP Pool after

Addresses in the pool are reserved for 60 minutes (default), even if the user logs off. If the user disconnects from their ISP and then redials and reconnects, there will be two Pool NAT addresses in use for the user until the first address from the IP Pool times out. If users regularly lose their ISP connections, you may want to decrease the time-out to prevent the IP Pool from being depleted.

ii. Reuse IP addresses from the pool for different destinations

This is a good option unless it is necessary to allow back connections to be opened to clients from any source, rather than just from the specific server to which the client originally opened the connection.

- g. Click OK to close the Advanced IP Pool NAT Configuration window.
- h. In a cluster object:
 - i. From the left, click Cluster Members.
 - ii. Double-click each Cluster Member.
 - iii. From the top, click the IP Pool NAT tab.
 - iv. Select Use IP Pool NAT.
 - v. In the Allocate IP addresses from field, select the applicable object for this Cluster Member.
 - Important In a Cluster, you must configure separate IP Pool for each Cluster Member. It is not possible to configure a separate IP Pool for each Cluster Member interface.
 - vi. Click **OK** to close the Cluster Member Properties window.
- i. Click **OK** to close the Security Gateway / Cluster object.
- 4. Install the Security Policy

- a. Connect with the SmartConsole to the Security Management Server.
- b. Install the Access Control Policy on the remote Security Gateway / Cluster.

5. Edit the routing table of each internal router

Configure the applicable routes so that packets with an IP address assigned from the NAT pool are routed to the appropriate Security Gateway or, if using IP Pools per interface, the appropriate Security Gateway interface.

Mobile Access to the Network

Check Point Mobile Access lets remote users easily and securely use the Internet to connect to internal networks. Remote users start a standard HTTPS request to the Mobile Access Security Gateway, and authenticate with one or more secure authentication methods.

The Mobile Access Portal lets mobile and remote workers connect easily and securely to critical resources over the internet. Check Point Mobile Apps enable secure encrypted communication from unmanaged smartphones and tablets to your corporate resources. Access can include internal apps, email, calendar, and contacts.

To include access to Mobile Access applications in the Rule Base, include the **Mobile Application** in the **Services & Applications** column.

To give access to resources through specified remote access clients, create Access Roles for the clients and include them in the **Source** column of a rule.

Check Point Mobile Access Solutions

Check Point Mobile Access has a range of flexible clients and features that let users access internal resources from remote locations. All these solutions include these features:

- Enterprise-grade, secure connectivity to corporate resources
- Strong user authentication
- Granular access control

For more information about the newest versions of Mobile Access solutions and clients, go to sk67820.

Client-Based vs. Clientless

Check Point remote access solutions use IPsec and SSL encryption protocols to create secure connections. All Check Point clients can work through NAT devices, hotspots, and proxies in situations with complex topologies, such as airports or hotels. These are the types of installations for remote access solutions:

- Client-based Client application installed on endpoint computers and devices. The client supplies access to most types of corporate resources according to the access privileges of the user.
- Clientless Users connect through a web browser and use HTTPS connections. Clientless solutions usually supply access to web-based corporate resources.
- On demand client Users connect through a web browser and a client is installed when necessary. The client supplies access to most types of corporate resources according to the access privileges of the user.

Mobile Access Clients

- Capsule Workspace An app that creates a secure container on the mobile device to give users access to internal websites, file shares, and Exchange servers.
- Capsule Connect A full L3 tunnel app that gives users network access to all mobile applications.
- Check Point Mobile for Windows A Windows IPsec VPN client that supplies secure IPsec VPN connectivity and authentication.

Mobile Access Web Portal

The Mobile Access Portal is a clientless SSL VPN solution that supplies secure access to webbased resources. After users authenticate to the portal, they can access Mobile Access applications such as Outlook Web App and a corporate wiki.

SSL Network Extender

SSL Network Extender is an on-demand SSL VPN client and is installed on the computer or mobile device from an Internet browser. It supplies secure access to internal network resources.

Configuring Mobile Access to Network Resources

Sample Mobile Access Workflow

This is a high-level workflow to configure remote access to Mobile Access applications and resources.

- 1. Use SmartConsole to enable the Mobile Access Software Blade on the Security Gateway.
- 2. Follow the steps in the Mobile Access Configuration wizard to configure these settings:
 - a. Select mobile clients.
 - b. Define the Mobile Access Portal.
 - c. Define applications, for example Outlook Web App.
 - d. Connect to the AD server for user information.
- 3. Select the policy type:
 - The default is to use the Legacy Policy, configured in the Mobile Access tab in SmartConsole.
 - To include Mobile Access in the Unified Access Control Policy, select this in Gateway Properties > Mobile Access.
- 4. Add rules to the Policy:
 - For Legacy Policy: Add rules in SmartConsole. Select Security Policies > Shared Policies > Mobile Access > Open Mobile Access Policy in SmartConsole
 - For Unified Access Control Policy: Add rules in SmartConsole > Security Policies Access Control Policy.
- 5. Configure the authentication settings in **Gateway Properties > Mobile Access > Authentication**.
- 6. Install the Access Control Policy on the Security Gateway.

Users can access mobile applications through the configured Mobile Access Portal with the defined authentication method.


- 7. Optional: Give secure access to users through the Capsule Workspace app with certificate authentication.
 - a. In the Security Gateway object > Mobile Access > Authentication, click Settings, and select Require client certificate.

- b. Use the Certificate Creation and Distribution Wizard (in the Security Policies view > Client Certificates > New).
- c. Users download the Capsule Workspace app.
- d. Users open the Capsule Workspace app and enter the Mobile Access Site Name and necessary authentication, such as user name and password.

Enable Mobile Access	-	Configure settings in Mobile Access wizard		Update the Authentication settings		
						¥
Users can access internal resources	+	Users download app, open it, and enter settings	•	Generate a certificate for the clients	ł	Install the Access Control Policy

Sample Mobile Access Deployment

This is a sample deployment of a Mobile Access Security Gateway with an AD and Exchange server in the internal network.



ltem	Description
1	Mobile devices
2	Mobile Access tunnels
3	Internet (external networks)
4	Mobile Access Security Gateway

ltem	Description
5	Internal network resources, AD and Exchange servers

In this sample Mobile Access deployment, a mobile device uses a Mobile Access tunnel to connect to the internal network. The Mobile Access Security Gateway decrypts the packets and authenticates the user. The connection is allowed and the mobile device connects to the internal network resources.

Using the Mobile Access Configuration Wizard

This procedure describes how to enable and configure the Mobile Access Software Blade on a Security Gateway with the Configuration wizard. For this sample configuration, the AD user group Mobile Access contains all the users that are allowed to connect to the internal network. The deployment is based on the Sample Mobile Access Deployment.

This configuration lets these clients connect to internal resources:

- Android and iOS mobile devices
- Windows and Mac computers
- Internet browsers can open a SSL Network Extender connection to the internal network

To configure Mobile Access:

1. In SmartConsole, go to Gateways & Servers and double-click the Security Gateway object.

The General Properties window opens.

2. In the General Properties > Network Security section, select Mobile Access.

The Mobile Access page of the Mobile Access Configuration Wizard opens.

- 3. Configure the Security Gateway to allow connections from the Internet and mobile devices. Select these options:
 - Web
 - Mobile Devices Select the required options.
 - **Desktops/Laptops** -Select the required options.
- 4. Click Next.

The Web Portal page opens.

5. Enter the primary URL for the Mobile Access Portal.

The default is: https://<IPv4 Address of Security Gateway>/sslvpn

6. Click Next.

The Applications page opens.

- 7. Configure the applications to show:
 - a. In **Web Applications**, make sure **Demo web application (World Clock)** is selected.
 - b. In Mail/Calendar/Contacts, enter the domain for the Exchange server and select:
 - Mobile Mail (including push mail notifications)
 - ActiveSync Applications
 - Outlook Web App

The Mobile Access Portal shows links to the Demo web and Outlook Web App applications. The client on the mobile device shows links to the other applications.

8. Click Next.

The Active Directory page opens.

- 9. Select the AD domain and enter the user name and password.
- 10. Click Connect.

The Security Gateway makes sure that it can connect to the AD server.

11. Click Next.

The Users page opens.

Click Add and then select the group Mobile Access.

12. Click **Next** and then click **Finish**.

The Mobile Access Configuration Wizard closes.

13. Click **OK**.

The Gateway Properties window closes.

Allowing Mobile Connections

The Mobile Access Configuration Wizard enables and configures the Mobile Access Software Blade. It is necessary to add Firewall rules to allow connections from the VPN clients on the computers and devices. Create a Host Node object for the Exchange server, all of the other objects are predefined.

Name	Source	Destinatio n	VPN	Service	Action	Install On	Track
Mobile Access Users	Any	ExchngSr vr	RemoteAcce ss	HTTP HTTPS MSExchan ge	Accept	Mobile Access GW	Log

All connections from the RemoteAccess VPN community to the Exchange server are allowed. These are the only protocols that are allowed: HTTP, HTTPS, and MS Exchange. This rule is installed on Security Gateway in the MobileAccessGW group.

Defining Access to Applications

Use the **Security Policies** page in SmartConsole to define rules that let users access Mobile Access applications. The applications that are selected in the Configuration Wizard are automatically added to this page. You can also create and edit the rules that include these SmartConsole objects:

- Users and user groups
- Mobile Access applications
- Mobile Access Security Gateways

Activating Single Sign-On

Enable the SSO (Single Sign-On) feature to let users authenticate one time for applications that they use during Mobile Access sessions. The credentials that users enter to log in to the Mobile Access Portal can be re-used automatically to authenticate to different Mobile Access applications. SSO user credentials are securely stored on the Mobile Access Security Gateway for that session and are used again if users log in from different remote devices. After the session is completed, the credentials are stored in a database file.

By default, SSO is enabled on new Mobile Access applications that use HTTP. Most Web applications authenticate users with specified Web forms. You can configure SSO for an application to use the authentication credentials from the Mobile Access Portal. It is not necessary for users to log in again to each application.

To configure SSO

- 1. In SmartConsole, go to Security Policies > Shared Policies > Mobile Access.
- 2. Click Open Mobile Access Policy in SmartDashboard.
- 3. In the **Mobile Access** tab, select **Additional Settings > Single Sign-On**.

The Single Sign-On page opens.

4. Select an application and click Edit.

The application properties window opens and shows the Single Sign On page.

For Web form applications

- In the Application Single Sign-On Method section, select Advanced and click Edit. The Advanced window opens.
- 2. Select This application reuses the portal credentials. Users are not prompted.
- 3. Click OK.
- 4. Select This application uses a Web form to accept credentials from users.
- 5. Click OK.
- 6. Install the policy.

Connecting to a Citrix Server


Citrix Services

The Mobile Access Software Blade integrates the Citrix clients and services. It is not necessary to use STA (Secure Ticketing Authority) servers in a Mobile Access Security Gateways deployment because Mobile Access uses its own STA engine. You can also use Mobile Access in a deployment with STA and CSG (Citrix Secure Gateway) servers.

The Mobile Access server certificate must use a FQDN (Fully Qualified Domain Name) that is issued to the FQDN of the Mobile Access Security Gateway.

Sample Deployment with Citrix Server

This is a sample deployment of a Mobile Access Security Gateway and a Citrix web server in the DMZ. The Citrix XenApp server is connected to the internal network.



ltem	Description
1	Mobile devices
2	Mobile Access tunnels
3	Internet (external networks)
4	Security Gateway for the internal network
5	Mobile Access Security Gateway in the DMZ
6	Citrix web interface
7	Internal network resources
8	Citrix XenApp (MetaFrame) server

Configuring Citrix Services for Mobile Access

This procedure describes how to configure Mobile Access to let remote users connect to Citrix applications. The deployment is based on the Sample Deployment with Citrix Server (see *"Sample Deployment with Citrix Server" on the previous page*).

To configure Citrix services:

- 1. In SmartConsole, go to Manage & Settings > Blades.
- 2. In the Mobile Access, click Configure in SmartDashboard.
- 3. In the Mobile Access tab, click Applications > Citrix Services.
- 4. Click New.

The General Properties page of the Citrix Service window opens.

- 5. Enter the Name for the Citrix server object.
- 6. From the navigation tree, click **Web Interface**.
- Create a new object for the Citrix web interface server, in Servers, click Manage > New > Host.

The Host Node window opens.

- 8. Enter the settings for the Citrix web interface server.
- 9. Click OK.
- 10. In Services, select one or more of these services that the Citrix web interface server supports:
 - HTTP
 - HTTPS
- 11. From the navigation tree, click Link in Portal.
- 12. Configure the settings for the link to the Citrix services in the Mobile Access Portal:
 - Link text The text that is shown for the Citrix link
 - URL The URL for the directory or sub-directory of the Citrix application
 - Tooltip Text that is shown when the user pauses the mouse pointer above the Citrix link
- 13. From the navigation tree, select Additional Settings > Single Sign On.
- 14. Enable Single Sign On for Citrix services, select these options:

- Turn on single Sign On for this application
- Prompt users for their credentials, and store them for future use
- 15. Click **OK**.

The Citrix server object is added to **Defined Citrix Services**.

- 16. From the Mobile Access navigation tree, select **Policy**.
- 17. Add the Citrix services object to the applicable rules.
 - a. Right-click on the Applications cell of a rule and select Add Applications.
 - b. Select the Citrix services object.
- 18. Install the policy.

Compliance Check

The Mobile Access Software Blade lets you use the Endpoint Security on Demand feature to create compliance policies and add more security to the network. Mobile devices and computers are scanned one time to make sure that they are compliant before they can connect to the network.

The compliance scanner is installed on mobile devices and computers with ActiveX (for Internet Explorer on Windows) or Java. The scan starts when the Internet browser tries to open the Mobile Access Portal.

Compliance Policy Rules

The compliance policy is composed of different types of rules. You can configure the security and compliance settings for each rule or use the default settings.

These are the rules for a compliance policy:

- Windows security Microsoft Windows hotfixes, patches and Service Packs.
- Anti-Spyware protection Anti-Spyware software.
- Anti-Virus protection Anti-Virus software version and virus signature files.
- Firewall Personal Firewall software.
- Spyware scan Action that is done for different types of spyware.
- Custom Compliance rules for your organization, for example: applications, files, and registry keys.
- OR group A group of the above rules. An endpoint computer is compliant if it meets one of the rules in the group.

Creating a Compliance Policy

By default, Endpoint Security on Demand only allows endpoint computers that are compliant with the compliance policy log in to the Mobile Access Portal.

To create a compliance policy:

- 1. In SmartConsole, go to Manage & Settings > Blades.
- 2. In the Mobile Access section, click Configure in SmartDashboard.
- 3. On the **Mobile Access** tab, select **Endpoint Security on Demand > Endpoint Compliance**.
- 4. Click Edit policies.

The Policies window opens.

5. Click New Policy.

The **Policies** > **New Policy** window opens.

- 6. Enter the Name and Description for the policy.
- 7. Click Add.

The Add Enforcement Rules window opens.

8. Select rules for the policy.

You can also create new rules - click New Rule, and configure the rule settings.

9. Click OK.

The **Policies** > **New Policy** window shows the rules for the policy.

10. Select Bypass spyware scan if necessary.

When selected, the scan for endpoint computers that are compliant with the Anti-Virus or Anti-Spyware settings is changed. These computers do not scan for spyware when they connect to a Mobile Access Security Gateway.

11. Click OK.

The Policies window opens.

12. Click **OK**.

Configuring Compliance Settings for a Security Gateway

The Firewall on a Mobile Access Security Gateway only allows access to endpoint computers that are compliant with the compliance policy.

This procedure shows how to configure the Laptop Computer policy for a Security Gateway (see "*Compliance Policy Rules*" on the previous page).

To configure the compliance settings:

- 1. In SmartConsole, go to Manage & Settings > Blades.
- 2. In the Mobile Access section, click Configure in SmartDashboard.
- 3. In the **Mobile Access** tab, select **Endpoint Security on Demand > Endpoint Compliance**.
- 4. Select the Security and click Edit.

The **Endpoint Compliance** page of the Security Gateway properties window opens.

- 5. Select Scan endpoint machine when user connects.
- 6. Select Threshold policy and from the drop-down menu select Laptop Computer.

- 7. Click OK.
- 8. Install the policy on the Mobile Access Security Gateway.

Secure Workspace

Secure Workspace is a security solution that allows remote users to connect to enterprise network resources safely and securely. The Secure Workspace virtual workspace provides a secure environment on endpoint computers that is segregated from the "real" workspace. Users can only send data from this secure environment through the Mobile Access Portal. Secure Workspace users can only access permitted applications, files, and other resources from the virtual workspace.

Secure Workspace creates an encrypted folder on the computer called **My Secured Documents** and can be accessed from the virtual desktop. This folder contains temporary user files. When the session terminates, Secure Workspace deletes this folder and all other session data.

For more about configuring Secure Workspace and Mobile Access VPN, see the <u>R82 Mobile</u> <u>Access Administration Guide</u>.

To enable Secure Workspace on a Mobile Access Security Gateway

- 1. In SmartConsole, go to Manage & Settings > Blades.
- 2. In the Mobile Access section, click Configure in SmartDashboard.

Legacy SmartDashboard opens.

- 3. In the Mobile Access tab, click Endpoint Security on Demand > Secure Workspace.
- 4. Select the Security Gateway and click Edit.

The **Check Point Secure Workspace** page of the Security Gateway properties window opens.

- 5. Select This gateway supports access to applications from within Check Point Secure Workspace.
- 6. Click OK.
- 7. Install the policy.

Secure Workspace

Secure Workspace is a security solution that allows remote users to connect to enterprise network resources safely and securely. The Secure Workspace virtual workspace provides a secure environment on endpoint computers that is segregated from the "real" workspace. Users can only send data from this secure environment through the Mobile Access Portal. Secure Workspace users can only access permitted applications, files, and other resources from the virtual workspace.

Secure Workspace creates an encrypted folder on the computer called **My Secured Documents** and can be accessed from the virtual desktop. This folder contains temporary user files. When the session terminates, Secure Workspace deletes this folder and all other session data.

For more about configuring Secure Workspace and Mobile Access VPN, see the <u>R82 Mobile</u> <u>Access Administration Guide</u>.

To enable Secure Workspace on a Mobile Access Security Gateway

- 1. In SmartConsole, go to Manage & Settings > Blades.
- 2. In the Mobile Access section, click Configure in SmartDashboard.

Legacy SmartDashboard opens.

- 3. In the **Mobile Access** tab, click **Endpoint Security on Demand > Secure Workspace**.
- 4. Select the Security Gateway and click Edit.

The **Check Point Secure Workspace** page of the Security Gateway properties window opens.

- 5. Select This gateway supports access to applications from within Check Point Secure Workspace.
- 6. Click **OK** and then install the policy.

To Learn More About Mobile Access

To learn more about Mobile Access VPN, see the <u>R82 Mobile Access Administration Guide</u>.

Site-to-Site VPN


The basis of Site-to-Site VPN is the encrypted VPN tunnel. Two Security Gateways negotiate a link and create a VPN tunnel and each tunnel can contain more than one VPN connection. One Security Gateway can maintain more than one VPN tunnel at the same time.

Sample Site-to-Site VPN Deployment

Item	Description
A, B	Security Gateways
2	VPN tunnel
3	Internal network in VPN domain
4	Host 4
5	Host 5

In this sample VPN deployment, Host 4 and Host 5 securely send data to each other. The Security Gateways perform IKE negotiation and create a VPN tunnel. They use the IPsec protocol to encrypt and decrypt data that is sent between Host 4 and Host 5.

VPN Workflow



VPN Communities

A VPN Domain is a collection of internal networks that use Security Gateways to send and receive VPN traffic. Define the resources that are included in the VPN Domain for each Security Gateway. Then join the Security Gateways into a VPN community - collection of VPN tunnels and their attributes. Network resources of different VPN Domains can securely communicate with each other through VPN tunnels that terminate at the Security Gateways in the VPN communities.

VPN communities are based on Star and Mesh topologies. In a Mesh community, there are VPN tunnels between each pair of Security Gateway. In a Star community, each satellite Security Gateway has a VPN tunnel to the central Security Gateway, but not to other Security Gateways in the community.

Mesh Topology	Star Topology

Item	Description
1	Security Gateway
2	Satellite Security Gateways
3	Central Security Gateway

Sample Star Deployment

This section explains how to configure a VPN star community. This deployment lets the satellite Security Gateways connect to the internal network of the central Security Gateway. The internal network object is named: **Internal-network**.

To create a new VPN Star Community:

- 1. In SmartConsole, go to the **Security Policies** page.
- 2. In the Access Tools section, click VPN Communities.
- 3. Click New and select Star Community.

The New Star Community window opens.

- 4. Enter the name for the community.
- 5. From the navigation tree, select **Encryption**.
- 6. Configure the VPN encryption methods and algorithms for the VPN community.
- 7. Click OK.

To configure star VPN for the Security Gateways

For each Security Gateway in the VPN community, follow these configuration steps.

1. In SmartConsole, go to the **Gateways & Servers** page and double-click the Security Gateway object.

The Security Gateway properties window opens.

- 2. In the Network Security section of the General Properties page, select IPsec VPN.
- 3. From the navigation tree, go to **Network Management > VPN Domain**.
 - For the central Security Gateway, click Manually defined and select the Internal-network object
 - For a satellite Security Gateway, select **All IP addresses**
- 4. From the navigation tree, click **IPsec VPN**.
- 5. Configure the Security Gateway as a member of a VPN star community.
 - a. In the **This Security Gateway participates in the following VPN Communities** section, click **Add**.

The Add this Gateway to Community window opens.

- b. Select the VPN Community.
- c. Click OK.
- 6. Click OK.

After you create a community and configure Security Gateways, add those Security Gateways to the community as a center or as a satellite Security Gateway.


To add a Security Gateway to a new star community

- 1. In SmartConsole, go to the **Security Policies** page.
- 2. In the Access Tools section, click VPN Communities.
- 3. Select the new star community and click Edit.

The Star Community window opens.

- 4. In the Gateways page, add Security Gateways to the community:
 - Center Gateways Click Add and select center Security Gateways. Select Mesh center gateways, if necessary.
 - Satellite Gateways Click Add and select satellite Security Gateways.
- 5. Click OK.

Sample Combination VPN Community



ltem	Description
1	London Security Gateway
2	New York Security Gateway
3	London - New York Mesh community
4	London company partner (external network)
5	London Star community
6	New York company partner (external network)
7	New York Star community

This deployment is composed of a Mesh community for London and New York Security Gateways that share internal networks. The Security Gateways for external networks of company partners do not have access to the London and New York internal networks. However, the Star VPN communities let the company partners access the internal networks of the sites that they work with.

Allowing VPN Connections

To allow VPN connections between Security Gateways in specific VPN communities, add Access Control rules that accept such connections.

To allow all VPN traffic to hosts and clients on the internal networks of a specific VPN community, select these options in the **Encrypted Traffic** section of the properties configuration window for that VPN Community:

- For a meshed community: Accept all encrypted traffic
- For a Star Community: Accept all encrypted traffic on Both center and satellite gateways, or Accept all encrypted traffic on Satellite gateways only.

Sample VPN Access Control Rules

This table shows sample VPN rules for an Access Control Rule Base. (The Action, Track and Time columns are not shown. Action is set to Allow, Track is set to Log, and Time is set to Any.)

No.	Name	Source	Destination	VPN	Service	Install On
1	-	Any	NEGATED Member Security Gateways	BranchOffices LondonOffices	Any	BranchOffices LondonOffices
2	Site-to- site VPN	Any	Any	All_GwToGw	FTP-port HTTP HTTPS SMTP	Policy Targets
3	Remote access	Any	Any	RemoteAccess	HTTP HTTPS IMAP	Policy Targets

1. Automatic rule that SmartConsole adds to the top of the *Implied Rules* when the Accept All Encrypted Traffic configuration option is selected for the BranchOffices VPN community and the LondonOffices VPN community. This rule is installed on all the Security Gateways in these communities. It allows all VPN traffic to hosts and clients on the internal networks of these communities. Traffic that is sent to the Security Gateways in these VPN communities.

Note - This automatic rule can apply to more than one VPN community.

- 2. **Site-to-site VPN** Connections between hosts in the VPN Domains of all Site-to-Site VPN communities are allowed. These are the only protocols that are allowed: FTP, HTTP, HTTPS and SMTP.
- 3. **Remote access** Connections between hosts in the VPN Domains of Remote Access VPN community are allowed. These are the only protocols that are allowed: HTTP, HTTPS, and IMAP.

To Learn More About Site-to-Site VPN

To learn more about site-to-Site VPN, see the <u>R82 Site to Site VPN Administration Guide</u>.

Remote Access VPN

If employees remotely access sensitive information from different locations and devices, system administrators must make sure that this access does not become a security vulnerability. Check Point's Remote Access VPN solutions let you create a VPN tunnel between a remote user and the internal network. The Mobile Access Software Blade extends the functionality of Remote Access solutions to include many clients and deployments.

VPN Connectivity Modes

When securely connecting remote clients with the internal resources, organizations face connectivity challenges, such as these:

- The IP addresses of a remote access client might be unknown
- The remote access client can be connected to a LAN with internal IP addresses (such as, at hotels)
- It is necessary for the remote client to use protocols that are not supported

The Check Point IPsec VPN Software Blade provides these VPN connectivity modes to help organizations resolve those challenges:

Office Mode

Remote users can be assigned the same or non-routable IP addresses from the local ISP. Office Mode solves these routing problems and encapsulates the IP packets with an available IP address from the internal network. Remote users can send traffic as if they are in the office and avoid VPN routing problems.

Visitor Mode

Remote users can be restricted to using only HTTP and HTTPS protocols. Visitor Mode lets these users tunnel all protocols through regular TCP connections on port 443.

Sample Remote Access VPN Workflow


Here is an example of a Remote Access VPN workflow:

- 1. Use SmartConsole to enable Remote Access VPN on the Security Gateway.
- 2. Add the remote user information to the Security Management Server:
 - Create and configure an LDAP Account Unit
 - Enter the information in the SmartConsole user database

Optional: Configure the Security Gateway for remote user authentication.

- 3. Define the Access Control and encryption rules for the Security Gateway.
- 4. Create the group objects to use in the Security Gateway rules:

- LDAP Group object for an LDAP Account Unit
- User Group object for users configured in the SmartConsole user database
- 5. Create and configure the encryption settings for the VPN community object in **Menu** > **Global properties** > **Remote Access** > **VPN - Authentication and Encryption**.
- 6. Add Access Control rules to the Access Control Rule Base to allow VPN traffic to the internal networks.



Configuring the Security Gateway for a Remote Access Community

Make sure that the VPN Software Blade is enabled before you configure the Remote Access community.

To configure the Security Gateway for Remote Access

1. In SmartConsole, click Gateways & Servers and double-click the Security Gateway.

The Security Gateway object opens and shows the General Properties page.

2. From the navigation tree, click **IPsec VPN**.

The page shows the VPN communities that the Security Gateway is participating.

- 3. To add the Security Gateway to a Remote Access community:
 - a. Click Add.
 - b. Select the community.
 - c. Click OK.
- 4. From the navigation tree, click **Network Management > VPN Domain**.
- 5. Configure the VPN Domain.

To configure the settings for Visitor Mode

- 1. From the navigation tree, click VPN Clients > Office Mode.
- 2. Configure the settings for Office Mode.

Note - Office Mode support is mandatory on the Security Gateway side.

- 3. Click OK.
- 4. Publish the SmartConsole session.

To Learn More About Remote Access VPN

See the <u>R82 Remote Access VPN Administration Guide</u>.

Implied Rules

The Check PointSecurity Management Server and its managed objects (Security Gateways, Cluster Members, Log Servers, and so on) communicate with each other through the Check Point protocols. By default, each Access Control policy contains predefined implied rules that allow the required internal Check Point communication.

To view the implied rules in SmartConsole:

- 1. From the left navigation panel, click **Security Policies**.
- 2. In the top left panel, click Access Control > Policy.
- 3. From the top toolbar, click **Actions > Implied Rules**.

To configure the implied rules in SmartConsole:

- 1. In the top left corner, click **Menu > Global properties**.
- 2. In the **Firewall** page, select the applicable options and configure the order of the implied rules.
- 3. Click OK
- 4. Install the Access Control policy on each managed Security Gateway / Cluster / Virtual System.

For more information, see <u>sk179346</u>.

Creating a New Threat Prevention Policy

To learn about configuring a Threat Prevention Policy, see the <u>*R82 Threat Prevention*</u> <u>*Administration Guide*</u>.

Installing the Threat Prevention Policy

The IPS, Anti-Bot, Anti-Virus, Threat Emulation and Threat Extraction Software Blades have a dedicated Threat Prevention Policy. You can install this policy separately from the policy installation of the Access Control Software Blade. Install only the Threat Prevention Policy to minimize the performance impact on the Security Gateways.

To install the Threat Prevention Policy:

1. From the Global toolbar, click Install Policy.

The Install Policy window opens and shows the installation targets (Security Gateways).

- 2. Select Threat Prevention.
- 3. Select Install Mode:
 - Install on each selected gateway independently Install the policy on the selected Security Gateways without reference to the other targets. A failure to install on one Security Gateway does not affect policy installation on other Security Gateways.

If the Security Gateway is a member of a cluster, install the policy on all the members. The Security Management Server makes sure that it can install the policy on all the members before it installs the policy on one of them. If the policy cannot be installed on one of the members, policy installation fails for all of them.

- Install on all selected gateways, if it fails do not install on gateways of the same version Install the policy on all installation targets. If the policy fails to install on one of the Security Gateways, the policy is not installed on other targets of the same version.
- 4. Click OK.

Analyzing Threats

Networks today are more exposed to cyber threats than ever. This creates a challenge for organizations in understanding the security threats and assessing damage.

SmartConsole helps the security administrator find the cause of cyber threats, and remediate the network.

The **Logs & Events** > **Logs** view presents the threats as logs.

The other views in the **Logs & Events** view combine logs into meaningful security events. For example, malicious activity that occurred on a host in the network in a selected time interval (the last hour, day, week or month). They also show pre- and post-infections statistics.

You can create rich and customizable views and reports for log and event monitoring, which inform key stakeholders about security activities. For each log or event, you can see a lot of useful information from the ThreatWiki and IPS Advisories about the malware, the virus or the attack.

For information, see the:

- *R82 Threat Prevention Administration Guide*.
- *R82 Logging and Monitoring Administration Guide.*

UserCheck in the Access Control Policy

This section describes how to configure and use UserCheck.

When you enable the UserCheck feature, the Security Gateway sends messages to users about possible non-compliant behavior or dangerous Internet browsing, based on the rules an administrator configured in the Security Policy. This helps users prevent security incidents and learn about the organizational security policy. You can develop an effective policy based on logged user responses. Create UserCheck objects and use them in the Rule Base, to communicate with the users.

These Software Blades support the UserCheck feature:

- Data Loss Prevention
- Access Control:
 - Application Control
 - URL Filtering
 - Content Awareness
- Threat Prevention:
 - Anti-Bot
 - Anti-Virus
 - Threat Emulation
 - Threat Extraction
 - Zero Phishing

Getting Started with UserCheck for the Data Loss Prevention Software Blade:

See the <u>R82 Data Loss Prevention Administration Guide</u> > Chapter "UserCheck".

Getting Started with UserCheck for the Application Control, URL Filtering, and Content Awareness Software Blades:

- 1. In SmartConsole, in the Security Gateway / Cluster object:
 - a. Enable the applicable Access Control Software Blades.
 - b. Configure the applicable UserCheck settings.

See "Configuring UserCheck" on page 518.

- c. Optional: Download the UserCheck Client and install it on endpoint computers.
 See the *R82 Quantum Security Gateway Guide* > Chapter "UserCheck Client".
- 2. Optional: In the Global Properties, configure the applicable UserCheck settings.
- 3. Configure the applicable UserCheck Interaction Objects.

See "UserCheck Interaction Objects for Access Control Software Blades" on page 522.

4. Configure the applicable Access Control Policy.

See "Creating an Access Control Policy" on page 327:

In Access Control rules, click in the **Action** column > click the applicable menu **Drop**, **Ask**, or **Inform** > select the required UserCheck Interaction object.

- 5. Install the Access Control Policy on the Security Gateway / Cluster object.
- 6. Additional Configuration:
 - "Localizing and Customizing the UserCheck Portal" on page 530

Configuring UserCheck

Enable or disable UserCheck directly on the Security Gateway. When UserCheck is enabled, the user's Internet browser shows the UserCheck messages in a new window. If users connect to the Security Gateway remotely, set the internal interface of the Security Gateway (on the **Topology** page) to be the same as the **Main URL** for the UserCheck Portal.

To configure UserCheck on a Security Gateway

Step	Instructions
1	From the left navigation panel, click Gateways & Servers.
2	Double-click the Security Gateway / Cluster object.
3	In the left panel, click UserCheck .
4	Select Enable UserCheck for active blades.
5	In the UserCheck Web Portal section, the Main URL field shows the primary URL for the web portal that shows the UserCheck notifications. You can use the suggested Main URL or manually enter a different Main URL .
6	Optional: Click Aliases to add URL aliases that redirect different hostnames to the Main URL. For example: usercheck.mycompany.com The aliases must be resolved to the portal IP address on the corporate DNS server.
7	 In the Certificate section, click Import to import a certificate that the portal uses to authenticate to the Security Management Server. By default, the portal uses a certificate from the Check Point Internal Certificate Authority (ICA). This might generate warnings if the user browser does not recognize Check Point as a trusted Certificate Authority. To prevent these warnings, import your own certificate from a recognized external authority. Note - After you download your certificate, you can click Replace to replace it with a different certificate, and click View to see the certificate information.

Step	Instructions
8	In the Accessibility section, click Edit to configure interfaces on the Security Gateway through which the portal can be accessed. These options are based on the topology configured in the Security Gateway object. You must configure the topology settings on the Network Manegment page. Select the applicable option when the Security Gateway must send users to the UserCheck Portal based on how they connect:
	 Through all interfaces Through internal interfaces (default) Including undefined internal interfaces Including DMZ internal interfaces Including VPN encrypted interfaces (default) Applies to interfaces used for establishing route-based VPN tunnels (VTIs) According to the Firewall Policy Select this option if there is an Access Control rule that determinces who can access the UserCheck Portal. If the Main URL is set to an external interface, you must set the Accessibility to one of these:
	 Through all interfaces You must select this option if this is a VSX Gateway / VSX Cluster. According to the Firewall Policy
9	UserCheck Client - The UserCheck Client is installed on user devices to communicate with the Security Gateway and show UserCheck Interaction notifications to users.
	 Activate UserCheck Client support This enables UserCheck through the UserCheck Client. Download Client This downloads the installation file for the UserCheck Client.
	Note - The link is not active until the UserCheck Portal is up.
	See the <u><i>R82 Quantum Security Gateway Guide</i></u> > Chapter "UserCheck Client".

Step	Instructions				
10	In the Mail Server section, configure a mail server for UserCheck. This server sends notifications to users that the Security Gateway cannot notify using other means, if the server knows the email address of the user. For example, if a user sends an email which matched on a rule, the Security Gateway cannot redirect the user to the UserCheck Portal because the traffic is not HTTP. If the user does not have a UserCheck Client, UserCheck sends an email notification to the user.			er. Security the traffic is	
	Click th Use sp Select Send e	emails using this m a mail server from	this gatew de the def ail server	ault mail server settings.	ew mail
11	Click OK to close the Security Gateway / Cluster object.				
12	12 If there is encrypted traffic through an internal interface, add a new Firewall Layer of the Access Control Policy. Example rule:		rule to the		
	Source	Destination	VPN	Services & Applications	Action
	Any	Security Gateway on which UserCheck Client is enabled	Any	UserCheck	Accept

Step	Instructions
13	Install the Access Control Policy to enable UserCheck for these Access Control Software Blades.
	 Application Control URL Filtering Content Awareness Data Loss Prevention
	Install the Threat Prevention Policy to enable UserCheck for these Threat Prevention Software Blades:
	 Anti-Bot Anti-Virus Threat Emulation Threat Extraction Zero Phishing

UserCheck CLI

See the <u>*R82 CLI Reference Guide*</u> - Chapter "Security Gateway Commands" - Section "usrchk".

UserCheck Interaction Objects for Access Control Software Blades

This section describes how to configure UserCheck Interaction Objects.

UserCheck Interaction Objects add flexibility and give the Security Gateway a mechanism to communicate with users.

You use the UserCheck Interaction Objects in the "Action" column of the Access Control Policy to:

- Help users with decisions that can be dangerous to the organization security.
- Share the organization changing internet policy for web applications and sites with users, in real-time.

Note - You create and edit UserCheck Interaction objects for the Access Control policy only in SmartConsole.

Action Type	Description
Ask	Users get a message that asks if they want to continue to the requested site. UserCheck Interaction with this action type appear in Access Control rules Profiles > when you click in the Action column > in the menu Ask .
Block	Users get a message that the company policy blocked access to the requested site. UserCheck Interaction with this action type appear in Access Control rules Profiles > when you click in the Action column > in the menu Drop .
Cancel	After a user gets an Inform or Ask notification and clicks Cancel , they get a message that they cancelled their request to access a site.
Inform	Users get a message about the company policy for the requested site and they must click OK to continue to the site.

UserCheck Interaction Action Types

Default UserCheck Interaction Objects for Access Control

Explanation


- Notes:
 - These default objects open in the read-only view.
 - You can right-click each default object and click **Clone**.
 - To preview a default UserCheck Interaction object, click it.
 - 1. From the left navigation panel, click Security Policies.
 - 2. In the top panel, click Access Control.
 - 3. In the bottom panel, click Access Tools, click UserCheck.
 - 4. These are the default UserCheck Interaction objects for Access Control:

Default UserCheck Interaction Object	Action Type
Company Policy	Ask
Blocked Message - Access Control	Block
Cancel Page - Access Control	Cancel
Access Approval	Inform
Access Notification	Inform

Creating New UserCheck Interaction Objects for Access Control

Procedure

- 1. From the left navigation panel, click Security Policies.
- 2. In the top panel, click Access Control.
- 3. In the bottom panel Access Tools, click UserCheck.
- 4. From the top toolbar, click **New** > click the applicable UserCheck Interaction:



Ask UserCheck

If you select this UserCheck Interaction object in a Threat Prevention profile in the applicable Software Blade, then internal users get a message that asks them if they want to continue with the request or not.

To continue with their request, users are expected to enter a reason.

Inform UserCheck

If you select this UserCheck Interaction object in a Threat Prevention profile in the applicable Software Blade, then internal users get an informative message.

Users can continue or cancel their request.

Block UserCheck

If you select this UserCheck Interaction object in a Threat Prevention profile in the applicable Software Blade, then internal users get a message that their request was blocked.

- 5. **Optional:** In the top corner, on the right side of the icon, click the downward arrow and select the desired color.
- 6. In the top field, enter an object name.
- 7. Optional: In the Comment field, enter the applicable text.
- 8. In the left panel, click the Message page:
 - a. To select a language for the message (English is the default), above the message section, click the Languages button > select the required languages > click OK.



Note - The corresponding tab appears for each language you select.

b. To insert a variable field into the message, from the top toolbar, click **Insert Field** and click the applicable variable.

Notes:

- When the Ask, Inform, or Block action occurs, the UserCheck Portal and UserCheck Client replaces these variables with applicable values in the message.
- To resolve the Username variable, you must enable the Identity Awareness Software Blade and configure the required settings. See the <u>R82 Identity Awareness Administration Guide</u>.

c. To add your logo, in the message body, click **Add Logo** > click **★** > click **Add new image** > browse to the required image file and select it > click Open.



- The height of the image must be 176 pixels or less.
- The width of the image must be 52 pixels or less.
- d. To insert special fields for user input, from the top toolbar, click **Insert User Input** and click the applicable option.

Important:

To change the view to raw HTML code, click Source at the top.

To go back, click **Design**.

- You can preview the final message after you save this object.
- 9. In the left panel, click the **Settings** page:
 - a. In the Languages section:

Select the language for the UserCheck page, if a user did not configure a default language in their web browser.

b. In the Faillback Action section:

Note - This section appears only in the UserCheck Interaction object of the type Ask and Inform.

Select the UserCheck action, if it is not possible to show a UserCheck notification on a user's computer:

Fallback Action	Behavior
Allow	Allows the user to access the website or application. The UserCheck Client (if installed) shows the notification.
Drop	The Security Gateway tries to show the notification in the application that caused the notification. If it cannot, and the UserCheck Client is installed, the UserCheck Client shows the notification. Blocks the website or application, even if the user does not see the notification.

c. In the Conditions section:

R Note - This section appears only in the UserCheck Interaction object of the type Ask and Inform.

Select the required condition that users must meet to send their data through the Security Gateway:

Condition	Behavior
User accepted and selected the confirm checkbox	This applies if on the Message page, from the Insert User Input menu you inserted the element Confirm Checkbox . In the message, users must select the checkbox before they can access the application.
User filled some textual input	This applies if on the Message page, from the Insert User Input menu you inserted the element Textual Input . Users must enter text in the text field before they can access the application. For example, you might require that users to enter an explanation for use of the application.

d. In the External Portal section:

Configure whether to redirect users to an external portal instead of showing a UserCheck notification or redirecting them to the UserCheck Portal on the Security Gateway. There is no notification to users about this redirect.

This can be an external system that obtains authentication credentials from the user, such as a user name or password. It sends this information to the Security Gateway.

- i. Select Redirect the user to external portal.
- ii. In the URL field, configure the required URL.
- iii. **Optional:** Select **Add UserCheck Incident ID to the URL query** to append an incident ID to the end of the URL query.
- iv. In the **URL Template** field, enter the path to an XML file on the external portal server, so that it can be sent back to the Security Gateway.

Note - This field appears only in the UserCheck Interaction object of the type Ask and Inform.

v. In the **Pre-Shared Secret** field, enter the required string that authenticates the external portal server to the Security Gateway.

Note - This field appears only in the UserCheck Interaction object of the type **Ask** and **Inform**.

- 10. Click OK.
- 11. Preview this UserCheck Interaction in the right pane in each available language and each available view:
 - Regular View
 - Mobile
 - Agent
 - Email
 - R80.10 and Higher Gateways
 - Earlier Gateways
- 12. Install the Access Control Policy.

Send Email Notifications in Plain Text

Not all emails clients can handle emails in rich text or HTML format.

To accommodate such clients, you can configure the Security Gateway to send email notification in plain text without images, in addition to the HTML format.

The user's email client decides which format to show.

- 1. Connect to the command line to the Security Gateway / each Cluster Member / Scalable Platform Security Group.
- 2. Log in to the Expert mode.
- 3. Back up the configuration file:
 - On a Security Gateway / each Cluster Member:

cp -v \$FWDIR/conf/usrchkd.conf{, BKP}

• On a Scalable Platform Security Group:

```
g all cp -v $FWDIR/conf/usrchkd.conf{, BKP}
```

4. Edit the configuration file:

```
vi $FWDIR/conf/usrchkd.conf
```

5. Change the value of the applicable parameter:

from

```
:send_emails_with_no_images (false)
```

to

```
:send_emails_with_no_images (true)
```

- 6. Save the changes in the file and exit the editor..
- 7. On a Scalable Platform Security Group, copy the modified file to all Security Group Members:

```
asg cp2blades $FWDIR/conf/usrchkd.conf
```

8. Kill the userchkd process to load the new configuration:

• On a Security Gateway / each Cluster Member:

```
killall userchkd
```

• On a Scalable Platform Security Group:

```
g_all killall userchkd
```

The Security Gateway / Cluster Member / Security Group automatically restarts this process.

Localizing and Customizing the UserCheck Portal

For more information, see sk83700.

External Network Feeds

A network feed object is a network object that lets you enforce feeds that are generated on external HTTP/HTTPS servers. The feed can contain IP addresses (single or ranges), domains, or both.

For example:

- Single IP (1.1.1.1)
- Range (1.1.1.1-2.2.2.2)
- IP + masklen (1.1.1.1/24)
- FQDN domain (google.com)
- Non-FQDN domain (*.google.com)

The feed must be written in a supported format (see below). The Security Gateway fetches, parses, and updates the network feed object automatically according to the feed changes on the external source server. There is no need to install policy for the updates to take effect. You can use an external network feed object in the Access Control / HTTPS Inspection / NAT policy as a source, or a destination.

1 Note - Local feeds hosted on the Security Gateway are not supported.

Use Case

This feature is relevant for any customer who wants to use an external source as a network data provider, and use this data in the Rule Base.

When you use a network feed, the Security Gateway updates the feed automatically, which:

- Requires less manual maintenance of the feed
- Reduces the number of policy installations
- Simplifies policy configuration

Notes:

- To work well, the Security Gateway must have access to the feed server through HTTP/HTTPS. Otherwise, the Security Gateway cannot fetch the feed.
- A Security Gateway supports up to 500 network feed objects. Each object can hold up to 50,000 IP addresses. There is no limitation on the number of domains per object.
- A Security Gateway supports a total of 5,000 objects of these types: Dynamic objects, Updatable objects, Generic Data Center objects, and Network Feed objects. A Security Gateway supports a total of 350,000 IP addresses and 12,500 domains in all of these object types combined.
- Supported feed formats: flat list, JSON.
- Dynamic and domain objects enforce the network feeds on the Security Gateway.
- SmartConsole shows logs for update feed events (if there is an Error/Warning during the update), and for a successful feed update. Search for the network feed name in the logs search field.
- You can define network feeds as global objects in Multi-Domain Server environments.
- Make sure that the Security Gateways can always reach the network feed. If the network feed is not reachable or accessible, the latest cached version is used.
- Make sure that the network feed only contains valid entries. The Security Gateways ignore invalid entries and use the rest of the list.

To configure external network feeds:

- 1. In SmartConsole, go to the Object Explorer.
- 2. Click New > More > Network Object > Network Feed.

The New Network Feed window opens.

3. Configure Network settings:

Feed URL - Configure the URL which gives access to the external server feed.



Best Practice - Use HTTPS and not HTTP.

4. Feed Parsing:

Format - Configure the content structure in the feed, so the Security Gateway knows how to parse the feed. The supported formats are Flat list and JSON.

If you select the Flat list format, configure these settings:

 Data type - From the drop-down menu, select: Domain, IP Address or IP Address/Domain, so the Security Gateway knows which data type to enforce.

- **Delimiter** Separates between the data values in the feed.
- Ignore lines with prefix Defines which lines to ignore in the feed.

If you select the JSON format, configure these settings:

- Data Type From the drop-down menu, select: Domain, IP Address or IP Address/Domain, so the Security Gateway knows which data type to enforce.
- JSON Query Defined how to extract the data from the feed in JQ syntax. For more information on JQ, visit <u>http://stedolan.github.io/jq/</u>

5. Advanced Settings:

- Authentication Enter the username and password with which you authenticate to the URL.
- Network:
 - Use gateway proxy for connection Select this checkbox to use the proxy when the Security Gateway connects to the external server.
 - Check feed interval Interval in minutes for the feed update on the Security Gateway. The default is 60 minutes.
- 6. Test Feed:
 - a. Click the **Test Feed** button to make sure that the Security Gateway can connect to the Feed URL and that the certificate of the server which contains the Feed URL is valid.

The Test Feed window opens.

- b. In the **Select gateway** field, from the drop-down menu, select the Security Gateway on which you want to run the test:
 - If the test succeeds, you get a **test completed successfully** message.
 - If the test fails, you get an error message.
 - If the test fails because of an invalid certificate, this error message appears: Test failed to authenticate the server certificate.

In this case, you can override the error message and connect to the server if you trust it.

Select Accept certificate anyway to connect to the server.

- 7. Click OK.
- 8. Use the **New Network Feed** object in your Access Control Rule Base.
- 9. Install the Access Control policy.

Monitoring

To monitor network feeds on the Security Gateway, run these commands in the Expert mode:

1 Note - In a cluster, run these commands on all Cluster Members.

Operation	Command	
See error and warning messages for network feed update events	grep -i < <i>Name of Network Feed></i> \$FWDIR/log/efo_error.elg	
Get a list of IP addresses for all network feeds that are used in the policy	dynamic_objects -efo_show	
Get a list of Domains and IP ranges related to a specific network feed	dynamic_objects -efo <name of<br="">Network Feed></name>	
Get a list of Domains associated with a specific IP address	domains_tool -ip < <i>IP Address</i> >	
Get a list of IP addresses associated with a specific Domain	domains_tool -d < <i>Name of Domain</i> >	

Troubleshooting

To debug network feeds on the Security Gateway, run these commands in the Expert mode:

1 Note - In a cluster, run these procedures on all Cluster Members.

Operation	Procedure
Collect the kernel debug for network feed matching	 Important - This kernel debug causes high CPU load. Schedule a maintenance window. For more information, see the <u>R82 Quantum Security</u> <u>Gateway Guide</u> > Chapter Kernel Debug.
	 Configure the kernel debug options: fw ctl debug 0 fw ctl debug -buf 8200 fw ctl debug -m RAD_KERNEL all fw ctl debug -m DOMO all fw ctl debug -m UP all Examine the kernel debug settings: fw ctl debug -m Start the kernel debug: fw ctl kdebug -T -f > /var/log/kernel_ debug.txt Replicate the issue. Stop the kernel debug - press the CTRL+C keys. Reset the kernel debug options: fw ctl debug 0 Analyze the kernel debug output file: /var/log/kernel_debug.txt
Collect the policy installation debug to see information about network feeds	 In the first shell, start the debug: fw -d fetchlocal -d \$FWDIR/state/

Operation	Procedure
Collect the debug of the network feed update events	 In the first shell, start the debug: TDERROR_ALL_ALL=1 dynamic_objects -efo_ update <name feed="" network="" of=""> >> /var/log/network_feed_update.txt 2>&1 </name> In the second shell, monitor the output file: tail -f /var/log/network_feed_ update.txt In the first shell, stop the debug: Press the CTRL+C keys. In the second shell, stop monitoring the output file: Press the CTRL+C keys. Analyze the debug output file: /var/log/network_feed_update.txt

Connecting On-Premises Management Servers and Security Gateways to the Infinity Portal

You can connect from your on-premises Management Server and Security Gateways to the Infinity Portal. This lets you:

 Run services that are managed in the Infinity Portal on your Management Server and Security Gateways.

To see the full list of services, go to SmartConsole > Infinity Services view.

For some services for the Management Server, you must enable Configuration Sharing and Log Sharing. See the documentation for the specific service in the <u>Infinity Portal</u> <u>Administration Guide</u>.

• See a unified log view of all your Check Point products, in the cloud and on-premises.

This way, you can search for logs and events from all Check Point products in the same place.

• Use new administrator capabilities on the on-premises Management Server.

For example, you can run management APIs on the on-premises Management Server through the Infinity Portal securely from anywhere in the world.

Prerequisites

- You must have a valid license for each Infinity Portal application or service that you use.
- In the SmartConsole Access Control Rule Base, add this rule for Check Point Security Gateways. Use "Check Point Services" as an updatable object (see "Updatable Objects" on page 295):

Source	Destination	Services	Action
Any	Check Point Services	http	Allow

- For non-Check Point gateways, allow access to the domains listed in Scenario 3 of sk179105.
- You must have the Manage integration with Infinity Services option selected on your permission profile. To have this option selected:

Connecting On-Premises Management Servers and Security Gateways to the Infinity Portal

- 1. Go to Manage & Settings > Permissions & Administrators > Permission Profiles
- 2. Open the relevant **Permission Profile**.
- 3. Go to Management, and select Manage integration with Infinity Services.

To connect your Security Management Server and Security Gateway objects from SmartConsole to the Infinity Portal

1. In SmartConsole, go to the Infinity Services view.

Click Get Started.

The Instructions window opens.

- 2. If you do not already have an account in the Infinity Portal, click **Create Account**. For information about how to open an Infinity Portal account, see <u>Getting Started with the</u> <u>Infinity Portal in the Infinity Portal Administration Guide</u>.
- 3. In **Connect to the Infinity Portal and get a token**, click **Get Token** to retrieve a token from the Infinity Portal to create trust between your Quantum Management Server and your Infinity Portal account.
- 4. If you have more than one account, the **Select Account** window in the Infinity Portal opens.

Select the applicable account from the drop-down list and click Next.

ID Note - Each Management Server can connect to one account only.

5. The Connect my Quantum Management to Infinity page opens.

Select the checkbox that indicates that you agree to share your Management Server data with the Infinity Portal, and click **Next**.

The Copy This to SmartConsole page opens.

6. Copy the token and paste it in the Instructions window in SmartConsole.

The Management Server connects to the Infinity Portal.

- 7. Some services require a running agent on the Security Gateways. You can configure automatic onboarding of Security Gateways when connecting the Management Server to the cloud. In **Connection timing for Security Gateways**, select one of these options:
 - Immediately (the default option) All supported Security Gateways are connected to the Infinity Portal immediately when the Security Management Server / Domain Management Server is connected to the Infinity Portal.

Connecting On-Premises Management Servers and Security Gateways to the Infinity Portal

- After policy installation All supported Security Gateways are connected to Infinity Portal only after the Security Management Server / Domain Management Server is connected to Infinity Portal and you install the Access Control policy.
- 8. Click **Connect**.

To share your on-premises Management Server configuration information with the Infinity Portal

- 1. In SmartConsole > Infinity Services view, go to Infinity Portal Settings at the bottom of the page > Configuration Sharing.
- 2. Click Edit.

The Configuration Sharing window opens.

3. Turn the **Enable** button to **ON**, and click **OK**.

The Management Server configuration information is now synchronized with the Infinity Portal.

Note - You cannot edit objects shared from the Management Server in the Infinity Portal.

To share your on-premises Management Server log information with the Infinity Portal

- 1. In SmartConsole > Infinity Services view > go to Infinity Portal Settings (located at the bottom of the page) > Log Sharing.
- 2. Click Edit.

The Log Sharing window opens.

- 3. Select the products whose log information you want to share:
 - All products
 - **Specific products** Select the applicable products from the drop-down list.
- 4. Change the **Enable** button to **ON**, and click **OK**.

The Management Server now synchronizes the log information with the Infinity Portal.

Note - To enable log sharing on a Standalone, the server must have:

- For an incoming log rate of less than 500 logs per second at least 2 CPU cores and 16GB of RAM.
- For an incoming log rate of more than 500 logs per second at least 4 CPU cores and 16GB of RAM.

Connecting On-Premises Management Servers and Security Gateways to the Infinity Portal

To configure the connection timing of Security Gateways to the Infinity Portal

- In SmartConsole > Infinity Services view, go to Gateways Connector at the bottom of the page.
- 2. Click Edit to change the configuration.
- 3. Select one of these two options:
 - Immediately (the default option) All supported Security Gateways are connected to the Infinity Portal immediately when the Security Management Server / Domain Management Server is connected to the Infinity Portal.
 - After policy installation All supported Security Gateways are connected to Infinity Portal only after the Security Management Server / Domain Management Server is connected to Infinity Portal and you install the Access Control policy.

1 Note - For more information on Security Gateway onboarding, see <u>sk180557</u>.

To connect to the applicable service in the Infinity Portal from SmartConsole

- 1. From the left navigation panel, click Infinity Services.
- 2. Go to the applicable service and connect to it.

For more information about each one of the services, see the <u>Infinity Portal Administration</u> <u>Guide</u>.

Troubleshooting

For Troubleshooting issues, see <u>sk181504</u>.

HTTPS Internet traffic uses the TLS (Transport Layer Security) protocol and is encrypted to give data privacy and integrity. However, HTTPS traffic has a possible security risk and can hide illegal user activity and malicious traffic. The enabled Software Blades on the Security Gateway cannot inspect HTTPS traffic because it is encrypted. HTTPS Inspection lets the Security Gateway intercept TLS connections and decrypt their traffic for inspection by the enabled Software Blades.

There are two modes of HTTPS Inspection:

- Outbound HTTPS Inspection To protect against malicious traffic that is sent from an internal client to an external site or server.
- Inbound HTTPS Inspection To protect internal servers from malicious requests that arrive from the Internet or an external network.

The Security Gateway uses certificates and becomes an intermediary between the client computer and the secure web site. All data is kept private in HTTPS Inspection logs. Only administrators with HTTPS Inspection permissions can see all the fields in such logs.

For information on what's new in HTTPS Inspection starting from R80.20, see sk163594.

Intercepting HTTPS Connections

Outbound HTTPS Inspection

Outbound connections are HTTPS connections that arrive from an internal client to an external server.

Outbound connection flow

- 1. An HTTPS request (from an internal client to an external server) arrives at the Security Gateway.
- 2. The Security Gateway intercepts the HTTPS request.
- 3. The Security Gateway determines whether the HTTPS request matches an existing HTTPS Inspection rule:
 - If the HTTPS request does not match a rule, the Security Gateway does not intercept the HTTPS connection.

In this case, HTTPS Inspection is bypassed.

- If the HTTPS request matches a rule, the Security Gateway intercepts the HTTPS connection and continues to the next step.
- 4. The Security Gateway validates the certificate of the external server.

By default, the Security Gateway uses the Online Certificate Status Protocol (OCSP) to check for certificate revocation.

If the certificate does not support OCSP, the Security Gateway uses the Certificate Revocation List (CRL) to check for certificate revocation.

- 5. The Security Gateway creates a new certificate for the connection to the external server.
- 6. The Security Gateway decrypts HTTPS traffic.
- 7. The Security Gateway calls the enabled Software Blades to inspect the decrypted HTTPS traffic.
- 8. If the Security Policy allows this traffic, the Security Gateway encrypts the HTTP connection.
- 9. The Security Gateway sends the HTTPS request to the external server.

Inbound HTTPS Inspection

Inbound connections are HTTPS connections that arrive from an external client and connect to a server in the DMZ or the internal network.

Inbound connection flow

- 1. An HTTPS request (from an external client to an internal server) arrives at the Security Gateway.
 - Note By design, the Security Gateway/Cluster is intentionally configured not to perform HTTPS Inspection on traffic directed towards it. To change this behavior, follow <u>sk114574</u>.
- 2. The Security Gateway intercepts the HTTPS request.
- 3. The Security Gateway determines whether the HTTPS request matches an existing HTTPS Inspection rule:
 - If the HTTPS request does not match a rule, the Security Gateway does not intercept the HTTPS connection.

In this case, the HTTPS Inspection is bypassed.

- If the HTTPS request matches a rule, the Security Gateway intercepts the HTTPS connection and continues to the next step.
- 4. The Security Gateway uses the certificate for the internal server to create an HTTPS connection with the external client.
- 5. The Security Gateway creates a new HTTPS connection with the internal server.
- 6. The Security Gateway decrypts the HTTPS traffic.
- 7. The Security Gateway calls the enabled Software Blades to inspect the decrypted HTTPS traffic.
- 8. If the Security Policy allows this traffic, the Security Gateway encrypts the HTTP connection.
- 9. The Security Gateway sends the HTTPS request to the internal server.

Getting Started with HTTPS Inspection

This section shows an example of how to configure a Security Gateway to intercept outbound and inbound HTTPS traffic.

Step	Instructions
1	Enable the relevant Software Blades on the Security Gateway. You must enable HTTPS Inspection on the Security Gateway for the enabled Software Blades to inspect the decrypted HTTPS traffic.
2	Configure the applicable HTTPS Inspection Policy - Inbound and Outbound. See "HTTPS Inspection Policy" on the next page
3	Configure the Security Gateway to use inbound certificates. See "Working with Inbound CA Certificates" on page 549.
4	 Configure HTTPS Inspection on the Security Gateway: a. Configure the Security Gateway to use outbound certificates and deploy the certificates in your organization. See "Working with Outbound CA Certificates" on page 554 b. Enable HTTPS Inspection on the Security Gateway. c. Configure additional settings. See "Configuring HTTPS Inspection on the Security Gateway" on page 550.
5	Install the Access Control Policy.

HTTPS Inspection Policy

The HTTPS Inspection rules define how the Security Gateways intercepts the HTTPS connections.

Starting from R82, the HTTPS Inspection policy is divided into "Inbound Policy" and "Outbound Policy".

The HTTPS Inspection rules can use the URL Filtering categories to identify traffic for different websites and applications. For example, to protect the privacy of your users, you can use a rule to ignore HTTPS traffic to banks and financial institutions.

By default, a Security Gateway enforces HTTPS Inspection for all enabled supported Software Blades.

These are the Software Blades that support HTTPS Inspection:

- Access Control:
 - Application Control
 - URL Filtering
 - Content Awareness
 - Data Loss Prevention
- Threat Prevention:
 - IPS
 - Anti-Virus
 - Anti-Bot
 - Threat Emulation
 - Threat Extraction
 - Zero Phishing

To enforce HTTPS Inspection for a specific Software Blade, you must:

- 1. Enable the required Software Blade in the Security Gateway object.
- 2. Create an applicable rule in the HTTPS Inspection policy and in the **Blade** column, select the required Software Blade.

You can create different HTTPS Inspection layers in different policy packages. When you create a new policy package, you can use the pre-defined HTTPS Inspection layer, or customize the HTTPS Inspection layer to fit your security needs.

You can share an HTTPS Inspection layer across multiple policy packages.

Columns in HTTPS Inspection Security Policy

These are the columns in the HTTPS Inspection Security Policy rules:

(To show or hide columns, right-click any column header.)

Column	Description
No.	Rule number in the HTTPS Inspection Rule Base.
Name	Name that the system administrator gives this rule.
Source	Network object that defines where the traffic starts.
Destination	Network object that defines the destination of the traffic.
Services	The services (protocols) that are intercepted or bypassed. By default, the services https on port 443 and HTTP_and_HTTPS proxy on port 8080 are intercepted. You can add or delete services in this column.
Site Category	Categories for applications or web sites that are intercepted or bypassed.
Action	The action taken by the Security Gateway when it matches HTTPS traffic to a rule.
	 Inspect - The Security Gateway intercepts the HTTPS connection. Bypass - The Security Gateway does not intercept the HTTPS connection.
	Important - For more information about the connection flow and this action, see:
	 "Outbound HTTPS Inspection" on page 542 "Inbound HTTPS Inspection" on page 543
Track	Tracking and logging action that is done when traffic matches the rule.
Blade	By default, contains the value "All" to inspect the decrypted HTTPS traffic by all the enabled supported Software Blades. You can select specific Software Blades to inspect the decrypted HTTPS traffic.

Column	Description
Install On	Security Gateways that will enforce this HTTPS Inspection Policy. By default, this column contains the object Policy HTTPS Targets . This object automatically applies to all Security Gateways that have HTTPS Inspection enabled. In this column, you can only select Security Gateways that have HTTPS Inspection enabled.
Certificate	This column exists only in the "Inbound Policy". In this column, you select the certificate that the internal server uses for the rule.
Comment	An optional field to add a description for the rule.

Configuring HTTPS Inspection Policy

Establish distinct HTTPS Inspection rules for outbound and inbound traffic within the corresponding outbound and inbound policies.

The inbound rules use a different certificate for each internal server.

You can also create bypass rules for traffic that is sensitive and should not be intercepted. Make sure that the bypass rules are at the top of the Outbound Policy.

Important - Every change in the Outbound Policy or Inbound Policy requires the installation of the Access Control policy.

Sample Outbound HTTPS Inspection Rule Base

No	Name	Sourc e	Destinati on	Servic es	Site Category	Action	Trac k	Install On
1	Financi al sites	*Any	Interne t	https HTTP_ HTTP S_ proxy	Financi al Service s	Bypas s	Log	HTTPS Polic Y Targe ts
2	Outbou nd traffic	*Any	Interne t	https HTTP_ HTTP S_ proxy	Any	Inspe ct	Log	HTTPS Polic Y Targe ts

This table shows a sample HTTPS Inspection Outbound Rule Base for a typical policy.

- 1. Financial sites This is a bypass rule that does not intercept HTTPS connections to websites that are defined in the "Financial Services" category.
- 2. **Outbound traffic -** This rule intercepts HTTPS connections to the Internet. This rule uses the Outbound CA certificate.

Sample Inbound HTTPS Inspection rule

This table shows a sample HTTPS Inspection Inbound rule for a typical policy.

No	Name	Sourc e	Destination	Service s	Action	Certificate
1	Inboun d traffic	*Any	WebCalendarSer ver	https	Inspec t	WebCalendarSe rver CA

Inbound traffic - This rule intercepts HTTPS connections to the network object WebCalendarServer. This rule uses the WebCalendarServer certificate.

HTTPS Inspection Policy Enforcement

HTTPS Inspection Rule Base enforcement consists of two steps:

- 1. Matching the connection against the Rule Base.
- 2. Calculating the action to be performed.

The action is calculated according to the matched rule, the Software Blades defined on the matched rule and the rule exceptions. In certain scenarios, the action in the matched rule is **Inspect**, but as a result of Step 2, the action is changed to **Bypass**. In such case, the HTTPS Inspection log is sent with data from the matched rule, but the action in the logged action is **Bypass**.

Working with Inbound CA Certificates

By design, the Security Gateway / Security Cluster is intentionally configured not to perform HTTPS Inspection on traffic directed towards it. To change this behavior, follow <u>sk114574</u>.

Assigning a Server Certificate for Inbound HTTPS Inspection

When a client from outside the organization initiates an HTTPS connection to an internal web server (for example, a server located in the organization's DMZ behind the Security Gateway, the Security Gateway can intercept the traffic.

To perform HTTPS Inspection in this scenario, the Security Gateway must impersonate the internal web server.

This requires the Security Gateway to present the TLS certificate of the internal web server and have access to the server's certificate private key.

Therefore, the administrator must export the certificate and the private key from the internal web server in the *.p12 format (which includes both) and then import this P12 file to SmartConsole.

After importing the server's certificate, the administrator can add the corresponding certificate object to the HTTPS Inspection Inbound Policy.

To add a server certificate for inbound HTTPS Inspection	

Step	Instructions
1	In SmartConsole, go to Security Policies view > HTTPS Inspection > Inbound Policy > from the top toolbar, click Inbound Certificates .
2	Click Import. The Import Inbound Certificate window opens.
3	Enter a Certificate name and a Comment (optional).
4	Browse to the certificate file.
5	Enter the Password . Enter the same password that was used to protect the private key of the certificate on the server.

Step	Instructions
6	Click OK.
7	Click Close.

The **Successful Import** window opens the first time you import a server certificate. It shows you where to add the object in the HTTPS Inspection policy.

Click **Don't show this again** if you do not want to see the window each time you import a server certificate and **Close**.

Configuring HTTPS Inspection on the Security Gateway

You must configure HTTPS Inspection on each Security Gateway separately.

Step	Instructions
1	From the SmartConsole Gateways & Servers view, double-click the Security Gateway object.
2	Click HTTPS Inspection.
3	Optional: If the outbound CA certificate is already created or imported for another Security Gateway, you can use the global certificate or override it by selecting a specific certificate for each Security Gateway. To override the global certificate, navigate to HTTPS Inspection > Step 1 in the Security Gateway object, select Override global setting and select the required certificate from the drop-down list.
4	Import or Create an outbound CA certificate for HTTPS Inspection. See "Working with Outbound CA Certificates" on page 554.
5	Export and Deploy the outbound certificate in your organization . See "Exporting and Deploying the Generated CA Certificate" on page 557.
6	In Step 3, select Enable HTTPS Inspection.

To configure HTTPS Inspection on a Security Gateway:

Step	Instructions
7	Configure the HTTPS Inspection Deployment Mode :
	 Full inspection - HTTPS connections are intercepted based on the HTTPS Inspection policy. Learning mode - You can configure partial deployment of HTTPS Inspection to estimate its effect on connectivity and performance issues. With Learning mode, the Security Gateway intercepts a small percentage of the traffic to identify connectivity issues and estimate the expected resource consumption for the configured HTTPS Inspection policy. To see the effect of the learning mode or the statuses of all Security Gateways, go to the Security Policies view > HTTPS Inspection > Outbound Policy or Inbound Policy > in the HTTPS Inspection Tools section, click Deployment. For more information, see "HTTPS Inspection Deployment View" on page 553.

Step	Instructions
8	In Additional Settings > Edit, configure the client side and server side fail mode. In case of a client or a server connection error, you can select one of these modes:
	 Fail Open - The Security Gateway does not perform HTTPS Inspection on connections that failed on the server side or client side (HTTPS Inspection is bypassed).
	 Fail Close - The Security Gateway blocks connections that failed as a result of internal system error or server connection error (server side error) or as a result of client connectivity issues.
	You can handle server and client errors based on the global settings, or override the global settings for the specific Security Gateway. To configure Fail-mode configuration globally for all Security Gateways, see <i>"Fail Mode" on page 562</i> .
	To configure fail mode for a specific Security Gateway:
	 a. In Additional Settings, click Edit. The HTTPS Inspection Settings window opens. b. Configure Server Side Fail Mode - In case of an internal system error or a server connection error, select one of these options: Use the global setting - The default global setting is Fail Open. Override global settings - Select Fail-Open or Fail-Close. c. Client-Side Fail Mode - In case of a client connectivity issue is detected, select one of these two options: Use the global setting - The default global setting is Fail Open. Override global setting - The default global setting is Fail Open. Override global setting - The default global setting is Fail Open. Override global setting - The default global setting is Fail Open. Override global setting - The default global setting is Fail Open. Override global setting - The default global setting is Fail Open. Override global setting - The default global setting is Fail Open. Override global setting - The default global setting is Fail Open. Override global setting - The default global setting is Fail Open. Override global setting - The default global setting is Fail Open. In the Fail-Open mode, the Security Gateway blocks the first connection, but does not intercept subsequent connections with the same source and destination hostname, it bypasses them. In the Security Gateway versions R81.20 and lower, in case of a client-side error, the connection is always blocked (Fail-Close). You cannot change the behavior in these versions.

Step	Instructions
9	 Configure Bypass Under Load - This feature allows connectivity when the Security Gateway experiences heavy load (arising from any reason, not necessarily HTTPS Inspection). The Security Gateway reacts quickly to CPU spikes to avoid connection interruptions and temporarily bypasses HTTPS Inspection until the load stabilizes. During the bypass, the Security Gateway does not intercept the HTTPS traffic. After the Security Gateway stabilizes, it attempts to resume HTTPS Inspection to minimize the bypass duration. If persistent high load is detected after inspection resumes, the Security Gateway gradually increases the bypass duration to maintain stability. This feature is disabled by default. Important - To configure log type for Bypass Under Load, go to Security Policies > HTTPS Inspection > Inbound Policy or Outbound Policy > HTTPS Inspection Tools > Advanced Settings > Other > Bypass Under Load Logging. Note - You configure Bypass Under Load for each Security Gateway separately. There are no global settings for this feature.
10	Click OK and Install the Access Control Policy.

HTTPS Inspection Deployment View

This view presents the statuses and recommendations for Security Gateways with HTTPS Inspection enabled in Learning Mode.

It also shows the inspection status of each Security Gateway, as follows:

- Full inspection Displayed when Full Inspection is configured on the Security Gateway. The Security Gateway intercepts all HTTPS connections based on the configured HTTPS Inspection policy.
- Learning mode Displayed when Learning mode is configured on the Security Gateway. Here you can see the effect of the learning mode deployment and a recommendation regarding the deployment of HTTPS Inspection.
- Categorized HTTPS Inspection only Displayed when HTTPS Inspection is disabled on the Security Gateway and Categorized HTTPS websites is globally configured (Manage and Settings view > Blades > Application Control & URL Filtering > Advanced Settings > URL Filtering).
- Disabled HTTPS Inspection is not enabled on the Security Gateway and the Categorized HTTPS websites option is disabled.

Working with Outbound CA Certificates

The outbound CA certificates are used by the Security Gateways managed on the Security Management Server. The first time you enable HTTPS Inspection on one of the Security Gateways, you must create an outbound CA certificate for HTTPS Inspection or import a CA certificate already deployed in your organization. Starting from R82, you can create or import additional outbound certificates.

Creating an Outbound CA Certificate

The outbound CA certificate is saved with a CER file extension and uses a password to encrypt the private key of the file. The Security Gateways use this password to sign certificates for the HTTPS Inspection. You must keep this password secure because it is also used by other Security Management Servers that import the CA certificate to open the file.

After you create an outbound CA certificate, you must export it so it can be distributed to internal clients. If you do not deploy the generated outbound CA certificate on internal clients, users receive TLS error messages in their browsers when connecting to HTTPS sites. You can configure a troubleshooting option that logs such connections.

After you create the outbound CA certificate, use it in rules that intercept outbound HTTPS traffic in the HTTPS Inspection policy.

Step	Instructions				
1	In SmartConsole Gateways & Servers view, double -click the Security Gateway object. The Gateway Properties window opens.				
2	In the navigation tree, click HTTPS Inspection.				
3	 In Step 1, click Create. Note - To create the first outbound certificate, you can also go to the Security Policies view > HTTPS Inspection > Outbound Policy > from the top toolbar, click Outbound Certificates. 				
4	 Enter the necessary information: Issued by (DN) - Enter the domain name of your organization. Private key password - Enter the password that is used to encrypt the private key of the CA certificate. Retype private key password - Enter the password again. Valid from - Select the date range for which the CA certificate is valid. 				
5	Click OK.				

To create an outbound CA certificate

Step	Instructions			
6	Export and deploy the CA certificate. See "Exporting and Deploying the Generated CA Certificate" on page 557.			

Importing an Outbound CA Certificate

You can import a CA certificate that is already deployed in your organization or import a CA certificate created on one Security Management Server to another Security Management Server.



Best Practice - Use private CA Certificates.

For each Security Management Server that has Security Gateways with HTTPS Inspection enabled, you must:

- 1. Import the CA certificate.
- 2. Enter the password the Security Management Server uses to open the CA certificate file and sign the certificates for users. Use this password only when you import the certificate to a new Security Management Server.

To import an outbound CA certificate

Step	Instructions					
1	If the CA certificate was created on another Security Management Server, export the certificate from the Security Management Server, on which it was created. See "Exporting a Certificate from one Security Management Server to Another" on page 558.					
2	In the SmartConsole Gateways & Servers view, double-click the Security Gateway object.					
3	In the navigation tree, click HTTPS Inspection.					
4	 In Step 1, click Import. Note - You can also import the first outbound certificate you create through the Security policies view > HTTPS Inspection > Outbound Policy > from the top toolbar click Outbound Certificate. 					
5	Browse to the certificate file.					
6	Enter the private key password .					
7	Click OK.					

Step	Instructions
8	If the CA certificate was created on another Security Management Server, deploy it to clients. Click "Exporting and Deploying the Generated CA Certificate" on the next page.

Exporting and Deploying the Generated CA Certificate

To prevent users from getting warnings about the generated CA certificates that HTTPS Inspection uses, install the generated CA certificate used by HTTPS Inspection as a trusted CA. You can distribute the CA with different distribution mechanisms such as Windows GPO. This adds the generated CA to the trusted root certificates repository on client computers.

When users run standard updates, the generated CA is in the CA list and they do not receive certificate warnings in their browsers.

Step	Instructions				
1	Export the certificate from the Security Gateway: To export an outbound certificate, use one of these two options:				
	Option 1				
	 a. In SmartConsole, go to the Security Policies view > HTTPS Inspection > Outbound Policy. 				
	 b. In the top tool bar, click Outbound Certificates. The Manage Outbound Certificates window opens. 				
	 c. Select the required certificate, and click the ^{standard} button. d. Select the required folder in which to save the certificate, and click Save. 				
	Option 2				
	 a. In SmartConsole > the Gateways & Servers view > double-click the required Security Gateway object. The Security Gateway object editor opens. b. From the left menu, go to HTTPS Inspection. c. In Step 2, click Export Certificate. d. Select the required folder in which to save the certificate, and click Save 				
2	Use the Group Policy Management Console to add the certificate to the Trusted Root Certification Authorities certificate store. See "Deploying Certificates using Group Policy" on the next page.				
3	 Push the GPO Policy to the client computers in the organization. Note - Make sure that the CA certificate is pushed to the client computer organizational unit. 				
4	Test the CA certificate distribution by browsing to an HTTPS site from one of the client computers. Also, make sure the CA certificate shows the name you entered for the CA certificate that you created in the Issued by field.				

To distribute a certificate with a GPO

Deploying Certificates using Group Policy

You can use this procedure to deploy a certificate to multiple client computers with Active Directory Domain Services and a Group Policy Object (GPO). A GPO can contain multiple configuration options, and is applied to all computers in the scope of the GPO.



R Important - Membership in the local Administrators group, or equivalent, is necessary to complete this procedure.

To deploy a certificate using Group Policy

Step	Instructions					
1	On the Microsoft Windows Server, open the Group Policy Management Console .					
2	Find an existing GPO or create a new GPO to contain the certificate settings. Make sure the GPO is associated with the domain, site, or organization unit whose users you want affected by the policy.					
3	Right-click the GPO and select Edit . The Group Policy Management Editor opens and shows the contents of the policy object.					
4	Open Computer Configuration > Policies > Windows Settings > Security Settings > Public Key Policies > Trusted Publishers.					
5	Click Action > Import.					
6	Do the instructions in the Certificate Import Wizard to find and import the certificate you exported from SmartConsole.					
7	In the navigation pane, click Trusted Root Certification Authorities and repeat steps 5-6 to install a copy of the certificate to that store.					

Exporting a Certificate from one Security Management Server to Another

If you use more than one Security Management Server in your organization, you must first export the CA certificate with the "export https cert" CLI command from the Security Management Server on which it was created before you can import it to other Security Management Servers.

Command syntax

export https cert -help

```
export_https_cert {[-local] | [-s <server address>]} [-f
<certificate file name in the FWDIR/tmp/ directory>]
```

To export the CA certificate

On the Security Management Server, run this command:

```
$FWDIR/bin/export_https_cert -local -f <certificate file name in
the FWDIR/tmp/ directory>
```

Example:

```
$FWDIR/bin/export https cert -local -f mycompany.cer
```

Note - On a Multi-Domain Security Management Server, you must run this command in the context of the applicable Domain Management Server (mdsenv <IP Address of Domain Management Server>).

Working with Trusted CAs for Outbound HTTPS Inspection

When a client initiates a TLS connection to a server, the Security Gateway intercepts the TLS connection. The Security Gateway intercepts the traffic and creates a new TLS connection from the Security Gateway to the designated server.

When the Security Gateway establishes a TLS connection to the designated server, it must validate the server certificate.

HTTPS Inspection comes with a preconfigured list of trusted CAs. This list is updated by Check Point when necessary and is downloaded automatically from the Check Point Download Center to the Management Server. After you get the Trusted CA update on the Security Management Server, you must install the policy on the Security Gateways. You can select to disable the automatic update option and manually update the Trusted CA list. See <u>sk64521</u>.

If the Security Gateway receives a non-trusted server certificate, by default the user gets a self-signed certificate and not the generated certificate. A page notifies the user that there is a problem with the server security certificate, but lets the user continue to the server.

You can change the default setting to block untrusted server certificates. Go to Security Policies > HTTPS Inspection > HTTPS Inspection Tools > Advanced Settings > Server Validations > select Untrusted server certificates.

To manage the list of Trusted Certificates, in SmartConsole, go to the **Security Policies** view > **HTTPS Inspection** > in the **HTTPS Inspection Tools** section, click **Trusted Certificates**.

You can do these actions, in the Trusted Certificates window:

- In the Trusted CAs Package tab:
 - You can check if the trusted CAs package is up-to-date. You can see details about the downloaded package version, the last update timestamp, and the last check for these statuses. You can update the certificates in one of two ways:
 - Automatic update:

Select **Update Trusted CA package automatically**. The Trusted CAs package is updated automatically once a day at 2:00 AM.

• Manual update:

Select **Updated Trusted CAs Package manually**, and click **Update Now** or **Import Trusted CAs Package**, to manually update the package.

• In the **Certificates** section, you can view all certificates included in the package, export certificates, enable or disable certificates.

To enable or disable certificates:

1. Select the applicable certificates using the checkboxes.

Note - You can select all certificates by clicking the top checkbox.

- 2. From the top-menu, click **Actions**, and select **Enable** or **Disable**
- In the **Custom Trusted Certificates** tab, you can import, export or delete a certificate.
- **Note** To apply changes in the Trusted CAs settings, install policy on the applicable Security Gateway.

HTTPS Inspection Global Settings

You can configure HTTPS Inspection global settings for all Security Gateways in **Security Policies > HTTPS Inspection > HTTPS Inspection Tools > Advanced Settings**.

Fail Mode

To change the global settings for the fail mode

- 1. Go to the Security Policies view> HTTPS Inspection > Inbound Policy or Outbound Policy > in the HTTPS Inspection Tools section, click Advanced Settings.
- 2. Go to Fail Mode, and select the applicable settings:
 - a. In Server Side Fail Mode, select one of these options:
 - Bypass all requests (Fail-Open)
 - Block all requests (Fail-Close)
 - b. In Client Side Fail Mode, select one of these options:
 - Bypass all requests (Fail-Open)
 - Block all requests (Fail-Close)
 - Notes:
 - In the Fail-Open mode, the Security Gateway blocks the first connection, but does not intercept subsequent connections with the same source and destination hostname, it bypasses them.
 - In the Security Gateway versions R81.20 and lower, in case of a client-side error, the connection is always blocked (Fail-Close). You cannot change the behavior in these versions.

Categorization Mode

Configure a mode for categorizing HTTPS sites:

- Background All requests are allowed until categorization is complete. When a request cannot be categorized with a cached response, an uncategorized response is received. Access to the site is allowed. In the background, the Check Point Online Web Service continues the categorization procedure. The response is then cached locally for future requests. This option reduces latency in the categorization procedure.
- Hold This is the default setting. When a request cannot be categorized with the cached responses, it remains blocked until the Check Point Online Web Service completes categorization.

Server Validations

When a Security Gateway receives an untrusted certificate from a website server, the settings in this section define when to drop the connection.

- Untrusted server certificate:
 - When selected traffic from a site with an untrusted server certificate is immediately dropped. The user gets an error page that states that the browser cannot display the webpage.
 - When cleared, a self-signed certificate shows on the client machine when there is traffic from an untrusted server. The user is notified that there is a problem with the website's security certificate, but the user can continue to the website (default).
- Revoked server certificate (validate CRL):
 - When selected, the Security Gateway validates the site certificate of each server. The Security Gateway validates the certificate using the Online Certificate Status Protocol (OCSP) standard. OCSP is faster and uses much less memory than Certificate Revocation List (CRL) Validation, which is used for certificate validation in releases lower than R80.10.
 - When cleared, the Security Gateway does not check for revocations of server site certificates.

If OCSP is not supported for a server certificate, the Security Gateway uses CRL validation. If the CRL cannot be reached, the certificate is considered trusted. This is the default configuration. An HTTPS Inspection log is issued that indicates that the CRL could not be reached.

You can change this behavior in Database Tool (GuiDBEdit Tool):

Procedure

- **Important** This change applies to all Security Gateways with enabled HTTPS Inspection
 - 1. Close all SmartConsole windows.
 - 2. Connect with the *Database Tool (GuiDBEdit Tool)* to the Management Server.
 - 3. In the top left panel, click Other > ssl_inspection.
 - 4. In the top right panel, click **general_confs_obj and change**.
 - In the bottom panel, right-click the attribute "drop_if_crl_cannot_be_reached" > click Edit.
 - 6. Change the value from "false" to "true" > click OK.
 - 7. From the top, click the File menu and click Save All.

- 8. Close the Database Tool (GuiDBEdit Tool).
- 9. Connect with SmartConsole to the Management Server.
- 10. Install the Access Control policy.

To validate the CRL, the Security Gateway must have access to the Internet. For example, if a proxy server is used in the organizational environment, you must configure the Security Gateway to use this proxy server.

To configure the proxy server for the Security Gateway:

Optionally, you can use the default proxy server configured in SmartConsole Global Properties.

- 1. In SmartConsole, go to the **Gateways & Servers** view, and double-click the Security Gateway that requires proxy configuration.
- 2. Go to Network Management > Proxy.
- 3. Select Use custom proxy settings for this network object and Use proxy server, and enter the proxy IP address.
- 4. Click OK.
- 5. Install the Access Control policy.
- Important Make sure that there is a rule in the Rule Base that allows outgoing HTTP from the Security Gateway

Expired Server Certificate

- When selected, the Security Gateway drops the connection if the server certificate expired.
- When cleared, the Security Gateway creates a certificate with the expired date. The user can continue to the website (default).
- Track validation errors

Select whether to log the server validation (you can see the logs in the Logs & Events view > Logs in SmartConsole), or trigger other notifications.

Certificate Blocking

You can create a list of certificates that are blocked. Traffic from servers using these certificates is dropped. If a certificate in the list is also in the Trusted CAs list, the block certificate list overrides the Trusted CAs list.

- New Lets you add a certificate. Enter the certificate serial number (in hexadecimal format HH:HH) and a comment that describes the certificate.
- Edit Lets you change the details of the blocked certificate list.

- Delete Lets you delete a certificate from the blocked certificate list.
- Search Lets you search for a certificate in the blocked certificate list.
- Track dropped traffic Select whether to log the server validation (you can see the logs in the Logs & Events view > Logs in SmartConsole), or trigger other notifications.

Bypass Allow Lists

Check Point dynamically updates lists of well-known update services and certificate-pinned applications that can be bypassed for improved connectivity.

- Well-known update services Some well-known update services must be bypassed to function correctly. For the list of updated services, see <u>sk98655</u>.
- Certificate-pinned Applications Some mobile and desktop applications trust only specific server certificates. Such applications may terminate the connection due to a trust issue when presented with a certificate signed by HTTPS Inspection's outbound CA certificate. When a connection from a client which is classified as a certificate-pinned application is detected, the selected action is taken.

Action	Action Description					
Bypass	HTTPS Inspection is bypassed to ensure uninterrupted connectivity, and a 'bypass' log is sent.					
Detect	HTTPS Inspection is not bypassed, and a "Detect" log is sent. The application may show errors or malfunction.					
None	HTTPS Inspection is not bypassed, and a dedicated log is not sent. The application may show errors or malfunction.					

Available actions:

Session Logs

Starting in R82, the Security Gateway can send session logs, which provide a visual overview of the TLS traffic passing through it.

To allow the Security Gateway to send these logs:

- 1. Select Send session logs.
- 2. In the HTTPS Inspection Rule Base, set the **Track** column of the applicable rules to **Log**.

HTTPS Inspection session logs group individual connections into session logs based on several common characteristics:

- Source IP
- Destination IP
- SNI (Server Name Indication)
- HTTPS Inspection Action: Whether the traffic is bypassed or intercepted.
- Bypass Reason: Applicable only if the traffic is bypassed.
- Time Window: Connections that occur within the same 3-hour period.

By aggregating connections with these characteristics, session logs are used to create statistics views, including **Bypass** and **Inspect** decisions. For more details, see "HTTPS Inspection Statistics View" on the next page.

Other

Intermediate CA

Use the "Certificate Authority Information Access" extension to retrieve certificates that are missing from the certificate action.

Automatically retrieve intermediate CA certificates:

- When selected, intermediate CA certificates issued by trusted root CA certificates that are not part of the certificate chain are automatically retrieved using the information on the certificate (default).
- When cleared, a web server certificate signed by an intermediate CA and not sent as part of the certificate chain, is considered untrusted.

Bypass Under Load Logging

To configure the log type for Bypass Under Load:

- 1. Go to the Security Policies view > HTTPS Inspection > Inbound Policy or Outbound Policy
- 2. In the HTTPS Inspection Tools section, click Advanced Settings.
- 3. Click Other.
- 4. In the **Bypass Under Load Logging** section, in the **Track** field, select the applicable option.
- 5. Click OK.
- 6. Install the Access Control policy.

HTTPS Inspection Statistics View

Starting in R82, you can view HTTPS Inspection statistics in the Logs & Events view and in SmartView. The HTTPS Inspection statistics view provides a visual overview of HTTPS traffic that passes through the Security Gateway, including bypass and inspect statistics. The Statistics view is updated every time the Security Gateway sends a session log. (see "Session Logs" on page 565).

Configuration

- 1. Enable the required Software Blades on the Management Server or Log Server
 - a. Connect with SmartConsole to the Management Server.
 - b. On the left navigation panel, go to the Gateways & Servers view.
 - c. Double-click the object of the Management Server or Log Server, to which the Security Gateway sends its logs.
 - d. In the left panel, click General Properties.
 - e. In the Management tab, select these Software Blades:
 - Logging & Status
 - SmartEvent Server
 - SmartEvent Correlation Unit
 - f. Click **OK** and publish your changes.
 - g. In the top left corner, click **Menu > Install database**.
 - h. Select all objects and click Install.
 - i. Monitor the task progress in the bottom left corner.
- 2. Enable HTTPS Inspection session logs on the Security Gateway
 - a. In SmartConsole, go to the Manage & Settings view > Blades > HTTPS Inspection > Advanced Settings.

The HTTPS Inspection - Global Settings window opens.

- b. In the left navigation tree, go to Session Logs.
- c. Select Session Logs and click OK.

Viewing HTTPS Inspection Statistics

You can view the HTTPS Inspection statistics in these two locations:

In SmartConsole

- 1. On the left navigation panel, click Logs & Events.
- 2. At the top, click [+] to open a new tab.
- 3. In the left section, click Views.
- 4. In the top search field, enter: HTTPS.
- 5. Double-click the view called HTTPS Inspection Statistics.

In SmartView

1. With a web browser, connect to the SmartView portal on the Management Server or Log Server, to which the Security Gateway sends its logs.

For example:

https://192.168.22.33/smartview/

- 2. At the top, click [+] to open a new tab.
- 3. In the left section, click Views.
- 4. In the top search field, enter: HTTPS
- 5. Double-click the view HTTPS Inspection Statistics

To see log details:

- 1. In the HTTPS Inspection Statistics view, double-click the applicable chart or graph to see all the related session logs.
- 2. Double-click the applicable session log to see all the related connection logs (appear in the bottom panel).
- 3. Double-click the applicable connection log to see the complete log details.

SNI support for Site Categorization

Starting from R80.30, a new functionality allows the categorization of HTTPS sites before the HTTPS Inspection begins, and prevents connectivity failure if the inspection does not succeed.

SNI is an extension to the TLS protocol, which indicates the hostname at the start of the TLS handshaking process.

The categorization is performed by examining the SNI field in the client hello message at the beginning of the TLS handshaking process. To make sure that you reached the right site, the SNI is verified against the Subject Alternative Name of the host, which appears in the certificate.

After the identity of the host is known and verified, the site is categorized, and it is determined whether the connection should be intercepted or not.

SNI support is enabled by default.

HTTPS Inspection on Non-Standard Ports

Applications that use HTTP normally send the HTTP traffic to the TCP port 80. Some applications send HTTP traffic on other ports also. You can configure some Software Blades to only inspect HTTP traffic on port 80, or to also inspect HTTP traffic on non-standard ports.

The security policies inspect all HTTP traffic, even if it is sent using non-standard ports. This option is enabled by default. You can configure this option in the **Manage & Settings** view > **Blades > Threat Prevention > Advanced Settings > General > HTTPS Inspection**. If you make this change, you must install the Access Control policy.

Inspection of TLS v1.3 Traffic

Starting from R81, the Check Point Security Gateway can intercept traffic that relies on Transport Layer Security (TLS) v1.3 (see <u>RFC 8446</u>).

From R81.10, this feature is enabled by default for Security Gateways (and Cluster Members) that use the User Space Firewall (USFW)).

For the list of supported platforms, see sk167052.

Notes:

- To disable the inspection of the TLS v1.3 traffic for testing purposes, set the value of the global parameter "fwtls_enable_tlsio" to 0 with this command:
 - fw ctl set -f int fwtls_enable_tlsio 0
- To enable the inspection of the TLS v1.3 traffic again, set the value of the global parameter "fwtls_enable_tlsio" to 1 with this command: fw ctl set -f int fwtls enable tlsio 1
- HTTPS Inspection does not support TLS v1.3 when the Security Gateway / Cluster is configured as an HTTP/HTTPS Proxy (<u>sk110013</u>).

Inspection of HTTP/3 protocol (RFC 9114)

Starting from R82, Check Point Security Gateways can inspect the decrypted inbound and outbound HTTP/3 traffic based on the configuration of the enabled Software Blades.

HTTP/3 is a new version of the HTTP protocol designed to improve speed, reliability, and security, by using the QUIC transport protocol, which operates over UDP instead of TCP. The HTTP/3 protocol (RFC 9114) optimizes transport of HTTP semantics over QUIC.

HTTP/3 retains all core features of HTTP/2, while enhancing efficiency through reduced latency and improved performance.

HTTP/3 over TLS enables HTTP/3 connections over a secure TLS connection.

Best Practice - For Security Gateways running version R81.20 and earlier, block the QUIC protocol as described in <u>sk111754</u>.

Using HTTPS/3 the in a Rule Base

For transparent QUIC inspection, the QUIC service was added default HTTPS services group. You can use it in the Access Control policy in the **Services & Applications** column, and in the HTTPS Inspection policy, in the **Services** column.

For example:

N o.	Name	Sour ce	Destinat ion	Servic es	Categor y/ Custom Applicat ion	Action	Trac k	Blad e	Install On
1	QUIC - Bypas s the "game s" categ ory	*Any	Intern et	quic	Games	Bypas s	Log	All	Polic Y HTTPS Targe ts
2	QUIC - Inspec t	*Any	Intern et	quic	Any	Inspe ct	Log	All	Polic Y HTTPS Targe ts

Monitoring the HTTP/3 inspection

You can view the HTTP/3 inspection statistics on the Security Gateway in CPView:

1. Connect to the command line on the Security Gateway, and run:

cpview

2. At the top, click Advanced > HTTP-Parser > QUIC.

Example output:

```
| Logging CPU-Profiler Memory Network SDWAN SecureXL ClusterXL
CoreXL PrioQ Streaming NAT MUX Routed RAD Conn-Tracker UP HTTP-
Parser SSH-Parser CPAQ
               >>
_____
_____|
| General HTTP3-Information QUIC
         _____
_____|
| Connections overview
         | Processed Connections:
                                    0
         | HTTPS Inspection - Inspect:
                                    0
         0
| Website Categorization:
         | HTTPS Inspection - Bypass on first packet:
                                    0
         | HTTPS Inspection - Bypass on category/app:
                                    0
| Downgraded:
                                    0
                                    0
| Closed with error:
          _____
 _____
----- |
| Downgrade reasons
         I
```

```
| QUIC inspection disabled
                                 0
              | Strict Hold is active
                                 0
              | Exception
                                 0
              _____
  _____
 _____
| QUIC Errors
              | Error type
                                                     #
of errors
                 # in the last 10 min window
               | Unknown error
                                                     0
                 0
              | Transport internal error
                                                     0
                 0
              | Connection refused
                                                     0
                 0
| Flow control violation on stream
                                                     0
                 0
              | Frame exceeding stream limits
                                                     0
                 0
              | Received frame mismatch with stream state
                                                     0
                 0
              | New final size mismatch with previous final size
                                                     0
                 0
              | Could not decode frame
                                                     0
                 0
              0
| Bad transport parameters
                 0
```

```
| Received connection ID going over the limit
                                                                      0
                      0
                                                                      0
| Protocol violation
                      0
                   | Invalid token
                                                                      0
                      0
| Connection timeout due to lack of progress
                                                                      0
                      0
                   | Crypto buffer exceeded crypto level in stream
                                                                      0
                      0
| Key update error
                                                                      0
                      0
                   | AEAD limit reached
                                                                      0
                      0
                   0
| No viable path
                      0
| Cannot create control stream: peer-imposed limit
                                                                      0
                      0
| HTTP internal error
                                                                      0
                      0
                                                                      0
| Cannot create stream
                      0
| Critical stream closed
                                                                      0
                      0
                                                                      0
| Unexpected frame received on stream
                      0
                                                                      0
| Malfored frame: could not parse frame
                      0
| Excessive load
                                                                      0
                      0
                   0
| Invalid stream ID
                      0
```

	Unexpected HTTP/2 setting 0	0
I	First control frame is not SETTINGS 0	0
Ι	Got stream while going away 0	0
	Refuse push stream	0
I	Request is incomplete 0	0
I	Parsing error: frame contains invalid headers 0	0
I	Content error 0	0
I	Version fallback	0
	Stream QPACK decompression error	0
I	Error interpreting QPACK encoder stream	0
I	Error interpreting QPACK decoder stream	0
I	Invalid certificate	0

Limitations

The Security Gateways supports HTTP/3 inspection only when it runs in the User Space Firewall (USFW) mode, which is the default in versions R82 and higher.

The Security Gateway downgrades HTTP/3 traffic to an earlier HTTP version when it operates in the kernel mode firewall.

For information about the User Space Firewall (USFW) mode, see the Release Notes for your version and $\frac{sk167052}{sk167052}$.

- The Security Gateway drops HTTP/3 traffic when the Threat Prevention "Deep Inspection" mode is enabled.
- Chromium-based web browsers allow HTTP/3 traffic only if the HTTPS Inspection certificate is signed by a trusted CA from the Chromium trust list.

Chromium-based web browsers do not allow adding certificates for HTTP/3 traffic to the browser's trusted store. See sk11754.

- Inspection of QUIC traffic over a proxy is not supported.
- All other protocols, except HTTP/3, will be downgraded to an earlier HTTP version.

Blocking TLS Connections

You can block inbound TLS 1.0 and TLS 1.1 connections through a Security Gateway to internal networks, and outbound TLS 1.0 and TLS 1.1 connections from internal networks to a Security Gateway.

Prerequisites

- Management Server R80 and higher.
- Security Gateway R80.10 and higher.
- Enable the Application & URL Filtering Layer in the Access Control Policy.
- Enable the Application & URL Filtering blade on the Security Gateway.
- This procedure works in all these configuration combinations:

	HTTPS Inspection is enabled	HTTPS Inspection is disabled
Categorize HTTPS websites is enabled	Yes	Yes

	HTTPS Inspection is enabled	HTTPS Inspection is disabled
Categorize HTTPS websites" is disabled	Yes	Yes

Notes:

- To enable categorize HTTPS websites: In SmartConsole, go to the Manage & Settings view > Blades > Application Control & URL Filtering, click Advanced Settings > URL Filtering > Select Categorize HTTPS websites.
- To enable HTTPS Inspection: in SmartConsole, go to the Gateways & Servers view, double click the required Security Gateway or Security Cluster object, in the Security Gateway or Security Cluster editor, go to the HTTPS Inspection page, and select Enable HTTPS Inspection.
- When HTTPS Inspection is enabled, blocking TLS connections works in both Kernel Space Firewall (KSFW) and User Space Firewall (USFW).
 For more information about these Firewall modes, see <u>sk167052</u>.

Procedure

Part 1 - Create User-Defined Services

- 1. Use SmartConsole to connect to the Security Management Server or the Domain Management Server that manages this Security Gateway.
- 2. In the top-right corner in SmartConsole, click **Objects** and the icon, which opens the **Object Explorer** window.
- 3. In the top search field, search for:

tls

iect Explorer			
* All -	💥 New ▾ 🚿	× 🖆 Act	ions 🗸 🔍 tls 😢
 Categories 	Name	Port	Comments
categories	🜩 <mark>tis</mark> 1.2	443	
	In the sip_tis_authentication	5061	
 Applications/Categories (2) 	sip_tts_not_inspected	5061	
	- tis 1.0	443	
	🜩 <mark>tis</mark> 1.1	443	
	🜩 Idap-ssl	636	Lightweight Directory Access Protocol over TLS/SSL
	🚱 https	443	HTTP protocol over <mark>TLS</mark> /SSL


- 4. To block TLS 1.0 connections:
 - a. Right-click the predefined service **tls1.0**, and click **Clone**.

New TCP Service	Q, ❷ ×
	tls1.0_Clone Enter comment
44	Constant
General	General
Advanced	Protocol: - TLS10 -
	Match By
	Port:
	 Standard Port (443)
	O Customize ()
	Match for 'Any' Disabled.
	 Protocol Signature is disabled
	 Match for 'Any' is disabled
Groups	
	OK Cancel

The **New TCP Service** window opens.

- b. In the Name field, change the name from tls1.0_Clone to the required name.
 For example: tls1.0_Block
- c. Optional: In the **Comment** field, enter the applicable text. For example: User-defined service to block TLS 1.0 connections
- d. In the left panel, click Advanced.

e. In the top section, select Protocol Signature.



- f. Click OK.
- 5. To block TLS 1.1 connections:
 - a. Right-click the predefined service tls1.1, and click Clone.

The New TCP Service window opens.

New TCP Service	<u> </u>
	Is1.1_Clone inter comment
44	
General	General
Advanced	Protocol: - TLS11 -
	Match By
	Port:
	 Standard Port (443)
	Customize 0
	Match for 'Any' Disabled.
	Protocol Signature is disabled
	 Match for 'Any' is disabled
Groups	
	OK Cancel

- b. In the Name field, change the name from tls1.1_Clone to the required name.
 For example: tls1.1_Block
- c. Optional: In the **Comment** field, enter the applicable text.

For example: User-defined service to block TLS 1.1 connections.

- d. In the left panel, click Advanced.
- e. In the top section, select Protocol Signature.

New TCP Service	Q 😡 🗙
4	tls1.1_Block User-defined service to block TLS 1.1 connections
44 General	Source port:
Advanced	Protocol Signature Note: Protocol detection may allow several packets to pass the firewall until detection, even in drop rules.
	 Enable for TCP resource. Match for 'Any' Keep connections open after the policy has been installed.

f. Click OK.

Example result:

Object Explorer			
* All	🗧 New 👻 🔪 🔀 Actions 🕶	Q tls	8
▼ Categories	Name	Port	Comments
 Categories Services (9) 	🜩 tls1.2	443	
	■ sip_tls_authentication	5061	
 Applications/Categories (2) 	sip_tls_not_inspected	5061	
	🜩 tis1.0	443	
	🜩 tis1.1	443	
	🗧 Idap-ssi	636	Lightweight Directory Access Protocol over TLS/SSL
	🚱 https	443	HTTP protocol over TLS/SSL
	🗢 tls1.0_Block	443	User-defined service to block TLS 1.0 connections
	🜩 tls1.1_Block	443	User-defined service to block TLS 1.1 connections

6. Close the **Object Explorer** window.

Part 2 - Configure the Security Gateway

- 1. In SmartConsole, go to the Gateways & Servers view.
- 2. Double-click the applicable Security Gateway or Security Cluster object.

The Security Gateway or Security Cluster editor opens.

- 3. In the General Properties page, go to the Network Security tab.
- 4. Select the Application Control Software Blade.
- 5. Click OK.

Part 3 - Enable the Application & URL Filtering Layer

- 1. In the top left corner of SmartConsole, click , and select Manage policies and layers.
- Right-click the applicable policy that you installed on the Security Gateway or Security Cluster > click Edit.

Manage policies a	nd lay	ers			
44					
No Policies					🗊 Open
🕨 🍣 Layers			Na	me 🔺	Access Control
			L.	Standard	~
	Ŵ	Open			
	*	New			
	\mathbf{N}	Edit			
	×	Delete			
	Ľ	Actions	×		
4					

3. In the Access Control row, click in the top right corner, and select Edit Layer.

Policy				୯ ଡ ା ×
	rdard comment			
•• General Installation Targets	Policy Types	tion 🔽 💽 Threat Prevention		
	 Access Control VPN Traditional mode 	Blades: III	×	Edit Layer Delete Layer
	Custom Threat Prevention			Move Up Move Down
	Le Autonomous Threat Prevention			
	ATTPS Inspection (*)	Default Inbound Layer		■C Shared = -
		Default Outbound Layer		■C Shared = -
				OK Cancel

4. On the General page, in the Blades section, select Application & URL Filtering.

Layer Editor						ଦ୍ 😮	×
General Advanced Permissions	Blades Firewall Applications Content Awa Mobile Access Preview: Destination Sharing Multiple police	vpn	Filtering Services & Applications	Action	Track	Install Or	r
				ОК		Cancel	

5. Click OK to close the Layer Editor window.

- 6. Click **OK** to close the **Policy** window.
- 7. Close the Manage policies and layers window.

Part 4 - Configure the Access Control Policy

- 1. In the left navigation panel in SmartConsole, click Security Policies.
- 2. In the Access Control section, click Policy.
- 3. Add the applicable new rules to block TLS 1.0 and TLS 1.1 connections:

Name	Source	Destinatio n	VPN	Services & Applicatio ns	Conten t	Action	Track
Block TLS 1.0	Applicabl e Source	Applicable Destinatio n	*Any	User- defined services tls1.0_ Block	*Any	Drop	Log or None
Block TLS 1.1	Applicabl e Source	Applicable Destinatio n	*Any	User- defined services tls1.1_ Block	*Any	Drop	Log or None

- 4. Publish the session.
- 5. Install the Access Control policy on the Security Gateway or Security Cluster object.

Client Certificates for Smartphones and Tablets

To allow your users to access their resources using their handheld devices, make sure they can authenticate to the Security Gateway with client certificates.

In many organizations, the daily task of assigning and maintaining client certificates is done by a different department than the one that maintains the Security Gateways. The computer help desk, for example. You can create an administrator that is allowed to use SmartConsole to create client certificates, while restricting other permissions (see *"Giving Permissions for Client Certificates" on page 588*).

To configure client certificates, open SmartConsole and go to **Security Policies > Access Control > Access Tools > Client Certificates**.

To configure the Mobile Access policy, go to Manage & Settings > Blades > Mobile Access > Configure in SmartDashboard. The Client Certificates page in SmartConsole is a shortcut to the SmartDashboard Mobile Access tab, Client Certificates page.

Managing Client Certificates

Check Point Mobile Apps for mobile devices can use certificate-only authentication or twofactor authentication with client certificates and username/password. The certificate is signed by the internal CA of the Security Management Server that manages the Mobile Access Security Gateway.

Manage client certificates in Security Policies > Access Control > Access Tools > Client Certificates.

The page has two panes.

- In the Client Certificates pane:
 - Create, edit, and revoke client certificates.
 - See all certificates, their status, expiration date and enrollment key. By default, only the first 50 results show in the certificate list. Click **Show more** to see more results.
 - Search for specified certificates.
 - Send certificate information to users.
- In the Email Templates for Certificate Distribution pane:
 - Create and edit email templates for client certificate distribution.
 - Preview email templates.

Creating Client Certificates

Note - If you use LDAP or AD, creation of client certificates does not change the LDAP or AD server. If you get an error message regarding LDAP/AD write access, ignore it and close the window to continue.

To create and distribute certificates with the client certificate wizard:

- 1. In SmartConsole, select Security Policies > Access Control > Access Tools > Client Certificates.
- 2. In the Client Certificates pane, click New.

The Certificate Creation and Distribution wizard opens.

- 3. In the **Certificate Distribution** page, select how to distribute the enrollment keys to users. You can select one or both options.
 - a. Send an email containing the enrollment keys using the selected email template -Each user gets an email, based on the template you choose, that contains an enrollment key.
 - **Template** Select the email template that is used.
 - Site Select the Security Gateway, to which users connect.
 - Mail Server Select the mail server that sends the emails.

You can click Edit to view and change its details.

- b. Generate a file that contains all of the enrollment keys Generate a file for your records that contains a list of all users and their enrollment keys.
- 4. **Optional:** To change the expiration date of the enrollment key, edit the number of days in **Users must enroll within x days**.
- 5. **Optional:** Add a comment that will show next to the certificate in the certificate list on the **Client Certificates** page.
- 6. Click Next.

The Users page opens.

- 7. Click Add to add the users or groups that require certificates.
 - Type text in the search field to search for a user or group.
 - Select a type of group to narrow your search.
- 8. When all included users or groups show in the list, click **Generate** to create the certificates and send the emails.

9. If more than 10 certificates are being generated, click **Yes** to confirm that you want to continue.

A progress window shows. If errors occur, an error report opens.

- 10. Click Finish.
- 11. Click Save.
- 12. In SmartConsole, install the Policy.

Revoking Certificates

If the status of a certificate is Pending Enrollment, after you revoke it, the certificate does not show in the **Client Certificate** list.

To revoke one or more certificates

- 1. Select the certificate or certificates from the Client Certificate list.
- 2. Click Revoke.
- 3. Click OK.

After you revoke a certificate, it does not show in the Client Certificate list.

Creating Templates for Certificate Distribution

To create or edit an email template

- In SmartConsole, select Security Policies > Access Control > Access Tools > Client Certificates.
- 2. To create a new template: In the **Email Templates for Certificate Distribution** pane, select **New**.

To edit a template: In the **Email Templates for Certificate Distribution** pane, doubleclick a template.

The Email Template opens.

- 3. Enter a Name for the template.
- 4. **Optional:** Enter a **Comment**. Comments show in the Mail Template list on the **Client Certificates** page.
- 5. Optional: Click Languages to change the language of the email.

- 6. Enter a **Subject** for the email. Click **Insert Field** to add a predefined field, such as a Username.
- 7. In the message body add and format text. Click **Insert Field** to add a predefined field, such as Username, Registration Key, or Expiration Date.
- 8. Click inside the E-mail Template body.
- 9. Click **Insert Link** and select the type of link to add (link or QR code).
 - Site and Certificate Creation

For users who already have a Check Point app installed.

When users scan the QR code or go to the link, it creates the site and registers the certificate.

Select the client type that will connect to the site- Select one client type that users will have installed:

- **Capsule Workspace** An app that creates a secure container on the mobile device to give users access to internal websites, file shares, and Exchange servers.
- Capsule Connect/VPN A full Layer 3 tunnel app that gives users network access to all mobile applications.

Download Application

Direct users to download a Check Point App for their mobile devices.

Select the client device operating system:

- iOS
- Android

Select the client type that will connect to the site- Select one client type that users will have installed:

- **Capsule Workspace** An app that creates a secure container on the mobile device to give users access to internal websites, file shares, and Exchange servers.
- Capsule Connect/VPN A full Layer 3 tunnel app that gives users network access to all mobile applications.
- Custom URL

Lets you configure your own URL.

For each link type, you can select which elements are added to the mail template

- Link URL Enter the full link address.
- **QR Code** When enabled, users scan the code with their mobile devices.
- HTML Link When enabled, users tap the link on their mobile devices.
 You can select both QR Code and HTML Link to include both in the email.
- Display Text Enter the text for the link title.
- 10. Click OK.
- 11. Optional: Click Preview in Browser to see a preview of how the email will look.
- 12. Click OK.
- 13. Publish the changes.

Cloning a Template

Clone an email template to create a template that is similar to one that already exists.

To create a clone of an email template

- 1. Select a template from the template list in the **Client Certificates** page.
- 2. Click Clone.
- 3. A new copy of the selected template opens for you to edit.

Giving Permissions for Client Certificates

You can create an administrator that is allowed to use SmartConsole to create client certificates, and restrict other permissions.

To make an administrator for client certificates

- 1. Define an administrator (see "Managing Administrator Accounts" on page 74
- Create a customized profile for the administrator, with permission to handle client certificates. Configure this in the **Others** page of the Administrator Profile. Restrict other permissions (see "Assigning Permission Profiles to Administrators" on page 115).

Preferences and Management Settings

This section describes various settings in SmartConsole.

Database Revisions

The Security Management architecture has built-in revisions. Each publish operation creates a new revision which contains only the changes from the previous revisions.

Benefits of the revision architecture:

- Safe recovery from a crisis, restoring a database to a good known revision.
- Fast policy verification, based on the differences between installed versions
- More efficient Management High Availability.

Important - Before using the revision feature consider these limitations:

- Database Revision revert operation is not supported on a Backup Security Management Server.
- Reverting to a previous revision is an irreversible operation. Versions that are newer than the target revision are lost.
- Changes apply to objects only and not to the file system.
- Tasks, SIC, and Licenses are not reverted.
- The revert action disconnects all other connected users and discards all of their private sessions.
- Revision is not supported in these scenarios:
 - For the Endpoint Security Management Server.
 - If SmartConsole and the Security Management Server are connected through a proxy server, the GUI for this feature is not supported. In this case, use the applicable API command.
 - VSX configuration or related networks differ between the source and target revisions.
 - A new Multi-Domain Server, a Security Management Server or a Check Point object was created or deleted after the target revision date.
 - The corresponding revision of the Global Domain, or the IPS or Application Control components was purged.
- When you revert to a previous revision, a configuration of Site to Site VPN Tunnel with Native Cloud is not saved. (See <u>R82 Site to Site VPN</u> <u>Administration Guide</u> > Chapter Seamless Site to Site VPN Tunnel with Native Cloud.).



- 1. We recommend to update the IPS and Application Control signatures and install the policy after the revert. Install policy if changes to log destinations are applied.
- If you need a full environment restore to a certain point in time, use Restore Backup. All work done after the backup is lost. To learn more, see the: <u>R82</u> <u>Gaia Administration Guide</u>
- 3. We recommend to purge irrelevant revisions. Accumulating too many revisions can create a heavy load on the server, which may cause disk and performance issues.

To see saved database versions:

In SmartConsole, go to Manage & Settings > Sessions > Revisions.

To open a specific revision:

1. Go to Manage & Settings > Sessions > Revisions, and select a revision.

The bottom pane shows the audit logs of the changes made in the revision.

2. Optional: Click View.

A separate read-only SmartConsole session opens.

To compare between two revisions:

- 1. In SmartConsole, go to Manage & Settings > Sessions > Revisions.
- 2. Select a revision.
- 3. In the toolbar, click Changes.
- 4. Select the revision to compare to:
 - The current revision

Or

 A previous revision in the list. If you select this option, select the applicable revision from the list.

A changes report is generated. The report shows a comparison between the two selected revisions.

To revert to an earlier revision

- 1. Go to Manage & Settings > Sessions > Revisions, and select a revision.
- 2. In Actions, click Revert to this Revision.

The Revert to Revision wizard opens.

To delete all versions of the database that are older than the selected version:

- 1. Go to Manage & Settings > Sessions > Revisions, and select a revision.
- 2. In Actions, click Purge.
- 3. In the confirmation window that opens, click Yes.

Important - Purge is irreversible. When you purge, that revision and older revisions are deleted.

- Notes:
 - When connected with SmartConsole to a Security Management Server, sessions that were published through the Management API in the system Domain are not shown in the **Revisions** view.
 - When you connect with the Management API to the Domain of a Security Management Server and run the show sessions API command with viewpublished-sessions set to true, sessions that were published through SmartConsole are not returned, even if they include changes in the system Domain.

Setting IP Address Versions of the Environment

Many objects and rules use IP addresses. Configure the version that your environment uses to see only relevant options.

To set IP address version

- 1. Click Manage & Settings.
- 2. Click Preferences.
- 3. Select the IP address version that your environment uses: IPv4, IPv6, or IPv4 and IPv6.
- 4. Select how you want to see subnets: Mask Length or Subnet Mask.

Restoring Window Default

Some windows in the SmartConsole offer administrators the option to not see the window again. You can undo this selection, and restore all windows to show again.

This option is available only if administrators selected **do not show** in a window.

To restore windows from "do not show"

- 1. Click Manage & Settings.
- 2. Click Preferences.
- 3. In the User Preferences area, click Restore All Messages.

Configuring the Login Window

Administrators in your environment use SmartConsole daily. Customize the Login window, to set the environment to comply with your organization's culture.

To customize the Login window

- 1. Click Manage & Settings.
- 2. Click Preferences > Login Message.

The Login Message window opens.

- 3. Select Show custom message during login.
- 4. In Customize Message, enter a Header and Message for administrators to see.

```
The default suggestion is:
Warning
This system is for authorized use only
```

- 5. If you want the message to have a warning icon, in **Customize Layout**, select **Add warning sign**.
- 6. If you want the Login window to show your organization's logo, in **Customize Layout**, select **Add logo** and then **Browse** to an image file.

Synchronization with UserCenter

You can add information regarding your environment to User Center, such as Security Gateway name, version, and active blades. Check Point uses this additional information for better inventory management, pro-active support, and more efficient ticket resolution.

To learn more, see sk94064.

To sync with User Center

- 1. In SmartConsole, click Manage & Settings.
- 2. Click Sync with User Center
- 3. Select Synchronize information once a day.

Inspection Settings

You can configure inspection settings for the Security Gateway:

- Deep packet inspection settings
- Protocol parsing inspection settings
- VoIP packet inspection settings

The Security Management Server comes with two preconfigured inspection profiles for the Security Gateway:

- Default Inspection
- Recommended Inspection

When you configure a Security Gateway, the **Default Inspection** profile is enabled for it. You can also assign the **Recommended Inspection** profile to the Security Gateway, or to create a custom profile and assign it to the Security Gateway.

To activate the Inspection Settings, install the Access Control Policy.

Configuring Inspection Settings

To configure Inspection Settings

- 1. In SmartConsole, go to the Manage & Settings > Blades view.
- 2. In the General section, click Inspection Settings.

The Inspection Settings window opens.

You can:

- Edit inspection settings.
- Edit user-defined Inspection Settings profiles. You cannot change the Default Inspection profile and the Recommended Inspection profile.
- Assign Inspection Settings profiles to Security Gateways.
- Configure exceptions to settings.

To edit a setting

- 1. In the **Inspection Settings** > **General** view, select a setting.
- 2. Click Edit.
- 3. In the window that opens, select a profile, and click Edit.

The settings window opens.

- 4. Select the Main Action:
 - Default Action preconfigured action
 - Override with Action from the drop-down menu, select an action with which to override the default - Accept, Drop, Inactive (the setting is not activated)
- 5. Configure the Logging Settings

Select **Capture Packets**, if you want to be able to examine packets that were blocked in Drop rules.

- 6. Click OK.
- 7. Click Close.

For advanced configuration of SYN attacks, see <u>sk120476</u>.

To view settings for a certain profile

- 1. In the Inspection Settings > General view, click View > Show Profiles.
- 2. In the window that opens, select Specific Inspection settings profiles.
- 3. Select profiles.
- 4. Click OK.

Only settings for the selected profiles are shown.

You can add, edit, or delete custom Inspection Settings profiles.

To edit a custom Inspection Settings profile

- 1. In the **Inspection Settings > Profiles** view, select a profile.
- 2. Click **Delete**, to remove it, or click **Edit** to change the profile name, associated color, or tag.
- 3. If you edited the profile attributes, Click **OK** to save the changes.

To add a new Inspection Settings profile

- 1. In the **Profiles** view, click **New**.
- 2. In the New Profile window that opens, edit the profile attributes:
- 3. Click OK.

To assign an Inspection Settings profile to a Security Gateway

- In the Inspection Settings > Gateways view, select a Security Gateway, and click Edit.
- 2. In the window that opens, select an Inspection Settings profile.
- 3. Click OK.

To configure exceptions to inspection settings

1. In the **Inspection Settings** > **Exceptions** view, click **New** to add a new exception, or select an exception and click **Edit** to modify an existing one.

The Exception Rule window opens.

- 2. Configure the exception settings:
 - Apply To select the **Profile** to which to apply the exception
 - Protection select the setting
 - Source select the source Network Object, or select IP Address and enter a source IP address
 - Destination select the destination Service Object
 - Service select Port/Range, TCP or UDP, and enter a destination port number or a range of port numbers
 - Install On select a Security Gateway, on which to install the exception
- 3. Click OK.

To enforce the changes, install the Access Control Policy.

SmartTasks

Management SmartTasks let you configure automatic actions according to different triggers in the system. A SmartTask is a combination of trigger and action.

- **Triggers** are events currently defined in terms of existing management operations, such as installing a policy or publishing a session.
- Actions are automatic responses that take place after the trigger event, such as running a script, posting a web request or sending email.

Available Triggers

1 Note - Listed in the order they appear in SmartConsole.

- Before Publish Fired when an administrator publishes a session. The SmartTask passes the sessions meta-data (publishing administrator, domain information and session name) to the action. If the local Management API server is available, the session changes about to be published are formatted as a response to the "show changes" API.
- After Publish Fired after an administrator successfully publishes a session. The SmartTask passes the same information to the action as the **Before Publish** trigger.
- Before Install Policy Fired before a policy is installed. The SmartTask provides the action information related to the policy installation task, such as the package to be installed, the administrator who initiated the installation and the task's result. Additionally, it provides details about the policies which are currently installed on each Security Gateway, and the policies scheduled for installation in the current operation.
- After Install Policy Fired after a policy is installed. The SmartTask passes to the action information related to the policy installation task, such as the package installed, the administrator who initiated the installation and the task's result.
- CloudGuard Controller Event Fired when a new log is generated that matches this query in SmartConsole > Logs & Events view > Logs tab:

blade:"CloudGuard IaaS" AND severity:Critical

More Information

The Management Server creates events in this JSON format:

```
{
    "severity": "<VALUE1>",
```

```
"log-description": "<VALUE2>",
    "product": "CloudGuard IaaS",
    "gateway-name": "<VALUE3>",
    "datacenter-name": [
    "<VALUE4>",
    "<VALUE5>",
    "...",
    "<VALUEx>"
    ],
"version": "1.0"
}
```

This is an example script (in the Action field, select Run Script):

```
#!/bin/sh
input=$(echo $1 | base64 --decode)
severity=$(echo $input | jq '.severity')
message=$(echo $input | jq '."log-description"')
gw_name=$(echo $input | jq '."gateway-name"')
dc_name=$(echo $input | jq '."datacenter-name"')
echo -e "Subject: CloudGuard Controller event\r\n\r\nSeverity:
$severity\r\nMessage: $message\r\nData Center: $dc_
name\r\nGateway: $gw_name" | sendmail --domain=acme.com -f no-
reply@acme.com -v admin@acme.com --host=smtp.acme.com >
/dev/null
echo "Email sent"
```

- After Submit Fired after an administrator submits the current session for approval by another administrator (see "Approval Cycle for Sessions (SmartWorkflow and Identity Provider)" on page 131).
- Before Submit Fired immediately before an administrator submits the current session for approval by another administrator (see "Approval Cycle for Sessions (SmartWorkflow and Identity Provider)" on page 131).
- Before Reject Fired immediately before an administrator rejects a submitted session (see "Approval Cycle for Sessions (SmartWorkflow and Identity Provider)" on page 131).
- After Reject Fired after an administrator rejects a submitted session (see "Approval Cycle for Sessions (SmartWorkflow and Identity Provider)" on page 131).
- Before Login Fired immediately before an administrator logs in to SmartConsole.


- After Approve Fired after an administrator approves the session created by another administrator (see "Approval Cycle for Sessions (SmartWorkflow and Identity Provider)" on page 131.
- Before Approve Fired immediately before an administrator approves the session created by another administrator (see "Approval Cycle for Sessions (SmartWorkflow and Identity Provider)" on page 131).

Available Actions

Run Script - Runs a pre-defined Repository Script. The first parameter that the script gets is a path to a file that contains the trigger's data. When the script is not configured to run on the local machine, the trigger's data is passed as Base64 encoded JSON data, which can be decoded to implement custom business logic. However, when the script is configured to run on the local machine, no decoding is needed.

For SmartTasks configured to run with "Before" operation triggers, the repository script can signal whether to abort or continue the operation by printing a JSON object with the "result" and optional "message" fields and then exit with code 0. If the value of the "result" field is "failure" the operation aborts.

For SmartTasks configured to run with other triggers, exit code 0 is treated as success. Any other exit code is treated as failure.



 Web Request - Executes an HTTPS POST web request to the configured URL. The trigger's data is passed as JSON data to the request's payload.

Notes:

- The configured URL must start with HTTPS and the target web server capable of handling such requests.
- For web servers with self-signed SSL certificates, establish trust by specifying the certificate's fingerprint. You can get the fingerprint by clicking **Get Fingerprint** in the SmartTask editor or by viewing the certificate in a web browser.

For SmartTasks configured to run with "Before" operation triggers, the repository script can signal whether to abort or continue the operation by responding with JSON object "result" and optional "message" fields and a status of 200 OK. If the value of the "result" field is "failure" the operation aborts.

For SmartTasks configured to run with other triggers, a "200 OK" return code is treated as success. Any other exit code is treated as failure.

• Send Mail - Sends a configured email.



- Before you select this action, you must configure a **Server** object of type **SMTP Server** that represents your SMTP server.
- You must configure the email template on the Advanced pane.
- You can use this action only for these triggers: After Install Policy, After Submit, After Approve, After Publish, After Reject.

Configuring SmartTask Properties

- 1. Enter a unique name for the SmartTask The name property is required and case sensitive.
- 2. Switch the SmartTask **ON** or **OFF** using the toggle button.
- 3. Optional Enter a description for the SmartTask.
- 4. Select a trigger for the SmartTask.
- 5. Select an action that will happen once the trigger is fired.
- 6. Custom Data You can add additional information to the JSON data sent with the trigger information by adding a JSON object to the **Custom Data** field. The JSON custom data is concatenated to the trigger's payload and passed to the action.
- 7. Optional Add tags for the SmartTask object.

SmartTask Advanced Properties

The available advanced options depend on the action selected on the General tab.

Send Web Request

- **Time-out** Number of seconds before the request times out and the request aborted.
- If the HTTPS request times out Treat the time-out as an error and abort the event or continue normally.
- X-chkp-shared-secret Enter a shared secret that can be used by the target web server to identify the Security Management Server. The value is sent as part of the request in the X-chkp-shared-secret header in the out-going web request.

Run script

- **Time-out** Number of seconds before the request times out and the request aborted.
- If the script fails to run or times-out Treat time-out (or execution failure) as an error and abort the event or continue normally.

Send Email

Enter these email details:

- To
- Cc
- Sender
- Subject
- Attachment
- Body text

You can use the pre-defined options in the "To", "Cc", and "Sender" fields only for administrators that have an email address defined in SmartConsole. You cannot use these fields for administrators that are connected through an Identity Provider.

For administrators that do not have an email address defined in SmartConsole, do one of these:

- Manually enter the applicable email addresses of the administrators, or
- Create a mailing list of the administrators in your email program, and use the mailing list in the relevant field.

For example:

In an "After Session Approve" SmartTask, an administrator reviews and approves a change made by a submitter.

In the Email Configuration fields:

In the "To" field, instead of the pre-defined **Submitter email**" field, enter a mailing list of all the submitters.

In the "Cc" field, instead of the pre-defined "All reviewers" field" enter a mailing list of all the reviewers.

In the "Sender" field, instead of the pre-defined "Reviewer email" field, enter a dummy email, such as "SmartTask@mycompany.com".

For more information about the approval cycle workflow, see "Session Flow for Administrators" on page 125.

Example

Use Case:

A company policy dictates that the publish operation must be used with a service request number as a prefix to the session name before saving any changes to the database, so the administrators can see what the rationale for changing the security policy was.

Procedure:

Add the Validate Session Name Prefix to the Scripts Repository.

1. Save the script in the repository.

Instructions

- a. Click Gateways & Servers > Scripts > Scripts Repository > New (*)
- b. Give the script a name.
- c. In the Content text box, paste the script code below.
- d. Click **OK** to save the script in the repository.

```
Script Code
 #!/bin/bash
 JQ=<mark>${CPDIR</mark>}/jq/jq
 data=`echo $1 | base64 --decode -i`
 # Extracting the required session name prefix for the session
 name based on the input JSON
 sessionNamePrefix=`echo $data | $JQ -r .\"custom-
 data\".\"session-name-prefix\'
 # If there's no input session name prefix, publish is allowed
 if [[ $sessionNamePrefix = "null" ]] || [[ -z
 "$sessionNamePrefix" ]]; then
     printf '{"result":"success"}\n'
     exit 0
 fi
 # Extracting the actual session name
 sessionName=`echo $data | $JQ -r .session.\"session-name\"`
 # Abort the publish if the session doesn't contain a name at
 all
 if [[ $sessionName = "null" ]]; then
     m1="Corporate Policy requires you to use a service
 request number for the session's name prefix."
     m2="For example: ${sessionNamePrefix}######"
     m3="Session name is missing. Please change your session's
 name to meet the requirements and try to publish again."
     printf '{"result":"failure", "message": "%s %s
  %s"}\n' "$m1" "$m2" "$m3"
     exit 0
 fi
```

```
# Abort the publish if the session name doesn't match the
expected prefix
if [[ ! $sessionName == $sessionNamePrefix* ]]; then
    m1="Corporate Policy requires you to use a ticket number
as the session's name."
    m2="For example: ${sessionNamePrefix}###### "
    m2=\{m2// "/ \\"\}
    m3="Please change your session's name to meet the
requirements and publish again."
printf '{"result":"failure","message":"%s %s
%s"}\n' "$m1" "$m2" "$m3"
    exit 0
else
    # Session name matches the expected prefix, publish is
allowed
    printf '{"result":"success"}\n'
    exit 0
fi
```

2. Create a SmartTask to run the session validation script.

Instructions

- a. Go to Manage & Settings > Tasks > SmartTasks > New (*).
- b. Give the new SmartTask a name (you can call it "Validate Session Name Before Publish")
- c. In the **Trigger and Action** section, select from the drop down menu:

Before Publish and Run Script.

- d. In the **Select script from repository** drop down, select the script saved in Step 1.
- e. In the Custom Data field, enter this string:

{"session-name-prefix": "CR"}

• Note - The variable "session-name-prefix" correlates to the variable used at the beginning of the script in Step 1. If these are not identical, this script cannot work and the process fails.

SmartTasks

SmartTask	ଦ 🛛	$\mid \mathbf{x}$
¢.	Validate Session Name Before Publish	
It General Advanced	Enter Object Comment ON Description Run a validation script that ensures that the a session name matches the expected name perfix as described in the Custom Data field. Trigger and Action Before Publish Run Script Select script from repository: Validate Session Name Pre Custom Data ("session-name-prefix": "CR")	
	Add Tag	
	OK Cancel	

- 3. Publish the SmartConsole session.
- 4. Add a network object.
- 5. Publish the changes using the required prefix.

1 Note - If you publish the session without using the prefix, the process fails.

Network Security for IoT Devices

Important - In R81.20 and higher, if you use the IoT Network Security application in the Infinity Portal to configure IoT policies, all objects in the IoT Policy Layer in SmartConsole become read-only. To edit these objects, use only the IoT Network Security application in the Infinity Portal.

Introduction

The complexity of using IoT devices in the modern work environment such as hospitals, industries, and smart-buildings has, at cost, exposed them to ill-natured and harmful cyber attacks. Malicious cyber invasions into IoT devices have caused considerable financial loss to a number of enterprises. In addition to monetary loss and physical damage, these attacks can lead to data breaches, data tampering, ransomware, and even denial of service.

Common IoT devices susceptible to attack:

Smart Buildings/Offices	Healthcare	Industry
HVAC	HVAC	HVAC
Printers, copiers, fax machines	Printers, copiers, fax machines	Printers, copiers, fax machines
Elevators	Elevators	Elevators
Surveillance Cameras	Surveillance Cameras	Surveillance Cameras
Unhardened kiosk connected to a LAN	Unhardened kiosk connected to a LAN	Unhardened kiosk connected to a LAN
Access control points	Access control points	Access control points
Programmable logic controllers (PLCs)	Programmable logic controllers (PLCs)	Programmable logic controllers (PLCs)
Thermostats	Thermostats	Thermostats
Lighting	Lighting	Lighting
Residential smart meters	MRI machines	
Fire alarms	Fire alarms	Fire alarms
N/A	Ultrasound machines	
	C-arms	

Smart Buildings/Offices	Healthcare	Industry		
	Infusion pumps			
	Blood glucose meter			
	Patient monitor			

What makes IoT devices so vulnerable:

- Outdated software, legacy OS, or no OS
- Basic Micro Controllers
- No Security-by-Design
- Lack of device management
- Shadow Devices
- Operational Limitations

Check Point's Infinity for IoT provides comprehensive network security for enterprise IT and IoT devices, smart building devices, industrial IoT, and connected medical equipment in these ways:

- 1. Prevent malicious intents and unauthorized access to IoT devices by analyzing multiple threat indicators from various resources.
- 2. Prevent infected devices from compromising other network elements.
- 3. Minimize the attack surface through internal network segmentation.
- 4. Provide deep insight information per IoT device.
- 5. Uses 3rd party discovery engine for IoT assets discovery.
- 6. Create separated IoT policy layer, using the discovered IoT device's attributes.

Notes:

- Enforcement of IoT assets in the Access Control policy is not supported on Centrally Managed Quantum Spark appliances running Gaia Embedded operating system.
- Check Point also has a cloud-based IoT inspection services called Quantum IoT Protect.

In this service, everything is performed by Check Point software, including the discovery.

See the *Quantum IoT Protect Administration Guide*.

Prerequisites


- Check Point certified IoT Third Party Discovery Service installed on the network with a connection to the Management Server.
- Discovery Service
 - Industrial / Enterprise:
 - Armis
 - Claroty
 - Indegy
 - Ordr
 - ° SAM
 - SCADAfence
 - Medical:
 - Medigate
 - CyberMDX
 - ° Cynerio
- Identity Awareness Web API must be activated on the enforcing Security Gateway (the configuration is done automatically).
- Security Gateway version R80.10 and above

Network Overview

Check Point's Infinity for IoT delivers comprehensive IoT cyber-security by applying granular IoT-based policies. Check Point's IoT protection solution mobilizes hospitals, industries, smart buildings and offices to reduce and even eliminate IoT attacks.

- Identify and analyze IoT devices and traffic
- Deploy IoT policy enforcement points
- Identify and block IoT malicious intents

Network Diagram



Configuring the IoT Third Party Discovery Service

Before Check Point Infinity for IoT can protect IoT devices from malicious attacks, you must configure the IoT Third Party Discovery Service. The IoT Third Party Discovery Service configures a connection between the Check Point Management Server and the IoT Third Party Discovery Engines.

The IoT Third Party Discovery Engines:

- Discover the connected IoT assets (mainly in the Industrial and Healthcare sectors).
- Group the discovered assets into zones.
- Share the discovered assets and the recommended policies with the Check Point Management Server.

To define the IoT Third Party Discovery Service

Step	Instructions
1	Go to SmartConsole > Manage & Settings > Blades > IoT Third Party Discovery Service > Create Controller. The New IoT Third Party Discovery Service window opens.

Step	Instructions				
2	To configure the General tab:				
	 a. Enter the Hostname, Port, and Pre-shared Key. The pre-shared key must be provided by the certified IoT Third Party Discovery Service, and used for authorizing and authenticating the IoT Third Party Discovery Service. b. Click OK. The Certificate Trust window opens. Before verifying, check that the certificate is valid, and that the IoT Third Party Discovery Service is the certified owner. 				
	Infinity for IoT utilizes the Identity Awareness API. For easy activation, select the gateways on which IoT enforcement will be done. To configure the Gateways tab:				
	 Select the enforcing gateway for IoT traffic. 				
	To configure the Policies tab:				
	a. Select the Policy to be applied on the IoT layer.b. Click OK.				
3	Publish the SmartConsole session.				
4	Install Policy.				

Configuring a new IoT Third Party Discovery Service generates a new IoT policy layer on the selected profiles, a new Threat Prevention profile, and a new rule in the Threat Prevention policy.

To create a new IoT Third Party Discovery Service from an existing IoT Third Party Discovery Service

- 1. In SmartConsole, go to the **Object Explorer** pane.
- 2. Right-click an existing IoT Third Party Discovery Service and select New.

Adding IoT Assets to the Policy

After setting up the IoT policy, you can add IoT assets to the policy manually.

The policy is divided into three categories:

Category	Description				
User-Defined	Used by administrators.				

Category	Description
Auto-Generated	Rules generated from network traffic and IoT network patterns.
Cleanup	A set of rules for detected anomalies.

To define an IoT Access Rule

Step	Instructions
1	From Security Policies > Access Control, select the IoT Layer.
2	Click User-Defined Section, and then click the plus sign.
3	In the Source and/or Destination field , click the plus sign > Add new item . The Add new item window opens.
4	Select Import > IoT Controllers , and then select the IoT asset to add to the rule.

Infinity for IoT Logs

Using Check Point's IoT Security Manager, security teams can see detailed IoT device information such as the manufacture's name, model, serial number, and its location. With a thorough log they gain a clearer, contextual understanding about the device's behavior and forensics for event investigation.

Example 1 - Log Search by IoT Asset Information

Advanced log search using the enriched log data to simplify log filtering.

	🌍 Objects 🕶	🛛 🕑 Ins	🔮 Install Policy 🌐 Discard Session 👻 🖥 Changes 🏐 Publish						lish	
	General Overview	fw.log \times	+							
GATEWAYS & SERVERS	★ Queries 🛛 🗸	> 0 <	A O All Time •		g File Enterprise IP Ca	mera				
or serveros	Time		. Source Machine Name	Source	Destination Machine	Destination Service	Application Risk Application Name	Access Rule Number	Access Rule Name	Description
			Enterprise IP Camera		Contol Room	172.33.3.22 tcp-high-ports (TCP/8081)		1	Device to Server	tcp-high-ports Traffic Accepted from 172.23.250.163 to 172.33.3.22
	Today, 11:38:52 AM	🎫 🤁 *	Enterprise IP Camera	172.23.250.163	Contol Room	5 172.33.3.22 tcp-high-ports (TCP/8081)		1	Device to Server	tcp-high-ports Traffic Accepted from 172.23.250.163 to 172.33.3.22
SECURITY POLICIES										
~										
LOGS & EVENTS										
∞										
INFINITY SERVICES										
Services										
Ö										
MANAGE & SETTINGS										

Example 2 - Extended Log Data

IoT log data contains enriched information that helps identify the IoT assets in the log.

Network Security for IoT Devices

Log Details				_ 🗆 ×
⊕	Accept Dahua Camera (10.	.10.10.150) accessed time.cloudflare.com (162.159	9.200.123) Today at 1:24:30 P	м
Details Log Ir	Matched Rules	<u> </u>	NAT	~
Origin Time Blade		cm gw-31 ⊙ Today, 1:24:30 PM Firewall IoT	Xlate (NAT) Source IP Xlate (NAT) Source Port Xlate (NAT) Destination P NAT Rule Number	gw-31 (172.23.86.31) 38731 0
Produc Type	tt Family	Sccess	NAT Additional Rule Nu Web Traffic	0
Traffic Source		 Oahua Camera (10.10.10.150) Zhejiang dahua technology ip camer more 		2.asia.pool.ntp.org
Source Source	Zone	43284 Internal	Report Log	Report Log to Check Point
Destina Service Interfa Destina	ce	External ntp-tcp (TCP/123) eth1 time.cloudflare.com (162.159.200.12 et *.ntppool1.lexmark.com	Source Function Source Manufacturer Source Model Source ID	IP camera Zhejiang dahua technology DH-IPC-HDBW2231EP-S-S2 24:52:6A:41:7D:70_6eeb2aac-978
D.F.				

Management High Availability

This chapter descibes the configuration of Management High Availability.

Overview of Management High Availability

High Availability is redundancy and database backup for management servers. Synchronized servers have the same policies, rules, user definitions, network objects, and system configuration settings.

Management High Availability uses the built-in revisions technology and allows the High Availability procedure to synchronize only the changes done since the last synchronization. This provides:

- Real-time updates between peer Management Servers.
- Minimum effect on the Management Server resources.

The first management server installed is the primary. If the primary Security Management Server fails, or is off line for maintenance, the administrator can initiate a changeover, so that the secondary server takes over.



- For High Availability (and Load Sharing) environments for Security Gateways, see the <u>R82 ClusterXL Administration Guide</u>.
- For High Availability environments for Endpoint Security, see the <u>R82 Harmony</u> <u>Endpoint Security Server Administration Guide</u>.

The High Availability Environment

A Management High Availability environment includes:

- One Active Security Management Server
- One or more Standby Security Management Server

For full redundancy, the active management server at intervals synchronizes its database with the secondary server or servers.

Active vs. Standby

In a standard High Availability configuration there is one Active server at a time. The administrator uses the Active server to manage the High Availability configuration. The Active server automatically synchronizes the standby server(s) at regular intervals. You can open a Standby server only in Read Only mode. If the Active server fails, you can initiate a changeover to make a Standby server become the Active server. If communication with the Active server fails, there may be more than one Active server. This is called Collision Mode.

Primary Server vs. Secondary Server

The sequence in which you install management servers defines them as Primary or Secondary. The first management server installed becomes the Primary active server. When you install more Security Management Servers, you define them as Secondary. Secondary servers are Standby servers by default.

Important notes about backing up and restoring in Management High Availability environment:

- To back up and restore a consistent environment, make sure to collect and restore the backups and snapshots from all servers in the High Availability environment at the same time.
- Make sure other administrators do not make changes in SmartConsole until the backup operation is completed.

For more information:

- About Gaia Backup and Gaia Snapshot, see the <u>R82 Gaia Administration</u> <u>Guide</u>.
- About the "migrate export" and "migrate import" commands, see the <u>R82 CLI Reference Guide</u>.
- About the "mds_backup" and "mds_restore" commands, see the <u>R82 CLI</u> <u>Reference Guide</u>.
- About Virtual Machine Snapshots, see the vendor documentation.

Configuring a Secondary Security Management Server in SmartConsole

In the SmartConsole connected to the Primary Security Management Server, create a Check Point Host object for the Secondary Security Management Server. After you publish the SmartConsole session, synchronization starts between the Primary and Secondary Security Management Servers.

To configure the Secondary Security Management Server in SmartConsole:

- 1. Connect with SmartConsole to the Primary Security Management Server.
- In the Object Explorer, click New > More > Network Object > Gateways and Servers > Check Point Host.
- 3. In the **General Properties** page, enter a unique name and IP address for the Secondary Security Management Server.
- 4. In the **Software Blades** section, go to the **Management** tab, and select **Network Policy Management**.

This automatically selects the **Secondary Server**, **Logging and Status**, and **Provisioning**.

- 5. Create the SIC trust between the Secondary Security Management Server and the Primary:
 - a. Click Communication.
 - b. Enter the SIC Activation Key of the secondary server.
 - c. Click Initialize.
 - d. Click Close.
- 6. Click OK.
- 7. Publish the SmartConsole session to save these session changes to the database.

The initialization and synchronization between the Security Management Servers start.

- 8. Monitor these tasks in the Task List, in the SmartConsole System Information area. Wait for the Task List to show that a full sync has completed.
- 9. Open the **High Availability Status** window and make sure there is one Active Security Management Server, and one Standby Security Management Server.
- 10. For each Security Gateway / Cluster, open the Security Gateway / Cluster object > go to **Fetch Policy**, click **Add**, and add the Secondary Security Management Server.

Configuring a Secondary Security Management Server in SmartConsole

 Note - If you create an administrator on the Primary Security Management Server through cpconfig, the administrator cannot log in to SmartConsole of the Secondary Management Server until full synchronization from the Primary to the Secondary server is performed.

Synchronizing Active and Standby Servers

At intervals, the Active server synchronizes with the standby server or servers, and when you publish the SmartConsole session. Sessions that are not published are not synchronized.

Monitoring High Availability

The **High Availability Status** window shows the status of each Security Management Server in the High Availability configuration.

To see the server status in your High Availability environment:

- 1. Open SmartConsole and connect to a primary or secondary server.
- 2. On the Menu, click High Availability.

The High Availability Status window opens.

For the management server and its peer or peers in the High Availability configuration, the **High Availability Status** window shows:

- A Warning or Error message The message shows if there is a problem between the High Availability peers.
- Connected To The server that SmartConsole is connected to. Also, the High Availability mode of the server (Active or Standby), and the synchronization status and actions of the server.
- Peers The servers that the connected server sees. Also, the High Availability mode of each server (Active or Standby), and the synchronization status and actions of each server.

Monitoring Synchronization Status and Actions

Status messages can be general, meaning that they apply to the full system, or they can apply to a specified active or standby server. General messages show in the yellow overview banner.

General Status messages in overview banner	Description
	The database of the primary Security Management Server is identical with the database of the secondary.
Some servers could not be synchronized	A communication issue prevents synchronization, or some other synchronization issue exists.
	The active and standby servers are not communicating.

General Status messages in overview banner	Description		
Communication Problem	Some services are down or cannot be reached.		
Collision or HA conflict	More than one management server configured as active. Two active servers cannot sync with each other.		

When connected to a specified *active* management server:

Status window area:	Peer Status	Additional Information
Connected to:	Active	SmartConsole is connected to the active management server.
Peers	Standby	 The peer is in standby. The message can also show: Sync problem, last time sync Synchronized successfully. Last sync time: <time></time> No communication
	Not communicating, last sync time	
	Active	A state of collision exists between two servers both defined as active.

When connected to a specified *Standby* Management Server:

Status window area:	Peer Status	Description
Connected to:	Standby	Also shows: last sync time.
Peers	Active	 The peer is on standby. The message can also show: No communication, last sync time OK., last sync time: <time></time> Sync problem, last sync time (in any direction)
	Standby <i>or</i> Unknown	Can also show: no communication.

Changing a Server to Active or Standby

The Active server synchronizes with the Standby server or servers at intervals, and when you publish the session. Sessions that are not published are not synchronized.

Changeover between the primary (active) and secondary (standby) management server is not automatic. If the Active fails or it is necessary to change the Active to a Standby, you must do this manually. When the management server becomes Standby it becomes Read Only, and gets all changes from the new Active server.

When you initiate changeover, all public data is synchronized from the new Active to the new Standby server after the Standby becomes Active. Data from the new Active overrides the data on the new Standby. *Unpublished* changes are not synchronized.

Best Practice - We recommend that you publish the SmartConsole session before initiating a changeover to the Standby Security Management Server.

To Interchange the Active and Standby

- 1. Connect with SmartConsole to the Standby Security Management Server.
- 2. Click the Menu button and select High Availability.

The High Availability Status window opens.

3. Use the Action buttons to change the Standby server to Active.

This changes the previous Active server to Standby.

Working in Collision Mode

You can make more than one server Active. You may need to do that if there is no connectivity to the primary. When you change the Standby to Active, it becomes Active without telling the current Active server to become Standby. This is known as *collision mode*. You can later change one of the Active servers to Standby, and return to the standard configuration.

When in collision mode, the Active servers do not sync even if they have network connectivity. When you change one of them to Standby, sync starts and overwrites the data on the Standby server with the remaining Active data.

Changeover Between Active and Standby

Changeover between the primary (active) and secondary (standby) management server is not automatic. If the Active fails or it is necessary to change the Active to a Standby, you must do this manually. When the management server becomes Standby it becomes Read Only, and gets all changes from the new Active server.

High Availability Troubleshooting

These error messages show in the **High Availability Status** window when synchronization fails:

Not Communicating

Solution:

- 1. Check connectivity between the servers.
- 2. Test SIC.

Collision or HA Conflict

More than one management server is configured as active.

Solution:

1. From the main SmartConsole menu, select Management High Availability.

The High Availability Status window opens.

2. Use the Actions button to set one of the active servers to standby.

Warning - When this server becomes the Standby, all its data is overwritten by the active server.

Sync Error

Solution:

Do a manual sync.

Unlocking the Administrator

In a High Availability environment, if an administrator is locked on the Standby Management Server, the administrator is not locked and does not appear as locked on the Active Management Server. Therefore, you cannot unlock the administrator on the Active Management Server.

To unlock the administrator:

Use the API command unlock-administrator on the Standby Management Server. See the <u>Check Point Management API Reference</u>.

Environments with Endpoint Security

Environments that include Endpoint Security require additional steps and information.

For details, see *High Availability* in the <u>*R82 Harmony Endpoint Security Server Administration</u></u> <u><i>Guide*.</u></u>

High Availability Disaster Recovery

The first Management Server installed is the Primary Server and all servers installed afterwards are Secondary Servers. The Primary Server acts as the synchronization master. When the Primary server is down, secondary servers cannot synchronize their databases until a Secondary is promoted to Primary and the initial sync completes.

If the Primary Management Server becomes permanently unavailable:

Promote the Secondary Management Server to Primary, and create a new Primary Server with the IP address of the original Primary Server.

Step	Instruction
1	Change the Secondary Management Server from Standby to Active.
2	Promote the Secondary Management Server to be Primary (no need to remove instances of the old Primary Management object and install database). Before you start - Make sure that the Primary Server is offline.
	 a. Set the Secondary Server to Active. b. On the Secondary Management Server that you will promote, run: #\$FWDIR/bin/promote_util #cpstop c. Remove the \$FWDIR/conf/mgha* files. They contain information about the current Secondary settings. These files will be recreated when you start the Check Point services.
	 d. Make sure you have a mgmtha license on the newly promoted server. Note - All licenses must have the IP address of the promoted Security Management Server.
	 e. Run cpstart on the promoted server. f. Open SmartConsole, and: i. Remove all instances of the old Primary Management object. To see all of the instances, right-click the object and select Where Used. i. Note - When you remove the old Primary Management Server, all previous licenses are revoked. ii. Install database.
3	Install the new Secondary Management Server with the IP of the old Primary Management Server.
4	Reset SIC and create SIC to the new Secondary Management Server

To switch back to the original setup (to set the original Primary Management Server as the Primary Management Server again):

Step	Instruction	
1	Change the new Secondary Management Server from Standby to Active.	
2	 Promote the new Secondary Management Server to be the Primary Management Server. Promote the Secondary Management Server to be Primary (no need to remove instances of the old Primary Management object and install database). Before you start - Make sure that the primary server is offline. 	
	 a. Set the Secondary Server to Active. b. On the Secondary Management Server that you promote, run: #\$FWDIR/bin/promote_util #cpstop c. Remove the \$FWDIR/conf/mgha* files. They contain information about the current Secondary settings. These files will be recreated when you start the Check Point services. d. Make sure you have a mgmtha license on the newly promoted server. Note - All licenses must have the IP address of the promoted Security Management Server. e. Run cpstart on the promoted server. f. Open SmartConsole, and: Remove all instances of the old Primary Management object. To see all of the instances, right-click the object and select Where Used. Note - When you remove the old Primary Management Server, all previous licenses are revoked. i. Install database. 	
3	Install the new Secondary Management Server with the IP of the old Primary Management Server.	
4	Reset SIC and create SIC to the Secondary Management Server	
	rtant - Check Point product licenses are linked to IP addresses. At the end of the ter recovery you must make sure that licenses are correctly assigned to your ers	

Compliance

The Check Point Compliance blade is a dynamic solution that continuously monitors the Check Point security infrastructure. The blade uses the Continuous Compliance Monitoring (CCM) technology to examine Security Gateways, Software Blades, policies, and configuration settings against an extensive database of regulatory standards and security best practices. The blade suggests corrective measures to correct any security issues.

The Compliance blade performs these automatic scans:

- Daily One automatic scan per day, to find changes to gateway and policy configurations made with CLI or scripts.
- SmartConsole changes Automatic scan that detects when an administrator changes objects that have an effect on Security Gateway or policy configuration (the scan occurs after you publish the changes.)

You can also run manual scans.

To enable the Compliance blade on your Security Management Server:

1. In SmartConsole, go to the **Gateways & Servers** view, and double-click on the Security Management Server object.

The Security Management Server editor opens.

- 2. In the General Properties page, go to Management, and select Compliance.
- 3. Click OK.

To view the Compliance dashboard:

1. In SmartConsole, go to the Logs & Events view, and click + sign to open a new tab.

The New Tab opens.

2. Click Compliance.

The Compliance View

The Compliance view includes 5 widgets:

- Security Best Practices
- Gateways
- Blades

- Action Items and Messages
- Regulatory Compliance

The Compliance Scoring System

The Compliance blade calculates a numeric score for each best practice test for the organization Security Gateways, Software Blades, and regulations. The score is the average of the test results for each object examined.

Security Score in % Comments Status 0-50 Poor 0 = non-compliantMedium 50-75 Good 75-99 Secure 100 Compliant N/A Not Appears when: Applicable The applicable Software Blade is not installed on the Security Management Server. Or The Security Gateway does not support the examined feature.

This is the Check Point Compliance blade scoring system:

This chapter explains how to work with each Compliance view. For details about system requirements, troubleshooting and debugging, see <u>sk120256</u>.

The Security Best Practices Compliance View

The Security Best Practices Compliance view displays status information for each best practice.

The top table shows these details related to the best practice:

- Active Select to activate the best practice test. Clear to deactivate it.
- Blade Blade related to this best practice.
- ID Check Point Compliance ID assigned to the best practice.
- Name Name and brief description of the regulatory requirement related to the best practice.
- Status Poor, Medium, Good, Secure, or N/A. We recommend that you resolve "Poor" status items immediately.

The bottom section shows these items for the selected best practice test:

- **Description** Detailed description of the best practice test.
- Action Item Steps required to become compliant, including alternative scenarios.
- Dependency Shows when the selected best practice is dependent on another best practice. This test is only performed if the other best practice is compliant.
- Relevant Objects Objects related to the selected best practice test and their status. You can activate or deactivate the selected best practice test for specified objects (this section shows only when the best practice is applicable to specific objects.)
- Relevant Regulatory Requirements Link to a list of all the regulatory standards which are applicable to the best practice.

To search for a certain value, enter a string in the search box:

ecui	rity Best I	Practices	HTTPS Scrouping: -No Grouping- • + New Scale K Z Delete		
ctive	Blade /	ID /	Name	Status	
1	Applicati	APP 127	Check that the HTTPS Validation on the Application Control blade drops traffic from servers with Untrusted Server Certificates	Good	
1	Applicati	APP 129	Check that the HTTPS Validation on the Application Control blade drops traffic from servers with Expired Server Certificates	Good (
1	Applicati	APP128	Check that the HTTPS Validation on the Application Control blade drops traffic from servers with Revoked Server Certificates	Secure	
V	🗰 Firewall	FW164	Check that HTTPS Inspection is enabled on each Gateway	ETT Poor	
1	🗳 URL Filt	URL 142	Check that the HTTPS Validation on the URL Filtering blade drops traffic from servers with Untrusted Server Certificates	Good (
1	🗳 URL Filt	URL144	Check that the HTTPS Validation on the URL Filtering blade drops traffic from servers with Expired Server Certificates	Good	
7	GURL Filt	URL143	Check that the HTTPS Validation on the URL Filtering blade drops traffic from servers with Revoked Server Certificates	Secure	

To search for a certain parameter in a specific field, enter: field name:string

Active	Blade /	ID /	Name	Status
1	Firewall	FW102	Check that Anti-Spoofing has been activated on each Gateway	ED Poor
V	Firewall	FW103	Check that Anti-Spoofing is set to Prevent on each Gateway	ED Poor
	🗰 Firewall	FW107	Check that there is an additional log server defined for each Gateway for the storage of Firewall logs	Poor
	Firewall	FW150	Check the Expiration settings for User Accounts	Poor
-	Firewall	FW153	Check that each rule has a Comment defined	Poor
-	Firewall	FW156	Check the Expiration settings for Administrator Accounts	Poor
1	Firewall	FW164	Check that HTTPS Inspection is enabled on each Gateway	Poor
1	Firewall	FW108	Check that Firewall runs a script before deleting old log files	I Medium
1	Firewall	FW116	Check that NAT/PAT is enabled in the Gateway Properties	💷 🗋 Medium
1	Firewall	FW143	Check the Hit Count data configuration	Medium
1	🗰 Firewall	FW105	Check that each Policy has defined Track settings	Good (
1	Firewall	FW119	Check that no expired rules exist in the Access Policy	Good Good
V	Firewall	FW101	Check that 'Clean up Rule' is defined in Access Policy	Secure Secure
V	🗰 Firewall	FW106	Check on each Gateway that Firewall logs are being saved on a log server	Secure Secure
1	Firewall	FW109	Check the Capacity Optimization of each Gateway	Secure Secure
V	Firewall	FW110	Check that there are alerts to monitor the available disk space for the Firewall logs	Secure Secure
V	Firewall	FW111	Check the minimum threshold for the available disk space alert for the Firewall logs	Secure Secure
1	Firewall	FW112	Check that an Available Disk Space alert type has been defined for the Firewall Logs	Secure Secure
v	Firewall	FW113	Check that older Firewall log entries could be deleted if needed	Secure Secure
1	Firewall	FW114	Check that Firewall logs are only deleted when available disk space reaches a minimum level	Secure Secure
1	Firewall	FW115	Check that 'VPN packet handling errors' are being logged	Secure Secure

To group results, select Blade or Status in the grouping field;

vpn	🙁 Grouping:No Grouping- 🛛 🛨 New 🖄 Ec	lit 🗙 Delete
	No Grouping	
	Туре	
	Blade	
	Status	

To sort search results by a certain field, click the field header.

Creating User-Defined Best Practices

You can define your own, custom Security Best Practices based on organizational security requirements.

To create a new Firewall Security Best Practice:

- 1. In the 'Compliance tab > Security Best Practices pane .> click See All.
- 2. Click New, and select Firewall Best Practice.

The New Firewall Best Practice window opens.

- 3. Enter the Name and Description for this best practice.
- 4. Enter the Action Item generated by this best practice.
- 5. In the **Best Practice Rule Definition** section, enter the rule matching criteria in the table cells. A Security Best Practice match occurs when all table cells match one or more rules in the Rule Base (Logical AND).

- a. **Hit Count** Select a hit count level. A match occurs when the hit count for a rule is equal to or exceeds the specified hit count level. For example: To check the Rule Base for unused rules, you can select **Hit Count Zero**.
- b. Name
- c. Source Select one or more source objects.
- d. Destination Select one or more destination objects.
- e. VPN Select one or more VPN communities.
- f. Services & Applications Select one or more services or applications.
- g. Action The action which the rule triggers.
- h. Track The tracking method for the rule.
- i. Install On Security Gateways / Security Clusters to which the rule applies.
- j. Time Select the times at which the rule applies.
- k. Comment Enter a comment if necessary.
- Optional: click Advanced Settings to select the percentage of the Rule Base to scan and the direction of scan (Top or Bottom). For example, select Bottom 30% to scan 30% of the Rule Base starting from the bottom (last rule in the Rule Base).
- Note You can right-click a cell, and select Negate Cell to exclude the cell from matching. This feature is not available in the Name and Comment cells.
- 6. In the Best Practice Scoring section configure these settings:
 - a. Violation Definition Define if a match occurs when the best practice is matched by a rule or not. Select one of these options:
 - Rule found A match occurs when the best practice is matched by a rule in the Rule Base.
 - Rule not found A match occurs when the best practice is not matched by a rule in the Rule Base.

Select the level of **Tolerance** - A violation occurs when there are more than the specified number of matches (Default = 0). For example, if the tolerance is set to 0, the Compliance Blade creates a violation when the first match occurs. If the tolerance is set to 3, the Compliance Blade creates a violation when the fourth match occurs. The **Tolerance** option applies only to the **Rule found** option.

- b. Rule Index Display Criteria Define when the Rule Index (rule number) shows in the Relevant Objects pane in the Security Best Practices view. This lets you easily see which rules cause or prevent violations:
 - Display rules that match Shows rules that match the criteria specified in a Security Best Practice.
 - Display rules that don't match Shows rules that do not match the criteria specified in a Security Best Practice.
 - **Don't display rules** Does not show the rule.
- 7. Click OK.

The new best practice is added to the list of best practices.

8. Publish your changes.

To create a new Gaia OS Security Best Practice:

- 1. In the 'Compliance tab > Security Best Practices pane .> click See All.
- 2. Click New, and select Gaia OS Best Practice.

The new Gaia OS Best Practice window opens.

- 3. Enter the Name and Description for this best practice.
- 4. Enter the Action Item generated by this best practice.
- 5. Enter the **Practice Script** to run on the Security Gateways or load the script from a file.
- 6. Enter the **Expected Output** If the script output is equal to the Expected Output, the best practice status is secure.
- 7. Click OK.

The new best practice is added to the list of best practices.

8. Publish your changes.

Best Practice - We recommend that you run a manual scan after you create a new Security Best Practice. The scan reevaluates the Compliance status, to reflect any configuration changes. To do a manual scan . go to the Manage & Settings view > Blades > Compliance > Settings > click the Rescan button. You cannot perform any actions in the Compliance tab while the scan runs.

Activating and Deactivating Best Practice Tests

You can activate or deactivate enforcement of best practices by test, by Security Gateway, by Software Blade or by other objects. Activation changes are applied after the next scan.

By default, all best practice tests are active.

To deactivate a best practice for the entire organization:

- 1. Go to the **Security Best Practices** view > and select a best practice.
- 2. Right-click and select **Deactivate**.

The Expiration Details window opens.

- 3. Select **Never** or enter an expiration date. If you select an expiration date, the best practice test is automatically activated on that date.
- 4. In the **Comment** box, explain why it is necessary to deactivate this Compliance test.

To activate a best practice test that is not currently active:

 Go to the Security Best Practices view, select a best practice, right-click and select Activate.

Or

 Go to the Manage & Settings > view > Blades > Compliance > Inactive Objects > Inactive Security Best Practices > select the applicable security best practice and click Remove.

To deactivate a best practice for a specific Security Gateway:

- 1. Go to the Manage & Settings > view > Blades > Compliance > Inactive Objects.
- 2. In the Inactive Gateways section, click Add.
- 3. Enter or select a Security Gateway or a Security Cluster.
- Note To activate the best practice for the Security Gateway, select the Security Gatewayand click Remove. When prompted, click Yes.

To deactivate a best practice for a specific object:

- 1. Go to the Manage & Settings > view > Blades > Compliance > Inactive Security Best Practices on Specific Objects.
- 2. In the Inactive Gateways section, click Add.
- 3. Enter or select a Security Gateway or a Security Cluster.
- Best Practice We recommend that you run a manual scan after you activate or deactivate best practice tests. The scan reevaluates the compliance status, to reflect any configuration changes. To do a manual scan, go to the Manage & Settings view > Blades > Compliance > Settings > click the Rescan button. You cannot perform any actions in the Compliance tab while the scan runs.

The Gateways View

This widget displays security status of the Security Gateway - the five Security Gateways with the highest Compliance scores, lowest Compliance scores, or a predefined set of Favorites. To see the results of all Security Gateways, click **See All**

To see the best practices which are applicable to a specific Security Gateway / Security Cluster, click the specific Security Gateway / Security Cluster.

The top table shows these details related to the best practice:

- Active Select to activate the best practice test. Clear to deactivate it.
- Blade Blade related to this best practice.
- ID Check Point Compliance ID assigned to the best practice.
- Name Name and brief description of the regulatory requirement related to the best practice.
- Status Poor, Medium, Good, Secure, or N/A. We recommend that you resolve "Poor" status items immediately.

The bottom section shows these items for the selected best practice test:

- Description Detailed description of the best practice test.
- Action Item Steps required to become compliant, including alternative scenarios.
- Dependency Shows when the selected best practice is dependent on another best practice. This test is only performed if the other best practice is compliant.
- Relevant Objects Objects related to the selected best practice test and their status. You can activate or deactivate the selected best practice test for specified objects (this section shows only when the best practice is applicable to specific objects.)
- Relevant Regulatory Requirements Link to a list of all the regulatory standards which are applicable to the best practice.

The Blades View

This widget displays the security status by Software Blade - the average scores for the five Software Blades with the highest number of security best practices implemented. To see the result for a specific Software Blade, click it. To see the results for all Software Blades, click **See All**

The top table shows these details related to the best practice:

- Active Select to activate the best practice test. Clear to deactivate it.
- Blade Blade related to this best practice.
- ID Check Point Compliance ID assigned to the best practice.
- Name Name and brief description of the regulatory requirement related to the best practice.
- Status Poor, Medium, Good, Secure, or N/A. We recommend that you resolve "Poor" status items immediately.

The bottom section shows these items for the selected best practice test:

- Description Detailed description of the best practice test.
- Action Item Steps required to become compliant, including alternative scenarios.
- Dependency Shows when the selected best practice is dependent on another best practice. This test is only performed if the other best practice is compliant.
- Relevant Objects Objects related to the selected best practice test and their status. You can activate or deactivate the selected best practice test for specified objects (this section shows only when the best practice is applicable to specific objects.)
- Relevant Regulatory Requirements Link to a list of all the regulatory standards which are applicable to the best practice.

The Action Items and Messages View

When a Best Practice test finds a deficiency, the Check Point Compliance blade automatically generates an Action Item. The Action Item shows a helpful description for the corrective measures to take in order to amend the deficiency. You can assign a due date to an Action Item and monitor corrective steps. Due dates are not assigned to Action Items when they are generated. When you complete the corrective steps, the Check Point Compliance blade deletes the Action Item after the next scan.

This widget has 3 sections:

Action Items

This widget displays the updated status of pending action items for your organization:

- Upcoming items Action items whose due dates is in the next 30 days.
- Future items Action items whose due dates is after more than 30 days.
- Unscheduled items Action items without defined due dates.
- **Overdue items** Action items that are overdue.

Best Practice - Resolve overdue action items immediately

To open the action items for a status category, click Action Items:

In the top table, see these details related to the action item:

- **Due Date** Optionally assigned due date for resolving this Action Item. A due date is not automatically assigned when an Action Item is generated.
- Blade Blade related to the applicable best practice.
- ID Check Point Compliance ID assigned to the applicable best practice.
- Name Name and brief description of the regulatory requirement related to the applicable best practice.
- **Status** Poor, Medium, Good, Secure, or N/A. We recommend that you resolve "Poor" status items immediately.

In the bottom section, you can see these items for the selected action item:

- Action Item Description Steps required to become complaint.
- **Due Date** Optionally assigned due date for resolving this Action Item.

- **Dependency** Shows when the selected best practice is dependent on another best practice. This test is only performed if the other best practice is compliant.
- Relevant Objects Objects related to the selected best practice test and their status. You can activate or deactivate the selected best practice test for specified objects (this section shows only when the best practice is applicable to specific objects.)
- Relevant Regulatory Requirements Link to a list of all the regulatory standards which are applicable to the best practice.
- Alert Messages

Alerts are generated when a configuration change causes Compliance status degradation. To see all alert messages, click **Security Alerts**.

System Messages

System Message inform about system issues related to the Compliance, for example, Compliance package update. To see all system messages, click **System Messages**.

To assign a due date to an Action Item:

- In SmartConsole. go to the Logs & Events view > Compliance tab > Action Items and Messages > Pending Action Items > Unscheduled items.
- 2. Select an Action Item.
- 3. In the Action Item Description section, click Schedule Now. If the Action Item already has an assigned due date, click the date link to change it.
- 4. In the window that opens, enter or select a due date and click OK.

The Regulatory Compliance View

This widget displays Compliance statistics for selected regulatory standards:

- The number of regulatory requirements examined for each regulatory standard.
- Average Compliance scores.

To select the regulatory standards displayed:

- 1. Click this icon ³ in the top right corner of the **Regulatory Compliance** pane: .
- 2. In the Select Regulations and Standards window, select the standards to show in the Overview.

To see the compliance score for all regulatory requirements, click See All.

To see details of a specific standard, click the standard. The top table shows these items:

- **ID** Check Point Compliance ID assigned to the best practice.
- Status Poor, Medium, Good, Secure, or N/A. We recommend that you resolve "Poor" status items immediately.
- Name Name and brief description of the regulatory requirement.

The bottom section shows these items:

- Description Detailed description of the best practice test.
- Relevant best practices Applicable best practice for the selected requirement, and their Compliance status.
- Relevant objects Objects related to the selected best practice test and their status. You can activate or deactivate the selected best practice test for specified objects (this section shows only when the best practice is applicable to specific objects.)

You can select the regulatory standards that are applicable to your organization. By default, all supported regulatory standards are active.

To activate or deactivate regulatory standards:

1. Go to the Manage & Settings view > Blades > Compliance > Settings.

The Settings window opens.

- 2. In the Active Regulations section, select / clear the applicable regulatory standards.
- 3. Publish you changes.

To import a regulatory standard to SmartConsole:

- 1. Save the applicable regulatory standard locally in an XML file.
- Go to the Manage & Settings view > Blades > Compliance > Settings.
 The Settings window opens.
- 3. Go to the Active Regulations section and click Actions > Import.
- 4. Browse to the XML file you want to import, and click **Open**.
 - The regulation now appears in the list of **User-defined Regulations**.
- 5. Double-click the regulation.

The regulation window opens.

6. Click Save.

The process may take a few minutes to complete.

- 7. Publish your changes.
- Best Practice We recommend that you run a manual scan after you make changes to the regulatory standards list. The scan reevaluates the compliance status, to reflect any configuration changes. To do a manual scan, click the Rescan button in the Engine Status section. You cannot perform any actions in the Compliance tab while the scan runs.

Creating Reports

You can generate a report to show a summary of the Compliance status or a report on the implementation of a specific regulatory standard.

To create a report:

1. In SmartConsole, go to the Logs & Events view, and click the + sign to open a New Tab..

A New Tab opens.

- 2. Select the **Reports** view.
- 3. From the displayed list, select **Compliance Blade**.
- 4. Click Open.

The report opens.

5. Optional : In the toolbar, go to **Actions** to create reports in the PDF and CSV formats. To find an exported report, go to the **Logs & Events** view > open a **New Tab** > **Archive**.

To create a report per regulation:

- 1. In the Compliance view, go to the Regulatory Compliance pane, and select See All.
- 2. Click the required regulatory standard.
- 3. In the top tool bar, click Generate Report.
- 4. From the top toolbar, you can select to create reports in these output formats:
 - PDF document
 - An email with attached PDF
 - Output to printer
 - HTML output to your browser.

The ICA Management Tool

Overview

In the ICA Management Tool, an administrator can:

- Manage certificates
 - Warning Do not use the ICA Management Tool to change SIC certificates or VPN certificates. Change SIC and VPN certificates in SmartConsole only. Use the ICA Management Tool for user certificate operations only, such as certificate creation.
- Recreate CRLs
- Configure the Internal Certificate Authority (ICA) parameters
- Remove expired certificates

Note - The ICA Management Tool supports TLS.

Check Point ICA is fully compliant with X.509 standards for both certificates and CRLs. See the related X.509 and PKI documentation, and RFC 2459 for more information.

For more information, see sk102837: Best Practices - ICA Management Tool configuration

Connecting to the ICA Management Tool

The ICA Management Tool is disabled by default.

To connect to the ICA Management Tool:

1. In SmartConsole, configure the required administrator and user objects.

You must create a certificate for these administrators and users.

You use this certificate to configure the permitted users in the ICA Management Tool and in the client web browsers.

2. In the command line on the Management Server, add the required administrators and users that are permitted to use the ICA Management Tool.

cpca_client set_mgmt_tool add ...

See "cpca_client set_mgmt_tool" on page 741.

3. In the command line on the Management Server, start the ICA Management Tool.

cpca_client set_mgmt_tool on

See "cpca_client set_mgmt_tool" on page 741.

4. Check the status of the ICA Management Tool:

cpca_client set_mgmt_tool print

See "cpca_client set_mgmt_tool" on page 741.

- 5. Import the administrator's / user's certificate into the Windows Certificate Store:
 - a. Right-click the *.p12 file you saved when you created the required administrator / user, and click Install PFX.

The Certificate Import Wizard opens.

- b. In the Store Location section, select the applicable option:
 - Current User (this is the default)
 - Local Machine
- c. Click Next.
- d. Enter the same certificate password you used when you created the required administrator / user certificate.
- e. Clear Enable strong private key protection.
- f. Select Mark this key as exportable.
- g. Click Next.
- h. Select Place all certificates in the following store > click Browse > select Personal > click OK.
- i. Click Next.
- j. Click Finish.
- 6. In a web browser, connect to the ICA Management Tool:

https://<IP Address of the Management Server>:18265

Important - The fact that the TCP port 18265 is open is not a vulnerability. The ICA Management Tool Portal is secured and protected by SSL. In addition, only authorized administrators and users are allowed to access it using a certificate.

7. A dialog box with this message appears:

```
Client Authentication
```

```
Identification
```

The Web site you want to view requests identification.

Select the certificate to use when connecting.

- 8. Select the appropriate certificate for authenticating to the ICA Management Tool.
- 9. Click OK.
- 10. In the Security Alert dialog box, click Yes.

The ICA Management Tool Portal

Check Point SOFTWARE TECHNOLOGIES LTD. We Secure the Internet.	Internal CA Management Tool
 Manage Certificates Create Certificates Configure the CA Manage CRLs Help 	Search By User Name: Type: Any Not Status: Any Not Serial Number: Not Search Reset
	Manage Operations Revoke selected Remove selected Mail to selected
	3

Item	Pane	Description
1	Menu	Shows a list of operation.
2	Operations	 Manage certificates In this pane, you manage the existing certificates. The window divides into Search attributes configuration and Bulk operation configuration. Create Certificates In this pane, you can create new certificates. Configure the CA In this pane, you can configure the Internal Certificate Authority parameters. You can also view the CA's time, name, and the version and build number of the Security Management Server. Manage CRLs In this pane, you can download, publish, and recreate CRLs.
3	Results	Shows the results of the applied operation. This window consists of a table with a list of certificates and certificate attributes.

User Certificate Management

Internally managed User Certificates can be initialized, revoked or have their registrations removed using the ICA Management Tool. User Certificates of users managed on an LDAP server can only be managed using the ICA Management Tool.

This table shows User Certificate attributes that can be configured using the ICA Management Tool

Attributes	Default	Configurable	Comments
validity	2 years	yes	
key size	2048 bits	yes	Can be set to 4096 bits
DN of User certificates managed by the internal database	CN=user name, OU=users	no	This DN is appended to the DN of the ICA
DN of User certificates managed on an LDAP server		yes	Depends on LDAP branch
KeyUsage	5	yes	Digital signature and Key encipherment
ExtendedKeyUsage	0 (no KeyUsage)	yes	

Modifying the Key Size for User Certificates

If the user completes the registration from the Remote Access machine, the key size can be configured in the **Advanced Configuration** page in SmartConsole.

To configure the key size

- 1. From the Menu, select Global Properties.
- 2. Go to Advanced, and in the Advanced Configuration section, click configure.

The Advanced Configuration window opens.

- 3. Go to the Certificates and PKI properties page.
- 4. Set the new key size for this property: user_certs_key_size.
- 5. Click OK.

You can also change the key size using the <u>Database Tool (GuiDBEdit Tool</u>). Change the key size as it is listed in <code>users_certs_key_size Global Property</code>. The new value is downloaded when you update the site.

Performing Multiple Simultaneous Operations

The ICA Management Tool can do multiple operations at the same time. For example:

- Run an LDAP query for the details of all the organization's employees
- Create a file out of this data, and then use this file to:
 - Start (initialize) the creation of certificates for all employees
 - Send a notification about the new certificates to each of those employees

These operations can be done simultaneously:

- Start (initialize) user certificates
- Revoke user certificates
- Send mail to users
- Remove expired certificates
- Remove certificates for which the registration procedure was not completed

ICA Administrators with Reduced Privileges

The ICA Management Tool supports administrators with limited privileges. These administrators cannot execute multiple concurrent operations, and their privileges include only these:

- Basic searches
- Initialization of certificates for new users

Operations with Certificates

Management of SIC Certificates

SIC certificates are managed using SmartConsole.

Management of Security Gateway VPN Certificates

VPN certificates are managed in the **VPN** page of the corresponding network object. These certificates are issued automatically when the IPSec VPN blade is defined for the Check Point Security Gateway or host. This definition is specified in the **General Properties** window of the corresponding network object.

If a VPN certificate is revoked, a new one is issued automatically.

Management of User Certificates in SmartConsole

The user certificates of users that are managed on the internal database are managed in SmartConsole.

For more information, see *User Certificates* in the <u>*R82 Remote Access VPN Administration</u></u> <u><i>Guide*</u>.</u>

Notifying Users about Certificate Initialization

The ICA Management Tool can be configured to send a notification to users about certificate initialization.

To send mail notifications:

- 1. In the Menu pane, click Configure the CA.
- 2. In the Management Tool Mail Attributes area, configure:
 - The mail server
 - The mail "From" address
 - An optional "To" address, which can be used if the users' address is not know

The administrator can use this address to get the certificates on the user's behalf and forward them later.

3. Click Apply.

Retrieving the ICA Certificate Files

See "cpca_client set_ca_services" on page 738.

Searching for a Certificate

There are two search options:

- A basic search that includes only the user name, type, status and the serial number
- An advanced search that includes all the search fields (can only be performed by administrators with unlimited privileges)

To do a certificate search:

In the Manage Certificates page, enter the search parameters, and click Search.

Basic Search Parameters

- User Name Username string (by default, this field is empty)
- Type Drop-down list with these options:
 - Any (default)
 - *SIC*
 - Gateway
 - Internal User or LDAP user
- Status Drop-down list with these options:
 - Any (default)
 - Pending
 - Valid
 - Revoked
 - Expired
 - Renewed (superseded)
- Serial Number Serial number of the requested certificate (by default, this field is empty)

Advanced Search Attributes

In addition to the parameters of the basic search, specify these parameters:

- Sub DN DN substring (by default, this field is empty)
- Valid From Date, from which the certificate is valid, in the format dd-mmm-yyyy [hh:mm:ss] (for example 15-Jan-2003) (by default, this field is empty)

- Valid To Date until which the certificate is valid, in the format dd-mmm-yyyy [hh:mm:ss] (for example 14-Jan-2003 15:39:26) (by default, this field is empty)
- CRL Distribution Point Drop-down list with these options:
 - Any (default)
 - *No CRL Distribution Point* (for certificates issued before the management upgrade old CRL mode certificates)

The list also shows all available CRL numbers.

The Search Results

The results of a search show in the **Search Results** pane. This pane consists of a table with a list of searched certificate attributes such as:

- (SN) Serial Number The SN of the certificate
- User Name (CN) The string between the first equals sign ("=") and the next comma (",")
- DN
- Status One of these: Pending, Valid, Revoked, Expired, Renewed (superseded)
- The date, from which certificates are valid until the date they expire

• Note - The status bar shows search statistics after each search.

Viewing and Saving Certificate Details

You can view or save the certificate details that show in the search results.

To view and save certificate details

Click on the DN link in the Search Results pane.

- If the status is *pending*, the certificate information together with the registration key shows, and a log entry is created and shows in SmartConsole > Logs & Events > Logs.
- If the certificate was already created, you can save it on a disk or open directly (if the operating system recognizes the file extension)

Removing and Revoking Certificates and Sending Email Notifications

- 1. In the Menu pane, click Manage Certificates.
- 2. Search for a Certificate with set attributes (see "Searching for a Certificate" on the previous page).

The results show in the Search Results pane.

- 3. Select the certificates, as needed, and click one of these options:
 - Revoke Selected revokes the selected certificates and removes pending certificates from the CA's database
 - Remove Selected removes the selected certificates from the CA's database and from the CR

Note - You can only remove expired or pending certificates.

• Mail to Selected - sends mail for all selected *pending* certificate

The mail includes the authorization codes. Messages to users that do not have an email defined are sent to a default address. For more information, see *"Notifying Users about Certificate Initialization" on page 647*.

Submitting a Certificate Request to the CA

There are three ways to submit certificate requests to the CA:

- Initiate A registration key is created on the CA and used once by a user to create a certificate
- Generate A certificate file is created and associated with a password which must be entered when the certificate is accessed
- PKCS#10 When the CA receives a PKCS#10 request, the certificate is created and delivered to the requester

To initiate a certificate

- 1. In the Menu pane, select **Create Certificates > Initiate**.
- 2. Enter a User Name or Full DN, or click Advanced and fill in the form:
 - Certificate Expiration Date Select a date or enter the date in the format ddmmm-yyyy [hh:mm:ss] (the default value is two years from the date of creation)
 - Registration Key Expiration Date Select a date or enter the date in the format dd-mmm-yyyy [hh:mm:ss] (the default value is two weeks from the date of creation)
- 3. Click Go.

A registration key is created and show in the **Results** pane.

If necessary, click **Send mail to user** to email the registration key. The number of characters in the email is limited to 1900.

4. The certificate becomes usable after entering the correct registration key.

To generate a certificate

- 1. In the Menu pane, select Create Certificates > Generate.
- 2. Enter a User Name or Full DN, or click Advanced and fill in the form:
 - Certificate Expiration Date Select a date or enter the date in the format ddmm-yyyy [hh:mm:ss] (the default value is two years from the date of creation)
 - Registration Key Expiration Date Select a date or enter the date in the format dd-mm-yyyy [hh:mm:ss] (the default value is two weeks from the date of creation)
- 3. Enter a password.
- 4. Click Go.
- 5. Save the P12 file, and supply it to the user.

To create a PKCS#10 certificate

- 1. In the Menu pane, select Create Certificates > PKCS#10.
- 2. Paste into the space the encrypted base-64 buffer text provided.

You can also click on Browse for a file to insert (IE only) to import the request file.

- 3. Click Create and save the created certificate.
- 4. Supply the certificate to the requester.

Initializing Multiple Certificates Simultaneously

You can initialize a batch of certificates at the same time.

To initialize several certificates simultaneously

1. Create a file with the list of DNs to initialize.

Note - There are two ways to create this file - through an LDAP query or a non-LDAP query.

- 2. In the Menu pain, go to Create Certificates > Advanced.
- 3. Browse to the file you created.

- To send registration keys to the users, select Send registration keys via email
- To receive a file that lists the initialized DNs with their registration keys, select Save results to file

This file can later be used in a script.

4. Click Initiate from file.

Files created through LDAP Queries

The file initiated by the LDAP search has this format:

- Each line after a blank line or the first line in the file represents one DN to be initialized
- If the line starts with "mail=", the string continues with the mail of the use

If no email is given, the email address will be taken from the ICA's "Management Tool Mail To Address" attribute.

If there is a line with the not_after attribute, then the value at the next line is the Certificate Expiration Date.

The date is given in seconds from now.

If there is a line with the is otp_validity attribute, then the value at the next line is the Registration Key Expiration Date.

The date is given in seconds from now.

Here is an example of an LDAP Search output:

```
not_after
86400
otp_validity
3600
uid=user_1,ou=People,o=intranet,dc=company,dc=com
mail=user_1@company.com
<blank_line>
...
uid=...
```

For more information, see "Configuring Users on an External LDAP Server" on page 217.

Files created through a Simple Non-LDAP Query

It is possible to create a simple (non-LDAP) query by configuring the DN + email in a file using this format:

<email address 1> space <DN 1> ... blank line as a separator ... <email address 2> space <DN 2>

CRL

CRL Management

By default, the CRL is valid for one week. This value can be configured. New CRLs are issued:

- When approximately 60% of the CRL validity period has passed
- Immediately following the revocation of a certificate

It is possible to recreate a specified CRL using the ICA Management Tool. The utility acts as a recovery mechanism in the event that the CRL is deleted or corrupted. An administrator can download a DER encoded version of the CRL using the ICA Management Tool.

CRL Modes

The ICA can issue multiple CRLs. Multiple CRLs prevent one CRL from becoming larger than 10K. If the CRL exceeds 10K, IKE negotiations can fail when trying to open VPN tunnels.

Multiple CRLs are created by attributing each certificate issued to a specified CRL. If revoked, the serial number of the certificate shows in the specified CRL.

The CRL Distribution Point (CRLDP) extension of the certificate contains the URL of the specified CRL. This ensures that the correct CRL is retrieved when the certificate is validated.

CRL Operations

You can download, update, or recreate CRLs through the ICA management tool.

To do operations with CRLs

- 1. In the Menu pane, select Manage CRLs.
- 2. From the drop-down box, select one or more CRLs.
- 3. Select an action:
 - Click Download to download the CRL.
 - Publish the SmartConsole session to renew the CRL after changes have been made to the CRL database.

This operation is done at an interval set by the CRL Duration attribute.

• Click **Recreate** to recreate the CRL.

CA Cleanup

To clean up the CA, you must remove the expired certificates. You can remove the expired certificates manually or automatically.

To manually remove expired certificates:

- 1. Make sure that the time set on the Security Management Server is correct.
- 2. In the Menu pane, select Manage CRLs > Clean the CA's Database and CRLs from expired certificates.

Automatic removal of expired certificates:

- After each restart, all expired certificates are cleaned automatically.
- In addition, an automatic cleaning operation is scheduled to set every 3 weeks, starting from:
 - The first time you turn on the device.
 - Each restart you do on the device.

Configuring the CA

To configure the CA

- 1. In the Menu pane, select Configure the CA.
- 2. Edit the "CA Data Types and Attributes" below as necessary.
- 3. In the **Operations** pane, select an operation:
 - Apply Save and enter the CA configuration settings.

If the values are valid, the configured settings become immediately effective. All non-valid strings are changed to the default values.

- Cancel Reset all values to the values in the last saved configuration.
- **Restore Default** Revert the CA to its default configuration settings.

Entering the string Default in one of the attributes will also reset it to the default after you click **Configure**. Values that are valid will be changed as requested, and others will change to default values.

CA Data Types and Attributes

The CA data types are:

Time-displayed in the format: <number> days <number> seconds, for example: CRL Duration: 7 days 0 seconds

You can enter the values in the format in which they are displayed (<number> days <number> seconds) or as a number of seconds.

- Integer a regular integer, for example: SIC Key Size: 2048
- Boolean the values can be true or false (not case sensitive), for example: Enable renewal: true
- String an alphanumeric string, for example: Management Tool DN prefix: cn=tests

These are the CA attributes, in alphabetical order:

Attribute	Comment	Values	Default
Authorization Code Length	The number of characters of the authorization codes.	min-6 max-12	6
CRL Duration	The period of time for which the CRL is valid.	min-5 minutes max-1 year	1 week
Enable Renewal	For User certificates. This is a Boolean value setting which stipulates whether to enable renewal or not.	true or false	true
Grace Period Before Revocation	The amount of time the old certificate will remain in Renewed (superseded) state.	min-0 max-5 years	1 week
Grace Period Check Period	The amount of time between sequential checks of the <i>Renewed</i> <i>(superseded)</i> list in order to revoke those whose duration has passed.	min-10 minutes max-1 week	1 day
IKE Certificate Validity Period	The amount of time an IKE certificate will be valid.	min-10 minutes max-3 years	1 year
IKE Certificate Extended Key Usage	Certificate purposes for describing the type of the extended key usage for IKE certificates. Refer to RFC 2459.		means no KeyUsage

Attribute	Comment	Values	Default
IKE Certificate Key usage	Certificate purposes for describing the certificate operations. Refer to RFC 2459.		Digital signature and Key encipherment
Management Tool DN prefix	Determines the DN prefix of a DN that will be created when entering a user name.	possible values CN= UID=	CN=
Management Tool DN suffix	Determines the DN suffix of a DN that will be created when entering a user name.		ou=users
Management Tool Hide Mail Button	For security reasons the mail sending button after displaying a single certificate can be hidden.	true or false	false
Management Tool Mail Server	The SMTP server that will be used in order to send registration code mails. It has no default and must be configured in order for the mail sending option to work.		-
Management Tool Registration Key Validity Period	The amount of time a registration code is valid when initiated using the Management Tool.	min-10 minutes max-2 months	2 weeks
Management Tool User Certificate Validity Period	The amount of time that a user certificate is valid when initiated using the Management Tool.	min-one week max-20 years	2 years
Management Tool Mail From Address	When sending mails this is the email address that will appear in the from field. A report of the mail delivery status will be sent to this address.		-
Management Tool Mail Subject	The email subject field.		-

Attribute	Comment	Values	Default
Management Tool Mail Text Format	The text that appears in the body of the message. 3 variables can be used in addition to the text: \$REG_KEY (user's registration key); \$EXPIRE (expiration time); \$USER (user's DN).	Registration Key: \$REG_KEY Expiration: \$EXPIRE	
Management Tool Mail To address	When the send mail option is used, the emails to users that have no email address defined will be sent to this address.		-
Max Certificates Per Distribution Point	The maximum capacity of a CRL in the new CRL mode.	min-3 max-400	400
New CRL Mode	A Boolean value describing the CRL mode.	0 for old CRL mode 1 for new mode	true
Number of certificates per search page	The number of certificates that will be displayed in each page of the search window.	min-1 max- approx 700	approx 700
Number of Digits for Serial Number	The number of digits of certificate serial numbers.	min-5 max-10	5
Revoke renewed certificates	This flag determines whether to revoke an old certificate after it has been renewed. The reason for not revoking this is to prevent the CRL from growing each time a certificate is renewed. If the certificate is not revoked the user may have two valid certificates.	true or false	true
SIC Key Size	The key size in bits of keys used in SIC.	possible values: 1024 2048 4096	2048

Attribute	Comment Values		Default
SIC Certificate Key usage	Key usagecertificate operations. Refer to RFCand		Digital signature and Key encipherment
SIC Certificate Validity Period			5 years
User Certificate Extended Key Usage	Certificate purposes for describing the type of the extended key usage for User certificates. Refer to RFC 2459.		means no KeyUsage
User Certificate Key Size	The key size in bits of the user's certificates.	Possible values: 1024 2048 4096	2048
User Certificate Key usage	Certificate purposes for describing the certificate operations. Refer to RFC 2459		Digital signature and Key encipherment

Certificate Longevity and Statuses

Certificates issued by the ICA have a defined validity period. When period ends, the certificate *expires*.

SIC certificates, VPN certificates for Security Gateways and User certificates can be created in one step in SmartConsole. User certificates can also be created in two steps using SmartConsole or the ICA Management Tool. The two steps are:

- Initialization during this step a registration code is created for the user. When this is done, the certificate status is *pending*
- Registration when the user completes the registration procedure in the remote client. After entering the registration code the certificate becomes *valid*.

The advantages are:

Enhanced security

- The private key is created and stored on the user's machine
- The certificate issued by the ICA is downloaded securely to the client.

Pre-issuance automatic and administrator-initiated certificate removal

If a user does not complete the registration procedure in a given period (two weeks by default), the registration code is automatically removed. An administrator can remove the registration key before the user completes the registration procedure. After that, the administrator can revoke the user certificate.

Explicit or Automatic Renewal of User certificates ensuring continuous User connectivity

A user certificate of type PKCS12 can be renewed explicitly by the user. A PKCS12 certificate can also be set to renew automatically when it is about to expire. This renewal operation ensures that the user can continuously connect to the organization's network. The administrator can choose when to set the automatic revoke old user certificates.

One more advantage is:

Automatic renewal of SIC certificates ensuring continuous SIC connectivity

SIC certificates are renewed automatically after 75% of the validity time of the certificate has passed. If, for example, the SIC certificate is valid for five years. After 3.75 years, a new certificate is created and downloaded automatically to the SIC entity. This automatic renewal ensures that the SIC connectivity of the Security Gateway is continuous. The administrator can revoke the old certificate automatically or after a set period of time. By default, the old certificate is revoked one week after certificate renewal.

Gaia API Proxy


Check Point products support API commands. See the Check Point API Reference.

With the Gaia API Proxy feature on a Management Server, you run the Gaia API commands on managed Security Gateways and Cluster Members:

- 1. An administrator connects with an API Client to a Management Server.
- 2. From the Management Server, an administrator runs the Gaia API commands on managed Security Gateways and Cluster Members.

The Gaia API Proxy feature on the R82 Management Server works with all managed Security Gateways and Cluster Members that support the Gaia API.

Example diagram



Item	Description
1	An API Client
2	A Management Server with the Gaia API Proxy feature
3	A managed Security Gateway
4	A managed ClusterXL
А	Management API communication
В	Gaia API communication

Important - Scalable Platforms (ElasticXL, Maestro, and Chassis) do **not** support this feature (Known Limitation MBS-10832).

Workflow:

1. Run the Management API "login" command to log in to the Management Server

When you work with an API Client, run the Check Point API "login" command to log in to the Management Server (see the <u>Check Point Management API Reference</u>).

Important - The administrator that logs in must have the Run One Time Script permission enabled in the assigned permission profile. See "Assigning Permission Profiles to Administrators" on page 115.

2. Run the Gaia API commands on managed Security Gateways and Cluster Members

The Management API "login" command returns the Session Unique Identifier (SID) token.

In the same API Client, use this SID token in the "X-chkp-sid" field of the Gaia API commands you run on managed Security Gateways and Cluster Members.

Gaia API Syntax:

```
POST https://<IP Address of Management Server>/web_api/gaia-
api/<Gaia API Version>/<Gaia API Command>
```

See the Check Point Gaia API Reference.

The body of the Gaia API command must identify the managed Security Gateway or Cluster Member by one of these parameters:

- Object name
- Object primary IP address
- Object UID

3. The Gaia API Proxy logs in to the specified Security Gateway or Cluster Member

The Gaia API Proxy on the Management Server interprets the Gaia API command and logs in to the specified Security Gateway or Cluster Member.

- a. This login returns the SID for the Security Gateway or Cluster Member.
- b. The Gaia API Proxy uses this SID to run the Gaia API commands.

- c. The Gaia API Proxy saves this SID in its database:
 - The SID timeout is 580 seconds on the Management Server.
 - The SID timeout is 10 minutes on a Security Gateway or Cluster Member.
- 4. The Gaia API Proxy forwards the response from the Security Gateway or Cluster Member to the API client
 - To increase performance, the Gaia API Proxy saves the response in the Gaia API Proxy cache on the Management Server.
 - If the Gaia API Proxy gets the same Gaia API request during the cache timeout, it returns the Gaia API response from its cache and updates the cache.
 - An administrator can configure these cache parameters in the \$FWDIR/api/conf/cache.conf file on the Management Server:
 - Note After you change the \$FWDIR/api/conf/cache.conf file, you must reload the API server configuration with the "api reconf" command in the Expert mode.

Parameter	Accepted Values	Description
timeout	0, or greater	 Specifies the time, after which the next Gaia API command triggers a cache update for that Gaia API command: 0 - The Gaia API proxy does not use cache <integer> - The Gaia API proxy saves the Gaia API responses in its cache for the specified number of seconds (default: 60 seconds)</integer>
total_ gateways	integer	Specifies the number of unique Security Gateways and Cluster Members, from which to save the Gaia API responses.
maximum_ entries	integer	Specifies the number of unique Gaia API commands to save for each Security Gateway and Cluster Member.

Important - The Gaia API Proxy sends Gaia API command over HTTPS. The Access Control policy for the Security Gateway or ClusterXL must explicitly allow HTTPS traffic from the Management Server to the Security Gateway or Cluster Members.

Examples

Gaia API command "show-hostname"

In this example, we identify the managed Security Gateway by the object primary IP address.

Request

```
POST https://<IP Address of Management Server>/gaia-api/show-
hostname
Content-Type: application/json
X-chkp-sid: <Session ID>
{
    "target" : "192.168.1.1"
}
```

Response

```
{
   "command-name" : "show-hostname",
   "response-message" : {
        "name" : "gw-832546"
    }
}
```

Gaia API command "show-interface"

In this example, we identify the managed Security Gateway by the object name.

Request

```
POST https://<IP Address of Management Server>/gaia-
api/v1.4/show-interfaces
Content-Type: application/json
X-chkp-sid: <Session ID>
{
    "target" : "gw-832546",
    "name" : "eth0"
}
```

Response

```
{
   "command-name" : "v1.4/show-interfaces",
   "response-message" : {
      "ipv6-local-link-address": "Not Configured",
      "type": "physical",
      "name": "eth0",
      "ipv6-mask-length": "Not-Configured",
      "ipv6-address": "Not-Configured",
      "ipv6-autoconfig": "Not configured",
      "ipv4-address": "192.168.1.1",
      "enabled": true,
      "comments": "",
      "ipv4-mask-length": "24"
}
```

Gaia API command "show-diagnostics"

In this example, we identify the managed Security Gateway by the object UID.

Request

```
POST https://<IP Address of Management Server>/gaia-
api/v1.4/show-diagnostics
Content-Type: application/json
X-chkp-sid: <Session ID>
{
    "target" : "52048978-c507-8243-9d84-074d11154616",
    "category" : "os",
    "topic" : "disk"
}
```

Response

```
{
  "command-name" : "v1.4/show-diagnostics",
  "response-message" : {
    "to": 3,
    "total": 3,
    "from": 1,
    "objects": [
      {
      "total": "34342961152",
      "partition": "/",
      "used": "5718065152",
      "free": "28624896000"
      },
      {
      "total": "304624640",
      "partition": "/boot",
      "used": "26991616",
      "free": "277633024"
      },
      {
      "total": "34342961152",
      "partition": "/var/log",
      "used": "455684096",
      "free": "33887277056"
      }
    ]
  }
}
```

Testing New SmartConsole Features

You can influence Check Point product development by selecting and testing one or more of the new features listed here.

To test a new SmartConsole feature:

- 1. From the left navigation panel, click Manage & Settings...
- 2. Click Preferences.
- 3. In the Check Point Lab section (at the bottom), select the feature you want to test.
- 4. Publish the SmartConsole session.

Command Line Reference

See the *R82 CLI Reference Guide*.

Below is a limited list of applicable commands.

Syntax Legend for CLI Commands

Whenever possible, this guide lists commands, parameters and options in the alphabetical order.

This guide uses this convention in the Command Line Interface (CLI) syntax:

Character	Description	
ТАВ	<pre>Shows the available nested subcommands: main command → nested subcommand 1 → → nested subsubcommand 1-1 → → nested subsubcommand 1-2 → nested subcommand 2</pre>	
	Example:	
	<pre>cpwd_admin config -a <options> -d <options> -p -r del <options> Meaning, you can run only one of these commands: I This command: cpwd_admin config -a <options></options></options></options></options></pre>	
	<pre>Or this command: cpwd admin config -d <options></options></pre>	
	 Or this command: 	
	- Or this command: cpwd admin config -p	
	 Or this command: 	
	cpwd admin config -r	
	 Or this command: 	
	cpwd_admin del < <i>options</i> >	
Curly brackets or braces { }	Enclose a list of available commands or parameters, separated by the vertical bar . User can enter only one of the available commands or parameters.	

Character	Description
Angle brackets < >	Enclose a variable. User must explicitly specify a supported value.
Square brackets or brackets []	Enclose an optional command or parameter, which user can also enter.

contract_util

Description

Works with the Check Point Service Contracts.

For more information about Service Contract files, see <u>sk33089</u>: What is a Service Contract <u>File?</u>

Syntax

```
contract_util [-d]
   check <options>
   cpmacro <options>
   download <options>
   mgmt
   print <options>
   summary <options>
   update <options>
   verify
```

Parameter	Description
check	Checks whether the Security Gateway is eligible for an upgrade.
<options></options>	See <i>"contract_util check" on page 673</i> .
cpmacro	Overwrites the current cp.macro file with the specified cp.macro file.
< <i>options</i> >	See "contract_util cpmacro" on page 674.
download	Downloads all associated Check Point Service Contracts from the User Center, or from a local file.
<options></options>	See "contract_util download" on page 675.
mgmt	Delivers the Service Contract information from the Management Server to the managed Security Gateways. See "contract_util mgmt" on page 677.
print <options></options>	Shows all the installed licenses and whether the Service Contract covers these license, which entitles them for upgrade or not. See <i>"contract_util print" on page 678</i> .

Parameter	Description
summary <options></options>	Shows post-installation summary. See <i>"contract_util summary" on page 679</i> .
update < <i>options</i> >	Updates Check Point Service Contracts from your User Center account. See <i>"contract_util update" on page 680</i> .
verify	Checks whether the Security Gateway is eligible for an upgrade. This command also interprets the return values and shows a meaningful message. See "contract_util verify" on page 681.

contract_util check

Description

Checks whether the Security Gateway is eligible for an upgrade.

For more information about Service Contract files, see <u>sk33089</u>: What is a Service Contract <u>File?</u>

Syntax

```
contract_util check
  {-h | -help}
  hfa
  maj_upgrade
  min_upgrade
  upgrade
```

Parameter	Description
{-h - help}	Shows the applicable built-in usage.
hfa	Checks whether the Security Gateway is eligible for an upgrade to a higher Hotfix Accumulator.
maj_ upgrade	Checks whether the Security Gateway is eligible for an upgrade to a higher Major version.
min_ upgrade	Checks whether the Security Gateway is eligible for an upgrade to a higher Minor version.
upgrade	Checks whether the Security Gateway is eligible for an upgrade.

contract_util cpmacro

Description

Overwrites the current cp.macro file with the specified cp.macro file, if the specified is newer than the current file.

For more information about the cp.macro file, see sk96217: What is a cp.macro file?

Syntax

contract_util cpmacro /<path_to>/cp.macro

This command shows one of these messages:

Message	Description
CntrctUtils_ Write_cp_macro returned -1	 The contract_util cpmacro command failed: Failed to create a temporary file. Failed to write to a temporary file. Failed to replace the current file.
CntrctUtils_ Write_cp_macro returned 0	The contract_util cpmacro command was able to overwrite the current file with the specified file, because the specified file is newer.
CntrctUtils_ Write_cp_macro returned 1	The contract_util cpmacro command did not overwrite the current file, because it is newer than the specified file.

contract_util download

Description

Downloads all associated Check Point Service Contracts from User Center, or from a local file.

For more information about Service Contract files, see <u>sk33089</u>: What is a <u>Service Contract</u> <u>File?</u>

Syntax

```
contract_util download
    {-h | -help}
    local
        {-h | -help}
        [{hfa | maj_upgrade | min_upgrade | upgrade}] <Service
Contract File>
        uc
        {-h | -help}
        [-i] [{hfa | maj_upgrade | min_upgrade | upgrade}]
<Username> <Password> [<Proxy Server> [<Proxy Username>:<Proxy
Password>]]
```

Parameter	Description
{-h -help}	Shows the applicable built-in usage.
-i	Interactive mode - prompts the user for the User Center credentials and proxy server settings.
local	Specifies to download the Service Contract from the local file. This is equivalent to the "cplic contract put" command (see "cplic contract" on page 758).
uc	Specifies to download the Service Contract from the User Center.
hfa	Downloads the information about a Hotfix Accumulator.
maj_upgrade	Downloads the information about a Major version.
min_upgrade	Downloads the information about a Minor version.
upgrade	Downloads the information about an upgrade.
<username></username>	Your User Center account e-mail address.
<password></password>	Your User Center account password.
<proxy server=""> [<proxy Username>:<proxy Password>]</proxy </proxy </proxy>	 Specifies that the connection to the User Center goes through the proxy server. <proxy server=""> - IP address of resolvable hostname of the proxy server</proxy> <proxy username=""> - Username for the proxy server.</proxy> <proxy password=""> - Password for the proxy server.</proxy> Note - If you do not specify the proxy server explicitly, the command uses the proxy server configured in the management database.
<service contract<br="">File></service>	Path to and the name of the Service Contract file. First, you must download the Service Contract file from your User Center account.

contract_util mgmt

Description

Delivers the Service Contract information from the Management Server to the managed Security Gateways.

For more information about Service Contract files, see <u>sk33089</u>: <u>What is a Service Contract</u> <u>File?</u>

Syntax

contract_util mgmt

contract_util print

Description

Shows all the installed licenses and whether the Service Contract covers these license, which entitles them for upgrade or not.

This command can show which licenses are not recognized by the Service Contract file.

For more information about Service Contract files, see <u>sk33089</u>: What is a Service Contract <u>File?</u>

Syntax

```
contract_util [-d] print
  {-h | -help}
  hfa
  maj_upgrade
  min_upgrade
  upgrade
```

Parameter	Description
{-h -help}	Shows the applicable built-in usage.
-d	Shows a formatted table header and more information.
hfa	Shows the information about Hotfix Accumulator.
maj_upgrade	Shows the information about Major version.
min_upgrade	Shows the information about Minor version.
upgrade	Shows the information about an upgrade.

contract_util summary

Description

Shows post-installation summary and whether this Check Point computer is eligible for upgrades.

Syntax

```
contract_util summary
hfa
maj_upgrade
min_upgrade
upgrade
```

Parameter	Description
hfa	Shows the information about Hotfix Accumulator.
maj_upgrade	Shows the information about Major version.
min_upgrade	Shows the information about Minor version.
upgrade	Shows the information about an upgrade.

contract_util update

Description

Updates the Check Point Service Contracts from your User Center account.

For more information about Service Contract files, see <u>sk33089</u>: <u>What is a Service Contract</u> <u>File?</u>

Syntax

```
contract_util update
  [-proxy <Proxy Server>:<Proxy Port>]
  [-ca_path <Path to ca-bundle.crt File>]
```

Parameter	Description
update	Updates Check Point Service Contracts (attached to pre- installed licenses) from your User Center account.
-proxy <proxy Server>:<proxy Port></proxy </proxy 	 Specifies that the connection to the User Center goes through the proxy server: <proxy server=""> - IP address of resolvable hostname of the proxy server.</proxy> <proxy port=""> - The applicable port on the proxy server.</proxy> Note - If you do not specify the proxy explicitly, the command uses the proxy configured in the management database.
-ca_path <path to<br="">ca-bundle.crt File></path>	 Specifies the path to the Certificate Authority Bundle file (ca-bundle.crt). Note - If you do not specify the path explicitly, the command uses the default path.

contract_util verify

Description

Checks whether the Security Gateway is eligible for an upgrade.

This command is the same as the *"contract_util check" on page 673* command, but it also interprets the return values and shows a meaningful message.

For more information about Service Contract files, see <u>sk33089</u>: <u>What is a Service Contract</u> <u>File?</u>

Syntax

contract_util verify

cp_conf

Description

Configures or reconfigures a Check Point product installation.

R Note - The available options for each Check Point computer depend on the configuration and installed products.

Syntax on a Management Server

```
cp conf
      -h
      admin <options>
      auto <options>
      ca <options>
      client <options>
      finger <options>
      lic <options>
      snmp <options>
```

Parameter	Description
-h	Shows the entire built-in usage.
admin <options></options>	Configures Check Point system administrators for the Security Management Server. See "cp_conf admin" on page 684.
auto	Shows and configures the automatic start of Check Point products during boot.
< <i>options</i> >	See "cp_conf auto" on page 687.
ca	 Configures the Certificate Authority's (CA) Fully Qualified Domain
<options></options>	Name (FQDN). Initializes the Internal Certificate Authority (ICA). See "cp_conf ca" on page 688.
client	Configures the GUI clients that can use SmartConsole to connect to the Security Management Server.
< <i>options</i> >	See " <i>cp_conf client</i> " on page 690.

Parameter	Description
finger	Shows the ICA's Fingerprint.
<options></options>	See "cp_conf finger" on page 694.
lic	Manages Check Point licenses.
<options></options>	See "cp_conf lic" on page 695.
snmp <options></options>	Do not use these outdated commands. To configure SNMP, see the <u>R82 Gaia Administration Guide</u> - Chapter System Management - Section SNMP.

cp_conf admin

Description

Configures Check Point system administrators for the Security Management Server.



- Multi-Domain Server does not support this command.
- Only one administrator can be defined in the "cpconfig" on page 749 menu. To define additional administrators, use SmartConsole.
- This command corresponds to the option Administrator in the "cpconfig" on page 749 menu.

Syntax

```
cp_conf admin
    -h
    add [<UserName> <Password> {a | w | r}]
    add -gaia [{a | w | r}]
    del <UserName1> <UserName2> ...
    get
```

Parameter	Description
-h	Shows the applicable built-in usage.
add [<i><username></username></i> <i><password></password></i> {a w r}]	 Adds a Check Point system administrator: <username> - Specifies the administrator's username</username> <password> - Specifies the administrator's password</password> a - Assigns all permissions - read settings, write settings, and manage administrators w - Assigns permissions to read and write settings only (cannot manage administrators) r - Assigns permissions to only read settings
add -gaia [{a w r}]	 Adds the Gaia administrator user admin: a - Assigns all permissions - read settings, write settings, and manage administrators w - Assigns permissions to read and write settings only (cannot manage administrators) r - Assigns permissions to only read settings
del <username1> <username2></username2></username1>	Deletes the specified system administrators.
get	Shows the list of the configured system administrators.
get -gaia	Shows the management permissions assigned to the Gaia administrator user admin.

Example 1 - Adding a Check Point system administrator

```
[Expert@MGMT:0] # cp conf admin add
Administrator name: admin
Administrator admin already exists.
Do you want to change Administrator's Permissions (y/n) [n] ? y
Permissions for all products (Read/[W]rite All, [R]ead Only All, [C]ustomized) c
        Permission for SmartUpdate (Read/[W]rite, [R]ead Only, [N]one) w
        Permission for Monitoring (Read/[W]rite, [R]ead Only, [N]one) w
Administrator admin was modified successfully and has
Read/Write Permission for SmartUpdate
Read/Write Permission for Monitoring
[Expert@MGMT:0]#
[Expert@MGMT:0] # cp conf admin get
The following Administrators
are defined for this Security Management Server:
admin (Read/Write Permission for all products; )
[Expert@MGMT:0]#
```

Example 2 - Adding the Gaia administrator user

```
[Expert@MGMT:0] # cp conf admin add -gaia
Permissions for all products (Read/[W]rite All, [R]ead Only All, [C]ustomized) c
       Permission for SmartUpdate (Read/[W]rite, [R]ead Only, [N]one) w
       Permission for Monitoring (Read/[W]rite, [R]ead Only, [N]one) w
Administrator admin was added successfully and has
Read/Write Permission for SmartUpdate
Read/Write Permission for Monitoring
[Expert@MGMT:0]#
[Expert@MGMT:0] # cp conf admin get -gaia
The following Administrators
are defined for this Security Management Server:
admin (Read/Write Permission for all products; ) - Gaia admin
[Expert@MGMT:0]#
[Expert@MGMT:0] # cp_conf admin add -gaia a
Administrator admin already exists.
Administrator admin was modified successfully and has
Read/Write Permission for all products with Permission to Manage Administrators
[Expert@MGMT:0]#
[Expert@MGMT:0] # cp conf admin add -gaia w
Administrator admin already exists.
Administrator admin was modified successfully and has
Read/Write Permission for all products without Permission to Manage Administrators
[Expert@MGMT:0]#
[Expert@MGMT:0] # cp conf admin add -gaia r
Administrator admin already exists.
Administrator admin was modified successfully and has
Read Only Permission for all products
[Expert@MGMT:0]#
```

cp_conf auto

Description

Shows and controls which of Check Point products start automatically during boot.

Note - This command corresponds to the option Automatic start of Check Point
 Products in the "cpconfig" on page 749 menu.

Syntax on a Management Server in Gaia Clish or the Expert mode

```
cp_conf auto
    -h
    {enable | disable} <Product1> <Product2> ...
    get all
```

Parameters

Parameter	Description
-h	Shows the applicable built-in usage.
<pre>{enable disable} <product1> <product2></product2></product1></pre>	Controls whether the installed Check Point products start automatically during boot. This command is for Check Point use only.
get all	 Shows which of these Check Point products start automatically during boot: Check Point Security Gateway QoS (former FloodGate-1) SmartEvent Suite


Example from a Security Management Server

```
[Expert@MGMT:0]# cp_conf auto get all
Check Point Security Gateway is not installed
QoS is not installed
The SmartEvent Suite will start automatically at boot time.
[Expert@MGMT:0]#
```

cp_conf ca

Description

This command changes the settings of the Internal Certificate Authority (ICA).



Syntax

```
cp_conf ca
-h
fqdn <FQDN Name>
init
```

Parameter	Description
-h	Shows the applicable built-in usage.
fqdn <i><fqdn< i=""> Name></fqdn<></i>	 Configures the Fully Qualified Domain Name (FQDN) for the Internal Certificate Authority (ICA). The "<fqdn name="">" is the text string in this format: hostname.domainname</fqdn> Notes: The existing certificates for configured objects are not revoked. The existing ICA certificate is not changed. The Management Server uses the specified "<fqdn name="">" to configure the Certificate Revocation List Distribution Point (CRL DP) property in all certificates that the ICA generates. Refer to this command: "cpca_client get_crldp" on page 725</fqdn>
init	Initializes the Internal Certificate Authority (ICA).

Example

[Expert@MyMGMT:0]# hostname MyMGMT [Expert@MyMGMT:0]# [Expert@MyMGMT:0]# domainname checkpoint.com [Expert@MyMGMT:0]# [Expert@MyMGMT:0]# [Expert@MyMGMT:0]# cp_conf ca fqdn MyMGMT.checkpoint.com Trying to contact Certificate Authority. It might take a while... Certificate was created successfully MyMGMT.checkpoint.com was successfully set to the Internal CA [Expert@MyMGMT:0]#

cp_conf client

Description

Configures the GUI clients that are allowed to connect with SmartConsoles to the Security Management Server.

Notes:

- Multi-Domain Server does not support this command.
- This command corresponds to the option GUI Clients in the "cpconfig" on page 749 menu.

Syntax

```
cp_conf client
  add <GUI Client>
   createlist <GUI Client 1> <GUI Client 2> ...
  del <GUI Client 1> <GUI Client 2> ...
  get
```

Parameters

Parameter	Description
-h	Shows the built-in usage.
<gui client=""></gui>	 <gui client=""> can be one of these:</gui> One IPv4 address (for example, 192.168.10.20), or one IPv6 address (for example, 3731:54:65fe:2::a7) One hostname (for example, MyComputer) "Any" - To denote all IPv4 and IPv6 addresses without restriction A range of IPv4 addresses (for example, 192.168.10.0/255.255.255.0), or a range of IPv6 addresses (for example, 2001::1/128) IPv4 address wildcard (for example, 192.168.10.*)
add < <i>GUI Client</i> >	Adds a GUI client.
createlist <gui 1="" client=""> <gui 2="" client=""></gui></gui>	Deletes the current allowed GUI clients and creates a new list of allowed GUI clients.
del < <i>GUI Client 1</i> > < <i>GUI</i> <i>Client 2</i> >	Deletes the specified the GUI clients.
get	Shows the allowed GUI clients.

Examples

Example 1 - Configure one IPv4 address

```
[Expert@MGMT:0]# cp_conf client get
There are no GUI Clients defined for this Security Management Server
[Expert@MGMT:0]# cp_conf client add 172.20.168.15
172.20.168.15 was successfully added.
[Expert@MGMT:0]# cp_conf client get
172.20.168.15
[Expert@MGMT:0]#
[Expert@MGMT:0]# cp_conf client del 172.20.168.15
172.20.168.15 was deleted successfully
[Expert@MGMT:0]#
```

Example 2 - Configure one hostname

```
[Expert@MGMT:0]# cp_conf client get
There are no GUI Clients defined for this Security Management Server
[Expert@MGMT:0]#
[Expert@MGMT:0]# cp_conf client add MySmartConsoleHost
MySmartConsoleHost was successfully added.
[Expert@MGMT:0]#
[Expert@MGMT:0]# cp_conf client get
MySmartConsoleHost
[Expert@MGMT:0]#
[Expert@MGMT:0]# cp_conf client del MySmartConsoleHost
MySmartConsoleHost was deleted successfully
[Expert@MGMT:0]#
```

Example 3 - Configure "Any"

```
[Expert@MGMT:0]# cp_conf client get
There are no GUI Clients defined for this Security Management Server
[Expert@MGMT:0]# cp_conf client add "Any"
Any was successfully added.
[Expert@MGMT:0]#
[Expert@MGMT:0]# cp_conf client get
Any
[Expert@MGMT:0]#
[Expert@MGMT:0]# cp_conf client del "Any"
Any was deleted successfully
[Expert@MGMT:0]#
```

Example 4 - Configure a range of IPv4 addresses

```
[Expert@MGMT:0]# cp_conf client get
There are no GUI Clients defined for this Security Management Server
[Expert@MGMT:0]#
[Expert@MGMT:0]# cp_conf client add 172.20.168.0/255.255.255.0
172.20.168.0/255.255.255.0 was successfully added.
[Expert@MGMT:0]#
[Expert@MGMT:0]# cp_conf client get
172.20.168.0/255.255.255.0
[Expert@MGMT:0]#
[Expert@MGMT:0]# cp_conf client del 172.20.168.0/255.255.255.0
172.20.168.0/255.255.255.0 was deleted successfully
[Expert@MGMT:0]#
```

Example 5 - Configure IPv4 address wildcard

```
[Expert@MGMT:0]# cp_conf client get
There are no GUI Clients defined for this Security Management Server
[Expert@MGMT:0]#
[Expert@MGMT:0]# cp_conf client add 172.20.168.*
172.20.168.* was successfully added.
[Expert@MGMT:0]# cp_conf client get
172.20.168.*
[Expert@MGMT:0]#
[Expert@MGMT:0]# cp_conf client del 172.20.168.*
172.20.168.* was deleted successfully
[Expert@MGMT:0]#
```

Example 6 - Delete the current list and create a new list of allowed GUI clients

```
[Expert@MGMT:0] # cp conf client get
There are no GUI Clients defined for this Security Management Server
[Expert@MGMT:0]#
[Expert@MGMT:0]# cp_conf client add 172.20.168.0/255.255.255.0
172.20.168.0/255.255.255.0 was successfully added.
[Expert@MGMT:0]#
[Expert@MGMT:0] # cp conf client get
172.20.168.0/255.255.255.0
[Expert@MGMT:0]#
[Expert@MGMT:0]# cp conf client createlist 192.168.40.0/255.255.255.0 172.30.40.55
New list was created successfully
[Expert@MGMT:0]#
[Expert@MGMT:0] # cp conf client get
192.168.40.0/255.255.255.0
172.30.40.55
[Expert@MGMT:0]#
[Expert@MGMT:0] # cp conf client createlist "Any"
New list was created successfully
[Expert@MGMT:0]#
[Expert@MGMT:0]# cp_conf client get
Any
[Expert@MGMT:0]#
```

cp_conf finger

Description

Shows the Internal Certificate Authority's Fingerprint.

This fingerprint is a text string derived from the ICA certificate on the Security Management Server, Multi-Domain Server, or Domain Management Server.

This fingerprint verifies the identity of the Security Management Server, Multi-Domain Server, or Domain Management Server when you connect to it with SmartConsole.

Note - This command corresponds to the option Certificate's Fingerprint in the "cpconfig" on page 749 menu.

Syntax

A

```
cp_conf finger
-h
get
```

Parameters

Parameter	Description
-h	Shows the applicable built-in usage.
get	Shows the ICA's Fingerprint.


Example

```
[Expert@MGMT:0]# cp_conf finger get
EDNA COCO MOLE ATOM ASH MOT SAGE NINE ILL TINT HI CUBE
[Expert@MGMT:0]#
```

cp_conf lic

Description

Shows, adds and deletes Check Point licenses.



Syntax on a Management Server in Gaia Clish or the Expert mode

```
cp_conf lic
    -h
    add -f <Full Path to License File>
    add -m <Host> <Date> <Signature Key> <SKU/Features>
    del <Signature Key>
    get [-x]
```

Parameters

Parameter	Description
-h	Shows the applicable built-in usage.
add -f <full path="" to<br="">License File></full>	Adds a license from the specified Check Point license file. You get this license file in the <u>Check Point User</u> <u>Center</u> . This is the same command as the "cplic db_add" on page 760.
add -m <host> <date> <signature key=""> <sku features=""></sku></signature></date></host>	Adds the license manually. You get these license details in the <u>Check Point</u> <u>User Center</u> . This is the same command as the "cplic db_add" on page 760.
del <i><signature key=""></signature></i>	Delete the license based on its signature. This is the same command as the <i>"cplic del" on page 765</i> .
get [-x]	Shows the local installed licenses. If you specify the " $-x$ " parameter, output also shows the signature key for every installed license. This is the same command as the " <i>cplic print</i> " on <i>page 769</i> .

Example 1 - Adding the license from the file

Example 2 - Adding the license manually

cp_log_export

Description

Exports Check Point logs over syslog.

For more information, see sk122323 and R82 Logging and Monitoring Administration Guide.

Notes:

- You can run this command only in the Expert mode.
- On a Multi-Domain Server, you must run this command in the context of the applicable Domain Management Server:

mdsenv <IP Address or Name of Domain Management Server>

Syntax

```
cp_log_export
cp log export <command-name> help
```

Parameter	Description
No Parameters	Shows the built-in general help.
<command-name> help</command-name>	Shows the built help for the specified internal command.

Internal Commands

Name	Description
add	Configures a new Check Point Log Exporter.
	<pre>cp_log_export add name <name> target-server <target- Server> target-port <target-server-port> protocol {udp tcp} [Optional Arguments]</target-server-port></target- </name></pre>
delete	Removes an existing Log Exporter.
	cp_log_export delete name < <i>Name</i> >
reexport	Resets the current log position and exports all logs again based on the configuration.
	<pre>cp_log_export reexport name <name>apply-now</name></pre>
	<pre>cp_log_export reexport name <name> start-position <position exported="" last="" log="" of="">apply-now</position></name></pre>
	<pre>cp_log_export reexport name <name> start-position <position gap="" of="" start=""> end-position <position end="" gap="" of="">apply-now</position></position></name></pre>
restart	Restarts a Log Exporter process.
	cp_log_export restart name < <i>Name</i> >
set	Updates an existing Log Exporter configuration.
	<pre>cp_log_export set name <name> [<optional arguments="">]</optional></name></pre>
show	Shows the current Log Exporter configuration.
	cp_log_export show [<optional arguments="">]</optional>
start	Starts an existing Log Exporter process.
	cp_log_export start name < <i>Name</i> >
status	Shows a Log Exporter overview status.
	cp_log_export status [<optional arguments="">]</optional>
stop	Stops an existing Log Exporter process.
	<pre>cp_log_export stop name <name></name></pre>

Internal Command Arguments

Name	Description	Requ ired for "add" com mand	Requ ired for "set" com mand	Requ ired for "dele te" com mand	Req uired for "rec onf" com man d	Req uired for "rest art", "sho w", "stat us", "star t", "sto p" com man d	Requ ired for "reex port" com mand
apply-now	Applies immediately any change that was done with the "add", "set", "delete", or "reexport" command.	Optio nal	Optio nal	Man dator y	N/A	N/A	Man dator y
ca-cert < <i>Path</i> >	Specifies the full path to the CA certificate file *.pem. Important - Applicable only when the value of the "encrypted" argument is "true".	Optio nal	Optio nal	N / A	N / A	N / A	N/A

Name	Description	Requ ired for "add" com mand	Requ ired for "set" com mand	Requ ired for "dele te" com mand	Req uired for "rec onf" com man d	Req uired for "rest art", "sho w", "stat us", "star t", "sto p" com man d	Requ ired for "reex port" com mand
client-cert < <i>Path</i> >	Specifies the full path to the client certificate *.p12. Important - Applicable only when the value of the "encrypted" argument is "true".	Optio nal	Optio nal	N/A	N/A	N/A	N/A
client- secret < <i>Phrase</i> >	Specifies the challenge phrase used to create the client certificate *.p12. Important - Applicable only when the value of the "encrypted" argument is "true".	Optio nal	Optio nal	N/A	N/A	N/A	N/A

Name	Description	Requ ired for "add" com mand	Requ ired for "set" com mand	Requ ired for "dele te" com mand	Req uired for "rec onf" com man d	Req uired for "rest art", "sho w", "stat us", "star t", "sto p" com man d	Requ ired for "reex port" com mand
domain- server {mds all}	On a Multi-Domain Server, specifies the applicable Domain Management Server context. On a Multi-Domain Log Server, specifies the applicable Domain Log Server context. Important: Important: Important: Exports all logs from only the main	Man dator y	Man dator y	Man dator y	N/A	Opti onal	Man dator y
	MDS level. "all" (in small letters) - Exports all logs from all Domains.						

Name	Description	Requ ired for "add" com mand	Requ ired for "set" com mand	Requ ired for "dele te" com mand	Req uired for "rec onf" com man d	Req uired for "rest art", "sho w", "stat us", "star t", "sto p" com man d	Requ ired for "reex port" com mand
enabled {true false}	Default: true	Optio nal	Optio nal	N/A	N/A	N/A	N/A
encrypted {true false}	Specifies whether to use TSL (SSL) encryption to send the logs. Default: false	Optio nal	Optio nal	N / A	N / A	N/A	N/A
end-position < <i>Position</i> >	Specifies the end position, up to which to export the logs.	N/A	N/A	N/A	N/A	N/A	Optio nal
export- attachment- ids {true false}	Specifies whether to add a field to the exported logs that represents the ID of log's attachment (if exists). Default: false	Optio nal	Optio nal	N/A	N/A	N/A	N/A

Name	Description	Requ ired for "add" com mand	Requ ired for "set" com mand	Requ ired for "dele te" com mand	Req uired for "rec onf" com man d	Req uired for "rest art", "sho w", "stat us", "star t", "sto p" com man d	Requ ired for "reex port" com mand
export- attachment- link {true false}	Specifies whether to add a field to the exported logs that represents a link to SmartView that shows the log card and automatically opens the attachment. Default: false	Optio nal	Optio nal	N / A	N/A	N/A	N/A
export-link {true false}	Specifies whether to add a field to the exported logs that represents a link to SmartView that shows the log card. Default: false	Optio nal	Optio nal	N/A	N/A	N/A	N/A

Name	Description	Requ ired for "add" com mand	Requ ired for "set" com mand	Requ ired for "dele te" com mand	Req uired for "rec onf" com man d	Req uired for "rest art", "sho w", "stat us", "star t", "sto p" com man d	Requ ired for "reex port" com mand
<pre>export-link- ip {true false}</pre>	Specifies whether to make the links to SmartView use a custom IP address (for example, for a Log Server behind NAT). Important - Applicable only when the value of the "export- link" argument is "true", or the value of the "export- attachment- link" argument is "true". Default: false	Optio nal	Optio nal	N/A	N/A	N/A	N/A
export-log- position {true false}	Specifies whether to export the log's position. Default: false	Optio nal	Optio nal	N / A	N / A	N / A	N/A

Name	Description	Requ ired for "add" com mand	Requ ired for "set" com mand	Requ ired for "dele te" com mand	Req uired for "rec onf" com man d	Req uired for "rest art", "sho w", "stat us", "star t", "sto p" com man d	Requ ired for "reex port" com mand
<pre>filter- action-in {"Action1"," Action2", false}</pre>	Specifies whether to export all logs that contain a specific value in the "Action" field. Each value must be surrounded by double quotes (""). Multiple values are supported and must be separated by a comma without spaces. To see all valid values: 1. In SmartConsole , go to the Logs & Events view and open the Logs tab. 2. In the top query field, enter action: and a letter.	Optio nal	Optio nal	N/A	N/A	N/A	N/A

Name	Description	Requ ired for "add" com mand	Requ ired for "set" com mand	Requ ired for "dele te" com mand	Req uired for "rec onf" com man d	Req uired for "rest art", "sho w", "stat us", "star t", "sto p" com man d	Requ ired for "reex port" com mand
	 Accept Block Bypass Detect Drop HTTPS Bypass HTTPS Inspect Prevent Reject Important - This parameter replaces any other filter configuration that was declared earlier on this field directly in the filtering XML file. Other field filters are not overwritten. 						

Name	Description	Requ ired for "add" com mand	Requ ired for "set" com mand	Requ ired for "dele te" com mand	Req uired for "rec onf" com man d	Req uired for "rest art", "sho w", "stat us", "star t", "sto p" com man d	Requ ired for "reex port" com mand
<pre>filter- blade-in {"Blade1","B lade2", false}</pre>	Specifies whether to export all logs that contain a specific value in the " Blade " field (the object name of the Software Blade that generated these logs). Each value must be surrounded by double quotes (""). Multiple values are supported and must be separated by a comma without spaces. To see all valid values:	Optio nal	Optio nal	N/A	N/A	N/A	N/A
	 In SmartConsole , go to the Logs & Events view and open the Logs tab. 						

Name	Description	Requ ired for "add" com mand	Requ ired for "set" com mand	Requ ired for "dele te" com mand	Req uired for "rec onf" com man d	Req uired for "rest art", "sho w", "stat us", "star t", "sto p" com man d	Requ ired for "reex port" com mand
	 In the top query field, enter blade: and a letter. 						
	Examples of values:						
	 Anti-Bot Firewall HTTPS Inspection Identity Awareness IPS 						
	Valid Software Blade families:						
	 Access TP Endpoint Mobile 						

Name	Description	Requ ired for "add" com mand	Requ ired for "set" com mand	Requ ired for "dele te" com mand	Req uired for "rec onf" com man d	Req uired for "rest art", "sho w", "stat us", "star t", "sto p" com man d	Requ ired for "reex port" com mand
	important - This parameter replaces any other filter configuration that was declared earlier on this field directly in the filtering XML file. Other field filters are not overwritten.						

Name	Description	Requ ired for "add" com mand	Requ ired for "set" com mand	Requ ired for "dele te" com mand	Req uired for "rec onf" com man d	Req uired for "rest art", "sho w", "stat us", "star t", "sto p" com man d	Requ ired for "reex port" com mand
<pre>filter- origin-in {"Origin1"," Origin2", false}</pre>	Specifies whether to export all logs that contain a specific value in the " Origin " field (the object name of the Security Gateway / Cluster Member that generated these logs). Each origin value must be surrounded by double quotes (""). Multiple values are supported and must be separated by a comma without spaces.	Optio nal	Optio nal	N / A	N/A	N / A	N/A

Name	Description	Requ ired for "add" com mand	Requ ired for "set" com mand	Requ ired for "dele te" com mand	Req uired for "rec onf" com man d	Req uired for "rest art", "sho w", "stat us", "star t", "sto p" com man d	Requ ired for "reex port" com mand
	important - This parameter replaces any other filter configuration that was declared earlier on this field directly in the filtering XML file. Other field filters are not overwritten.						
format {generic cef json leef logrhythm rsa splunk syslog}	Specifies the format, in which the logs are exported. Default: syslog	Optio nal	Optio nal	N / A	N/A	N/A	N/A

cp_log_export

Name	Description	Requ ired for "add" com mand	Requ ired for "set" com mand	Requ ired for "dele te" com mand	Req uired for "rec onf" com man d	Req uired for "rest art", "sho w", "stat us", "star t", "sto p" com man d	Requ ired for "reex port" com mand
name "< <i>Name</i> >"	Specifies the unique name of the Log Exporter configuration.	Man dator y	Man dator y	Man dator y	Opti onal. By defa ult, appli es to all.	Opti onal. By defa ult, appli es to all.	Man dator y

Name	Description	Requ ired for "add" com mand	Requ ired for "set" com mand	Requ ired for "dele te" com mand	Req uired for "rec onf" com man d	Req uired for "rest art", "sho w", "stat us", "star t", "sto p" com man d	Requ ired for "reex port" com mand
	 Notes: Allowed characters are: Latin letters, digits ("0-9"), minus ("-"), underscore ("_"), and period ("."). Must start with a letter. The minimum length is two characters. The "add" command creates a new target directory with the specified unique name in the \$EXPORTERD IR/target s/ directory. 						

Name	Description	Requ ired for "add" com mand	Requ ired for "set" com mand	Requ ired for "dele te" com mand	Req uired for "rec onf" com man d	Req uired for "rest art", "sho w", "stat us", "star t", "sto p" com man d	Requ ired for "reex port" com mand
protocol {tcp udp}	Specifies the Layer 4 Transport protocol to use (TCP or UDP). There is no default value.	Man dator y	Optio nal	N/A	N/A	N/A	N/A

Name	Description	Requ ired for "add" com mand	Requ ired for "set" com mand	Requ ired for "dele te" com mand	Req uired for "rec onf" com man d	Req uired for "rest art", "sho w", "stat us", "star t", "sto p" com man d	Requ ired for "reex port" com mand
<pre>read-mode {raw semi- unified}</pre>	Specifies the mode, in which to read the log files. • raw - Specifies to export log records without any unification. • semi- unified - Specifies to export log records with step-by-step unification. That is, for each log record, export a record that unifies this record with all previously- encountered records with the same ID.	Optio nal	Optio nal	N/A	N/A	N/A	N/A

Name	Description	Requ ired for "add" com mand	Requ ired for "set" com mand	Requ ired for "dele te" com mand	Req uired for "rec onf" com man d	Req uired for "rest art", "sho w", "stat us", "star t", "sto p" com man d	Requ ired for "reex port" com mand
	Default : semi- unified Default : raw						
reconnect- interval { <i><number></number></i> default}	Specifies the interval (in minutes) after which the Log Exporter must connect again to the target server after the connection is lost. To disable, enter the value "default". There is no default value.	Optio nal	Optio nal	N/A	N/A	N/A	N/A
start- position < <i>Position</i> >	Specifies the start position, from which to export the logs.	N/A	N/A	N/A	N/A	N/A	Optio nal
target-port <target- Server-Port></target- 	Specifies the listening port on the target server, to which you export the logs.	Man dator y	Optio nal	N/A	N / A	N/A	N/A

Name	Description	Requ ired for "add" com mand	Requ ired for "set" com mand	Requ ired for "dele te" com mand	Req uired for "rec onf" com man d	Req uired for "rest art", "sho w", "stat us", "star t", "sto p" com man d	Requ ired for "reex port" com mand
target- server <target- Server></target- 	Specifies the IP address or FQDN of the target server, to which you export the logs.	Man dator y	Optio nal	N/A	N/A	N/A	N/A
time-in- milli {true false}	Specifies whether to export logs with the time resolution in milliseconds. Requires Security Gateways R81 and higher. Default: false	Optio nal	Optio nal	N/A	N/A	N/A	N/A

cpca_client

Description

Execute operations on the Internal Certificate Authority (ICA).

Note:

On a Multi-Domain Server, you must run this command in the context of the applicable Domain Management Server:

mdsenv <IP Address or Name of Domain Management Server>

Syntax

cpca_client [-d]
<pre>create_cert <options></options></pre>
double_sign < <i>options</i> >
<pre>get_crldp <options></options></pre>
get_pubkey < <i>options</i> >
<pre>init_certs <options></options></pre>
<pre>lscert <options></options></pre>
revoke_cert < <i>options</i> >
revoke_non_exist_cert < <i>options</i> >
<pre>search <options></options></pre>
<pre>set_ca_services <options></options></pre>
<pre>set_cert_validity <options></options></pre>
<pre>set_mgmt_tool <options></options></pre>
<pre>set_sign_hash <options></options></pre>

Parameter	Description
-d	 Runs the command in debug mode. Use only if you troubleshoot the command itself. Best Practice - If you use this parameter, then redirect the output to a file, or use the script command to save the entire CLI session.
create_cert <options></options>	Issues a SIC certificate for the Security Management Server or Domain Management Server. See "cpca_client create_cert" on page 721.

Parameter	Description
double_sign < <i>options</i> >	Creates a second signature for a certificate. See "cpca_client double_sign" on page 723.
get_crldp <i><options></options></i>	Shows how to access a CRL file from a CRL Distribution Point. See "cpca_client get_crldp" on page 725.
get_pubkey < <i>options</i> >	Saves the encoding of the public key of the ICA's certificate to a file. See "cpca_client get_pubkey" on page 726.
<pre>init_certs <options></options></pre>	Imports a list of DNs for users and creates a file with registration keys for each user. See "cpca_client init_certs" on page 727.
lscert <options></options>	Shows all certificates issued by the ICA. See "cpca_client lscert" on page 728.
revoke_cert <options></options>	Revokes a certificate issued by the ICA. See "cpca_client revoke_cert" on page 731.
revoke_non_exist_ cert < <i>options</i> >	Revokes a non-existent certificate issued by the ICA. See "cpca_client revoke_non_exist_cert" on page 734.
<pre>search <options></options></pre>	Searches for certificates in the ICA. See "cpca_client search" on page 735.
set_ca_services <options></options>	Controls the Certificate Authority Services Portal. See "cpca_client set_ca_services" on page 738.
<pre>set_cert_validity <options></options></pre>	Configures the default certificate validity period for new certificates. See "cpca_client set_cert_validity" on page 740.
set_mgmt_tool < <i>options</i> >	Controls the ICA Management Tool. See "cpca_client set_mgmt_tool" on page 741.
set_sign_hash <options></options>	Sets the hash algorithm that the CA uses to sign the file hash. See "cpca_client set_sign_hash" on page 746.

cpca_client create_cert

Description

Issues a SIC certificate for the Security Management Server or Domain Management Server.

Note:

On a Multi-Domain Server, you must run this command in the context of the applicable Domain Management Server:

mdsenv <IP Address or Name of Domain Management Server>

Syntax

```
cpca_client [-d] create_cert [-p <CA port number>] -n "CN=<Common
Name>" -f <Full Path to PKCS12 file> [-w <Password>] [-k {SIC |
USER | IKE | ADMIN PKG}] [-c "<Comment for Certificate>"]
```

Parameters

Parameter	Description
-d	 Runs the command in debug mode. Use only if you troubleshoot the command itself. Best Practice - If you use this parameter, then redirect the output to a file, or use the script command to save the entire CLI session.
-p <ca port<br="">number></ca>	Specifies the TCP port on the Security Management Server or Domain Management Server, which is used to connect to the Certificate Authority. The default TCP port number is 18209.
-n "CN=< <i>Common</i> Name>"	Sets the CN to the specified < Common Name>.
-f <full path<br="">to PKCS12 file></full>	Specifies the PKCS12 file, which stores the certificate and keys.
-w <password></password>	Optional. Specifies the certificate password.
-k {SIC USER IKE ADMIN_ PKG}	Optional. Specifies the certificate kind.
-c " <comment for Certificate>"</comment 	Optional. Specifies the certificate comment (must enclose in double quotes).

Example

[Expert@MGMT:0]# cpca_client create_cert -n "cn=cp_mgmt" -f \$CPDIR/conf/sic_cert.p12

cpca_client double_sign

Description

Creates a second signature for a certificate.

Note:

On a Multi-Domain Server, you must run this command in the context of the applicable Domain Management Server:

mdsenv <IP Address or Name of Domain Management Server>

Syntax

```
cpca_client [-d] double_sign [-p <CA port number>] -i <Certificate
File in PEM format> [-o <Full Path to Output File>]
```

Parameter	Description
-d	 Runs the command in debug mode. Use only if you troubleshoot the command itself. Best Practice - If you use this parameter, then redirect the output to a file, or use the script command to save the entire CLI session.
-p <ca port<br="">number></ca>	Optional. Specifies the TCP port on the Security Management Server or Domain Management Server, which is used to connect to the Certificate Authority. The default TCP port number is 18209.
-i <certificate File in PEM format></certificate 	Imports the specified certificate (only in PEM format).
-o <full path<br="">to Output File></full>	Optional. Saves the certificate into the specified file.

```
[Expert@MGMT:0] # cpca client double sign -i certificate.pem
Requesting Double Signature for the following Certificate:
       refCount: 1
       Subject: Email=example@example.com,CN=http://www.example.com/,OU=ValiCert Class 2 Policy
Validation Authority,O=exampleO\, Inc.,L=ExampleL Validation Network
Double Sign of Cert:
 _____
 (
       : (
               :dn ("Email=example@example.com,CN=http://www.example.com/,OU=exampleOU Class 2
Policy Validation Authority, O=exampleO\, Inc., L=exampleL Validation Network")
               :doubleSignCert (52016390... ... ...ebb67e96)
               :return code (0)
       )
)
[Expert@MGMT:0]#
```

cpca_client get_crldp

Description

Shows the Fully Qualified Domain Name (FQDN) configured for the Internal Certificate Authority (ICA) with the "*cp_conf ca*" *on page 688*" command.

The Management Server uses this FQDN:

- 1. To configure the Certificate Revocation List Distribution Point (CRL DP) property in all certificates that the ICA generates.
- 2. To create the URL for accessing the CRL.

Example: http://MyMGMT.checkpoint.com:18264/ICA_CRL1.crl

Syntax

cpca_client [-d] get_crldp [-p <ICA port number>]

Parameters

Parameter	Description
-d	 Runs the command in debug mode. Use only if you troubleshoot the command itself. Best Practice - If you use this parameter, then redirect the output to a file, or use the script command to save the entire CLI session.
-p <ica port number></ica 	Optional. Specifies the TCP port on the Security Management Server or Domain Management Server, which is used to connect to the Certificate Authority. The default TCP port number is 18264.

```
[Expert@MyMGMT:0]# hostname
MyMGMT
[Expert@MyMGMT:0]#
[Expert@MyMGMT:0]# domainname
checkpoint.com
[Expert@MyMGMT:0]#
[Expert@MyMGMT:0]# cpca_client get_crldp
MyMGMT.checkpoint.com
[Expert@MyMGMT:0]
```

cpca_client get_pubkey

Description

Saves the encoding of the public key of the ICA's certificate to a file.

Note:

On a Multi-Domain Server, you must run this command in the context of the applicable Domain Management Server:

mdsenv <IP Address or Name of Domain Management Server>

Syntax

```
cpca_client [-d] get_pubkey [-p <CA port number>] <Full Path to
Output File>
```

Parameters

Parameter	Description	
-d	 Runs the command in debug mode. Use only if you troubleshoot the command itself. Best Practice - If you use this parameter, then redirect the output to a file, or use the script command to save the entire CLI session. 	
-p <ca port<br="">number></ca>	Specifies the TCP port on the Security Management Server or Domain Management Server, which is used to connect to the Certificate Authority. The default TCP port number is 18209.	
<full path<br="">to Output File></full>	Saves the encoding of the public key of the ICA's certificate to the specified file.	

```
[Expert@MGMT:0]# cpca_client get_pubkey /tmp/key.txt[Expert@MGMT:0]#
[Expert@MGMT:0]# cat /tmp/key.txt
3082010a... ... ...f98b8910
[Expert@MGMT:0]#
```

cpca_client init_certs

Description

Imports a list of Distinguished Names (DN) for users and creates a file with registration keys for each user.

Note:

On a Multi-Domain Server, you must run this command in the context of the applicable Domain Management Server:

mdsenv <IP Address or Name of Domain Management Server>

Syntax

```
cpca_client [-d] init_certs [-p <CA port number>] -i <Full Path to
Input File> -o <Full Path to Output File>
```

Parameter	Description	
-d	 Runs the command in debug mode. Use only if you troubleshoot the command itself. Best Practice - If you use this parameter, then redirect the output to a file, or use the script command to save the entire CLI session. 	
-p <ca port<br="">number></ca>	Optional. Specifies the TCP port on the Security Management Server or Domain Management Server, which is used to connect to the Certificate Authority. The default TCP port number is 18209.	
-i <full Path to Input File></full 	Imports the specified file. Make sure to use the full path. Make sure that there is an empty line between each DN in the specified file. Example: CN=test1,OU=users <empty line=""> CN=test2,OU=users</empty>	
-o <full Path to Output File></full 	Saves the registration keys to the specified file. This command saves the error messages in the <name of="" output<br="">File>.failures file in the same directory.</name>	

cpca_client lscert

Description

Shows all certificates issued by the ICA.

Note:

On a Multi-Domain Server, you must run this command in the context of the applicable Domain Management Server:

mdsenv <IP Address or Name of Domain Management Server>

Syntax

```
cpca_client [-d] lscert [-dn <SubString>] [-stat {Pending | Valid
| Revoked | Expired | Renewed}] [-kind {SIC | IKE | User | LDAP}]
[-ser <Certificate Serial Number>] [-dp <Certificate Distribution
Point>]
```

Parameter	Description
-d	 Runs the command in debug mode. Use only if you troubleshoot the command itself. Best Practice - If you use this parameter, then redirect the output to a file, or use the script command to save the entire CLI session.
-dn < <i>SubString</i> >	Optional. Filters the search results to those with a DN that matches the specified < <i>SubString</i> >. This command does not support multiple values.
-stat {Pending Valid Revoked Expired Renewed}	Optional. Filters the search results to those with certificate status that matches the specified status. This command does not support multiple values.
-kind {SIC IKE User LDAP}	Optional. Filters the search results to those with certificate kind that matches the specified kind. This command does not support multiple values.
-ser < <i>Certificate Serial</i> Number>	Optional. Filters the search results to those with certificate serial number that matches the specified serial number. This command does not support multiple values.
-dp <certificate Distribution Point></certificate 	Optional. Filters the search results to the specified Certificate Distribution Point (CDP). This command does not support multiple values.

```
[Expert@MGMT:0] # cpca client lscert -stat Revoked
Operation succeeded. rc=0.
5 certs found.
Subject = CN=VSX2,O=MyDomain Server.checkpoint.com.s6t98x
Status = Revoked Kind = SIC Serial = 5521 DP = 0
Not Before: Sun Apr 8 14:10:01 2018 Not After: Sat Apr 8 14:10:01 2023
Subject = CN=VSX1,O=MyDomain Server.checkpoint.com.s6t98x
Status = Revoked Kind = SIC Serial = 9113 DP = 0
Not_Before: Sun Apr 8 14:09:02 2018 Not_After: Sat Apr 8 14:09:02 2023
Subject = CN=VSX1 VPN Certificate,O=MyDomain_Server.checkpoint.com.s6t98x
Status = Revoked Kind = IKE Serial = 82434
                                              DP = 2
Not_Before: Mon May 14 19:15:05 2018 Not_After: Sun May 14 19:15:05 2023
[Expert@MGMT:0]#
[Expert@MGMT:0] # cpca client lscert -kind IKE
Operation succeeded. rc=0.
3 certs found.
Subject = CN=VS1 VPN Certificate,O=MyDomain Server.checkpoint.com.s6t98x
Status = Valid Kind = IKE Serial = 27214 DP = 1
Not Before: Wed Apr 11 17:26:02 2018 Not After: Tue Apr 11 17:26:02 2023
Subject = CN=VSX_Cluster VPN Certificate,O=MyDomain_Server.checkpoint.com.s6t98x
Status = Valid Kind = IKE
                           Serial = 64655 DP = 1
Not Before: Mon Apr 9 19:36:31 2018 Not After: Sun Apr 9 19:36:31 2023
Subject = CN=VSX1 VPN Certificate,O=MyDomain Server.checkpoint.com.s6t98x
Status = Revoked Kind = IKE Serial = 82434 DP = 2
Not Before: Mon May 14 19:15:05 2018 Not After: Sun May 14 19:15:05 2023
[Expert@MGMT:0]#
```

cpca_client revoke_cert

Description

Revokes a certificate issued by the ICA.

Note:

On a Multi-Domain Server, you must run this command in the context of the applicable Domain Management Server:

mdsenv <IP Address or Name of Domain Management Server>

Syntax

```
cpca_client [-d] revoke_cert [-p <CA port number>] -n "CN=<Common
Name>" -s <Certificate Serial Number>
```

Parameters

Parameter	Description	
-d	 Runs the command in debug mode. Use only if you troubleshoot the command itself. Best Practice - If you use this parameter, then redirect the output to a file, or use the script command to save the entire CLI session. 	
-p <ca port<br="">number></ca>	Optional. Specifies the TCP port on the Security Management Server or Domain Management Server, which is used to connect to the Certificate Authority. The default TCP port number is 18209.	
-n "CN=< <i>Common</i> Name>"	Specifies the certificate CN. To get the CN, run the <i>"cpca_client lscert" on page 728</i> command and examine the text that you see between the "Subject =" and the ", O=".	
	Example	
	From this output:	
	Subject = CN=VS1 VPN Certificate , O=MyDomain_Server.checkpoint.com.s6t98x Status = Valid Kind = IKE Serial = 27214 DP = 1 Not_Before: Wed Apr 11 17:26:02 2018 Not_After: Tue Apr 11 17:26:02 2023	
	you get this syntax:	
	-n "CN=VS1 VPN Certificate	
	Note - You can use the parameter '-n' only, or together with the parameter "-s".	
-s <certificate Serial Number></certificate 	 Specifies the certificate serial number. To see the serial number, run the "cpca_client lscert" on page 728 command. Note - You can use the parameter "-s" only, or together with the parameter "-n". 	

Example 1 - Revoking a certificate specified by its CN

```
[Expert@MGMT:0]# cpca_client lscert
Subject = CN=VS1 VPN Certificate,O=MyDomain_Server.checkpoint.com.s6t98x
Status = Valid Kind = IKE Serial = 27214 DP = 1
Not_Before: Wed Apr 11 17:26:02 2018 Not_After: Tue Apr 11 17:26:02 2023
[Expert@MGMT:0]#
[Expert@MGMT:0]# cpca_client -d revoke_cert -n "CN=VS1 VPN Certificate"
Certificate was revoked successfully
[Expert@MGMT:0]#
```

Example 2 - Revoking a certificate specified by its serial number.

[Expert@MGMT:0]# cpca_client lscert Subject = CN=VS1 VPN Certificate,O=MyDomain_Server.checkpoint.com.s6t98x Status = Valid Kind = IKE Serial = 27214 DP = 1 Not_Before: Wed Apr 11 17:26:02 2018 Not_After: Tue Apr 11 17:26:02 2023 [Expert@MGMT:0]# [Expert@MGMT:0]# cpca_client -d revoke_cert -s 27214 Certificate was revoked successfully [Expert@MGMT:0]#

cpca_client revoke_non_exist_cert

Description

Revokes a non-existent certificate issued by the ICA.

Note:

On a Multi-Domain Server, you must run this command in the context of the applicable Domain Management Server:

mdsenv <IP Address or Name of Domain Management Server>

Syntax

```
cpca_client [-d] revoke_non_exist_cert -i <Full Path to Input
File>
```

Parameters

Paramet er	Description	
-d	Runs the cpca_client command under debug.	
-i <full Path</full 	Specifies the file that contains the list of the certificate to revoke. You must create this file in the same format as the "cpca_client lscert" on page 728 command prints its output.	
to Input	Example	
File>	<pre>Subject = CN=cp_mgmt,O=MGMT.5p72vp Status = Valid Kind = SIC Serial = 30287 DP = 0 Not_Before: Sat Apr 7 19:40:12 2018 Not_After: Fri Apr 7 19:40:12 2023 <empty line=""> Subject = CN=cp_mgmt,O=MGMT.5p72vp Status = Valid Kind = SIC Serial = 60870 DP = 0 Not_Before: Sat Apr 7 19:40:13 2018 Not_After: Fri Apr 7 19:40:13 2023</empty></pre>	

Note - This command saves the error messages in the <Name of Input File>.failures file.

cpca_client search

Description

Searches for certificates in the ICA.

Note:

On a Multi-Domain Server, you must run this command in the context of the applicable Domain Management Server:

mdsenv <IP Address or Name of Domain Management Server>

Syntax

```
cpca_client [-d] search <String> [-where {dn | comment | serial |
device_type | device_id | device_name}] [-kind {SIC | IKE | User |
LDAP}] [-stat {Pending | Valid | Revoked | Expired | Renewed}] [-
max <Maximum Number of Results>] [-showfp {y | n}]
```

Parameter	Description
-d	 Runs the command in debug mode. Use only if you troubleshoot the command itself. Best Practice - If you use this parameter, then redirect the output to a file, or use the script command to save the entire CLI session.
<string></string>	Specifies the text to search in the certificates. You can enter only one text string that does not contain spaces.

Parameter	Description
-where {dn comment serial device_type device_id device_	Optional. Specifies the certificate's field, in which to search for the string:
name}	 dn - Certificate DN comment - Certificate comment serial - Certificate serial number device_type - Device type device_id - Device ID device_name - Device Name The default is to search in all fields.
-kind {SIC IKE User LDAP}	Optional. Specifies the certificate kind to search. You can enter multiple values in this format: -kind <kind1> <kind2> <kind3> The default is to search for all kinds.</kind3></kind2></kind1>
-stat {Pending Valid Revoked Expired Renewed}	Optional. Specifies the certificate status to search. You can enter multiple values in this format: -stat <status1> <status2> <status3> The default is to search for all statuses.</status3></status2></status1>
-max <maximum number="" of="" results=""></maximum>	Optional. Specifies the maximum number of results to show. Range: 1 and greater Default: 200
-showfp {y n}	 Optional. Specifies whether to show the certificate's fingerprint and thumbprint: y - Shows the fingerprint and thumbprint (this is the default) n - Does not show the fingerprint and thumbprint

Example 1

```
[\tt Expert@MGMT:0] \# cpca_client search sample<br/>company -where comment -kind SIC LDAP -stat Pending Valid Renewed
```

Example 2

```
[Expert@MGMT:0]# cpca_client search 192.168.3.51 -where dn -showfp nOperation succeeded. rc=0.
1 certs found.
Subject = CN=192.168.3.51,O=MGMT.5p72vp
Status = Valid Kind = SIC Serial = 73455 DP = 0
Not_Before: Sat Apr 7 19:40:12 2018 Not_After: Fri Apr 7 19:40:12 2023
[Expert@MGMT:0]#
```

cpca_client set_ca_services

Description

This command enables and disables the Certificate Authority Services Portal on the Management Server on the TCP port 18268.

From this portal, you can download the applicable Internal Certificate Authority certificates.

For trust purposes, you can install this certificate on the applicable Security Gateways, externally managed Site to Site VPN peer gateways, Remote Access VPN clients, clients that use Clientless VPN, and so on.

R Note - In R82, the TCP port 18264 on the Management Server is available only for the retrieval of the CRL (Certificate Revocation List).

Syntax

cpca client set ca services {on | off}

Parameters

Parameter	Description
on	Enables the Certificate Authority Services Portal
off	Disables the Certificate Authority Services Portal

Procedure for a Security Management Server

Enabling the Certificate Authority Services Portal

- 1. Connect to the command line on the Security Management Server.
- 2. Log in to the Expert mode.
- 3. Enable the Certificate Authority Services Portal:

cpca client set ca services on

4. With a web browser, connect to:

http://<IP Address of Security Management Server>:18268

- 5. Download the required certificate.
- 6. Install this certificate on the applicable computers.

Disabling the Certificate Authority Services Portal

- 1. Connect to the command line on the Security Management Server.
- 2. Log in to the Expert mode.
- 3. Disable the Certificate Authority Services Portal:

cpca_client set_ca_services off

Procedure for a Domain Management Server

Enabling the Certificate Authority Services Portal

- 1. Connect to the command line on the Multi-Domain Server.
- 2. Log in to the Expert mode.
- 3. Go to the context of the Domain Management Server:

mdsenv <IP Address or Name of Domain Management Server>

4. Enable the Certificate Authority Services Portal:

cpca client set ca services on

5. With a web browser, connect to:

http://<IP Address of Domain Management Server>:18268

- 6. Download the required certificate.
- 7. Install this certificate on the applicable computers.

Disabling the Certificate Authority Services Portal

- 1. Connect to the command line on the Multi-Domain Server.
- 2. Log in to the Expert mode.
- 3. Go to the context of the Domain Management Server:

mdsenv <IP Address or Name of Domain Management Server>

4. Disable the Certificate Authority Services Portal:

cpca client set ca services off

cpca_client set_cert_validity

Description

This command configures the default certificate validity period for new certificates.

Notes:

 On a Multi-Domain Server, you must run this command in the context of the applicable Domain Management Server:

mdsenv <IP Address or Name of Domain Management Server>

The new certificate validity period applies only to certificate you create after this change.

Syntax

```
cpca_client set_cert_validity -k {SIC | IKE | USER} [-y <Number of
Years>] [-d <Number of Days>] [-h <Number of Hours>] [-s <Number
of Seconds>]
```

Parameters

Parameter	Description
-k {SIC IKE USER}	Specifies the certificate type.
-y <number of="" years=""></number>	Specifies the validity period in years.
-d <number days="" of=""></number>	Specifies the validity period in days.
-h <number hours="" of=""></number>	Specifies the validity period in hours.
-s <number of="" seconds=""></number>	Specifies the validity period in seconds.

```
[Expert@MGMT:0]# cpca_client set_cert_validity -k IKE -y 3
  cert validity period was changed successfully.
[Expert@MGMT:0]#
```

cpca_client set_mgmt_tool

Description

Controls the ICA Management Tool.

This tool is disabled by default.

Note:

On a Multi-Domain Server, you must run this command in the context of the applicable Domain Management Server:

mdsenv <IP Address or Name of Domain Management Server>

See sk102837: Best Practices - ICA Management Tool configuration

Syntax

```
cpca_client [-d] set_mgmt_tool {on | off | add | remove | clean |
print} [-p <CA port number>] [{-a <Administrator DN> | -u <User
DN> | -c <Custom User DN>}]
```

Parameter	Description
-d	 Runs the command in debug mode. Use only if you troubleshoot the command itself. Best Practice - If you use this parameter, then redirect the output to a file, or use the script command to save the entire CLI session.
on	Starts the ICA Management Tool.
off	Stops the ICA Management Tool.
add	Adds the specified administrator, user, or custom user that is permitted to use the ICA Management Tool.
remove	Removes the specified administrator, user, or custom user that is permitted to use the ICA Management Tool.
clean	Removes all administrators, users, or custom users that are permitted to use the ICA Management Tool.
print	Shows the configured administrators, users, or custom users that are permitted to use the ICA Management Tool.

Parameter	Description
-p <ca port<br="">number></ca>	Optional. Specifies the TCP port on the Security Management Server or Domain Management Server, which is used to connect to the Certificate Authority. The default TCP port number is 18265.
-a <administrator DN></administrator 	Optional. Specifies the DN of the administrator that is permitted to use the ICA Management Tool. Must specify the full DN as appears in SmartConsole
	Procedure
	 Open Object Explorer > Users Open the Administrator object or a User object properties Click the Certificates pane Select the certificate and click the pencil icon Click View certificate details In the Certificate Info window, click the Details tab Click the Subject field Concatenate all fields
	-a "CN=ICA_Tool_Admin,OU=users,O=MGMT.s6t98x"
-u < <i>User DN</i> >	Optional. Specifies the DN of the user that is permitted to use the ICA Management Tool. Must specify the full DN as appears in SmartConsole:
	Procedure
	 Open Object Explorer > Users Open the Administrator object or a User object properties Click the Certificates pane Select the certificate and click the pencil icon Click View certificate details In the Certificate Info window, click the Details tab Click the Subject field Concatenate all fields
	Example:
	-u "CN=ICA_Tool_User,OU=users,O=MGMT.s6t98x"

Parameter	Description
-c <custom User DN></custom 	Optional. Specifies the DN for the custom user that is permitted to use the ICA Management Tool. Must specify the full DN as appears in SmartConsole. Procedure
	 Open Object Explorer > Users Open the Administrator object or a User object properties Click the Certificates pane Select the certificate and click the pencil icon Click View certificate details In the Certificate Info window, click the Details tab Click the Subject field Concatenate all fields
	Example: -c "CN=ICA_Tool_User,OU=users,O=MGMT.s6t98x"

• Note - If you run the "cpca_client set_mgmt_tool" command without the parameter "-a" or "-u", the list of the permitted administrators and users is not changed. The previously defined permitted administrators and users can start and stop the ICA Management Tool.

To connect to the ICA Management Tool

1. In SmartConsole, configure the required administrator and user objects.

You must create a certificate for these administrators and users.

You use this certificate to configure the permitted users in the ICA Management Tool and in the client web browsers.

2. In the command line on the Management Server, add the required administrators and users that are permitted to use the ICA Management Tool.

```
cpca_client set_mgmt_tool add ...
```

3. In the command line on the Management Server, start the ICA Management Tool.

```
cpca client set mgmt tool on
```

4. Check the status of the ICA Management Tool:

cpca_client set_mgmt_tool print

- 5. Import the administrator's / user's certificate into the Windows Certificate Store:.
 - a. Right-click the *.p12 file you saved when you created the required administrator / user, and click **Install PFX**.

The Certificate Import Wizard opens.

- b. In the Store Location section, select the applicable option:
 - Current User (this is the default)
 - Local Machine
- c. Click Next.
- d. Enter the same certificate password you used when you created the required administrator / user certificate.
- e. Clear Enable strong private key protection.
- f. Select Mark this key as exportable.
- g. Click Next.
- h. Select Place all certificates in the following store > click Browse > select Personal > click OK.
- i. Click Next.
- j. Click Finish.

6. In a web browser, connect to the ICA Management Tool:

https://<IP Address of the Management Server>:18265

- **Important** The fact that the TCP port 18265 is open is not a vulnerability. The ICA Management Tool Portal is secured and protected by SSL. In addition, only authorized administrators and users are allowed to access it using a certificate.
- 7. A dialog box with this message appears:

```
Client Authentication
Identification
The Web site you want to view requests identification.
Select the certificate to use when connecting.
```

- 8. Select the appropriate certificate for authenticating to the ICA Management Tool.
- 9. Click OK.
- 10. In the Security Alert dialog box, click Yes.

cpca_client set_sign_hash

Description

Sets the hash algorithm that the CA uses to sign the file hash. Also, see <u>sk103840</u>.

Note:

On a Multi-Domain Server, you must run this command in the context of the applicable Domain Management Server:

mdsenv <IP Address or Name of Domain Management Server>

Syntax

cpca_client [-d] set_sign_hash {sha1 | sha256 | sha384 | sha512}

Important - After this change, you must restart the Check Point services with these commands:

- On Security Management Server, run:
 - 1. cpstop
 - 2. cpstart
- On a Multi-Domain Server, run:
 - 1. mdsstop_customer <Name or IP Address of Domain
 Management Server>
 - 2. mdsstart_customer <Name or IP Address of Domain
 Management Server>

Parameter	Description
-d	 Runs the command in debug mode. Use only if you troubleshoot the command itself. Best Practice - If you use this parameter, then redirect the output to a file, or use the script command to save the entire CLI session.
{sha1 sha256 sha384 sha512}	The hash algorithms that the CA uses to sign the file hash. The default algorithm is SHA-256.

Example

[Expert@MGMT:0]# cpca_client set_sign_hash sha256 You have selected the signature hash function SHA-256 WARNING: This hash algorithm is not supported in Check Point gateways prior to R71. WARNING: It is also not supported on older clients and SG80 R71. Are you sure? (y/n) y Internal CA signature hash changed successfully. Note that the signature on the Internal CA certificate has not changed, but this has no security implications. [Expert@MGMT:0]# [Expert@MGMT:0]# cpstop ; cpstart

cpca_create

Description

Creates new Check Point Internal Certificate Authority database.

Note:

On a Multi-Domain Server, you must run this command in the context of the applicable Domain Management Server:

mdsenv <IP Address or Name of Domain Management Server>

Syntax

```
cpca_create [-d] -dn <CA DN>
```

Parameter	Description
-d	 Runs the command in debug mode. Use only if you troubleshoot the command itself. Best Practice - If you use this parameter, then redirect the output to a file, or use the script command to save the entire CLI session.
-dn < <i>CA DN</i> >	Specifies the Certificate Authority Distinguished Name (DN).


cpconfig

Description

This command starts the Check Point Configuration Tool.

This utility configures specific settings for the installed Check Point products.

Syntax



• Note - On a Multi-Domain Server, run the "mdsconfig" command.

Menu Options

1 Note - The options shown depend on the configuration and installed products.

Menu Option	Description
Licenses and contracts	Manages Check Point licenses and contracts on this server.
Administrator	Configures Check Point system administrators for this server.
GUI Clients	Configures the GUI clients that can use SmartConsole to connect to this server.
SNMP Extension	Obsolete. Do not use this option anymore. To configure SNMP, see the <u><i>R82 Gaia Administration Guide</i></u> - Chapter System Management - Section SNMP.
Random Pool	Configures the RSA keys, to be used by Gaia Operating System.
Certificate Authority	Initializes the Internal Certificate Authority (ICA) and configures the Certificate Authority's (CA) Fully Qualified Domain Name (FQDN).
Certificate's Fingerprint	Shows the ICA's Fingerprint. This fingerprint is a text string derived from the server's ICA certificate. This fingerprint verifies the identity of the server when you connect to it with SmartConsole.
Automatic start of Check Point Products	Shows and controls which of the installed Check Point products start automatically during boot.
Exit	Exits from the Check Point Configuration Tool.

Example - Menu on a Security Management Server

cpinfo

Description

A utility that collects diagnostics data on your Check Point computer at the time of execution.

It is mandatory to collect these data when you contact <u>*Check Point Support*</u> about an issue on your Check Point server.

For more information, see <u>sk92739</u>.

cplic

Description

The ${\tt cplic}$ command manages Check Point licenses.

You can run this command in Gaia Clish or in the Expert mode.

License Management is divided into three types of commands:

Licensing Commands	Applies To	Description
Local licensing commands	Management Servers, Security Gateways and Cluster Members	You execute these commands locally on the Check Point computers.
Remote licensing commands	Management Servers only	You execute these commands on the Security Management Server or Domain Management Server. These changes affect the managed Security Gateways and Cluster Members.
License Repository commands	Management Servers only	You execute these commands on the Security Management Server or Domain Management Server. These changes affect the licenses stored in the local license repository.

Syntax for Local Licensing on a Management Server itself

cplic

Syntax for Remote Licensing on managed Security Gateways and Cluster Members

Syntax for License Database Operations on a Management Server

```
cplic [-d]
  {-h | -help}
  db_add <options>
  db_print <options>
  db_rm <options>
```

Parameter	Description
-d	 Runs the command in debug mode. Use only if you troubleshoot the command itself. Best Practice - If you use this parameter, then redirect the output to a file, or use the script command to save the entire CLI session.
{-h -help}	Shows the applicable built-in usage.
check <options></options>	Confirms that the license includes the feature on the local Security Gateway or Management Server. See "cplic check" on page 756.
contract <options></options>	Manages (deletes and installs) the Check Point Service Contract on the local Check Point computer. See "cplic contract" on page 758.
db_add < <i>options</i> >	Applies only to a Management Server. Adds licenses to the license repository on the Management Server. See "cplic db_add" on page 760.

Parameter	Description
db_print < <i>options</i> >	Applies only to a Management Server. Shows the details of Check Point licenses stored in the license repository on the Management Server. See "cplic db_print" on page 762.
db_rm < <i>options</i> >	Applies only to a Management Server. Removes a license from the license repository on the Management Server. See "cplic db_rm" on page 764.
del < <i>options</i> >	Deletes a Check Point license on a host, including unwanted evaluation, expired, and other licenses. See "cplic del" on page 765.
del <object Name> <options></options></object 	Detaches a Central license from a remote managed Security Gateway or Cluster Member. See "cplic del <object name="">" on page 766.</object>
get < <i>options</i> >	Applies only to a Management Server. Retrieves all licenses from managed Security Gateways and Cluster Members into the license repository on the Management Server. See <i>"cplic get" on page 767</i> .
print <options></options>	Prints details of the installed Check Point licenses on the local Check Point computer. See " <i>cplic print</i> " on page 769.
put < <i>options</i> >	Installs and attaches licenses on a Check Point computer. See "cplic put" on page 771.
put <object Name> <options></options></object 	Attaches one or more Central or Local licenses to a remote managed Security Gateways and Cluster Members. See "cplic put <object name="">" on page 774.</object>
upgrade < <i>options</i> >	Applies only to a Management Server. Upgrades licenses in the license repository with licenses in the specified license file. See <i>"cplic upgrade" on page</i> 777.

cplic check

Description

Confirms that the license includes the feature on the local Security Gateway or Management Server. See <u>sk66245</u>.

Syntax

```
cplic check {-h | -help}
cplic [-d] check [-p <Product>] [-v <Version>] [{-c | -count}] [-t
<Date>] [{-r | -routers}] [{-S | -SRusers}] <Feature>
```

You can run this command:

- On a Management Server / Security Gateway / Cluster Member in Gaia Clish or the Expert mode
- On a Scalable Platform Security Group in Gaia gClish or the Expert mode

Parameters	
------------	--

Parameter	Description
{-h - help}	Shows the applicable built-in usage.
-d	 Runs the command in debug mode. Use only if you troubleshoot the command itself. Best Practice - If you use this parameter, then redirect the output to a file, or use the script command to save the entire CLI session.
-p <product></product>	 Product, for which license information is requested. Some examples of products: fw1 - FireWall-1 infrastructure on Security Gateway / Cluster Member / Security Group (all Software Blades), or Management Server (all Software Blades) mgmt - Multi-Domain Server infrastructure services - Entitlement for various services cvpn - Mobile Access etm - QoS (FloodGate-1) eps - Endpoint Software Blades on Management Server
-v <version></version>	Product version, for which license information is requested.

Parameter	Description
{-c - count}	Outputs the number of licenses connected to this feature.
-t <date></date>	Checks license status on future date. Use the format ddmmyyyy . A feature can be valid on a given date on one license, but invalid on another.
{-r - routers}	Checks how many routers are allowed. The <feature> option is not needed.</feature>
{-S - SRusers}	Checks how many SecuRemote users are allowed.
<feature></feature>	Feature, for which license information is requested.

Example from a Management Server

```
[Expert@MGMT]# cplic print -p
Host Expiration Primitive-Features
W.X.Y.Z 24Mar2016 ::CK-XXXXXXXXX fwl:6.0:swb fwl:6.0:comp fwl:6.0:compunlimited fwl:6.0:cluster-1 fwl:6.0:cpxmgmt_qos_u_sites
fwl:6.0:sprounl fwl:6.0:nxunlimit fwl:6.0:swp evnt:6.0:smrt_evnt fwl:6.0:fwc fwl:6.0:ca fwl:6.0:rtmui fwl:6.0:sstui fwl:6.0:fwlv
fwl:6.0:cmd evnt:6.0:alzd5 evnt:6.0:alzc1 evnt:6.0:alzs1 fwl:6.0:sstui fwl:6.0:fwlv fwl:6.0:sme10 etm:6.0:rtm_u fwl:6.0:cep1 fwl:6.0:rt
fwl:6.0:cemid fwl:6.0:web_sec_u fwl:6.0:workflow fwl:6.0:raml fwl:6.0:routers fwl:6.0:supmgmt fwl:6.0:supunlimit fwl:6.0:prov
fwl:6.0:atlas-unlimit fwl:6.0:filter fwl:6.0:ui psmp:6.0:psmsunlimited fwl:6.0:vpe_unlimit fwl:6.0:cluster-u fwl:6.0:remotel fwl:6.0:abkmp fwl:6.0:dbvr_unlimit fwl:6.0:rtmmgmt fwl:6.0:fgmgmt fwl:6.0:blades
fwl:6.0:cpipv6 fwl:6.0:rdmgmtha fwl:6.0:remote
[Expert@MGMT]#
```

Example from a Management Server in High Availability

```
[Expert@MGMT]# cplic check -p fwl -v 6.0 -c mgmtha
cplic check 'mgmtha': 1 licenses
[Expert@MGMT]#
```

cplic contract

Description

Deletes the Check Point Service Contract on the local Check Point computer.

Installs the Check Point Service Contract on the local Check Point computer.



- For more information about Service Contract files, see <u>sk33089</u>: What is a <u>Service Contract File?</u>
- If you install a Service Contract on a managed Security Gateway / Cluster Member / Scalable Platform Security Group, you must update the license repository on the applicable Management Server - either with the "cplic get" on page 767 command, or in SmartUpdate.

Syntax

You can run this command:

- On a Management Server / Security Gateway / Cluster Member in Gaia Clish or the Expert mode
- On a Scalable Platform Security Group in Gaia gClish or the Expert mode

Parameter	Description
{-h -help}	Shows the applicable built-in usage.
-d	 Runs the command in debug mode. Use only if you troubleshoot the command itself. Best Practice - If you use this parameter, then redirect the output to a file, or use the script command to save the entire CLI session.
del	Deletes the Service Contract from the \$CPDIR/conf/cp.contract file on the local Check Point computer.
put	Merges the Service Contract to the <pre>\$CPDIR/conf/cp.contract</pre> file on the local Check Point computer.
<service Contract ID></service 	ID of the Service Contract.
{-o - overwrite}	Specifies to overwrite the current Service Contract.
<service Contract File></service 	Path to and the name of the Service Contract file. First, you must download the Service Contract file from your <u>Check</u> <u>Point User Center</u> account.

cplic db_add

Description

Adds licenses to the license repository on the Management Server.

When you add Local licenses to the license repository, Management Server automatically attaches them to the managed Security Gateway / Cluster Member with the matching IP address.

When you add Central licenses, you must manually attach them.

Wote - You get the license details in the <u>Check Point User Center</u>.

Syntax

cplic db_add {-h | -help}
cplic [-d] db_add -1 <License File> [<Host>] [<Expiration Date>]
[<Signature>] [<SKU/Features>]

Parameter	Description
{-h -help}	Shows the applicable built-in usage.
-d	 Runs the command in debug mode. Use only if you troubleshoot the command itself. Best Practice - If you use this parameter, then redirect the output to a file, or use the script command to save the entire CLI session.
-l <license File></license 	Name of the file that contains the license.
<host></host>	Hostname or IP address of the Security Management Server / Domain Management Server.
<expiration Date></expiration 	The license expiration date.
<signature></signature>	The license signature string. For example: aa6uwknDc-CE6CRtjhv-zipoVWSnm-z98N7Ck3m Case sensitive. Hyphens are optional.

Parameter	Description
<	The SKU of the license summarizes the features included in the license.
SKU/Features>	For example, CPSUITE-EVAL-3DES-vNG

Example

If the file 192.0.2.11.lic contains one or more licenses, the command "cplic db_add - 1 192.0.2.11.lic" produces output similar to:

```
[Expert@MGMT]# cplic db_add -l 192.0.2.11.lic
Adding license to database ...
Operation Done
[Expert@MGMT]#
```

cplic db_print

Description

Shows the details of Check Point licenses stored in the license repository on the Management Server.

Syntax

```
cplic db_print {-h | -help}
cplic [-d] db_print {<Object Name> | -all} [{-n | -noheader}] [-x]
[{-t | -type}] [{-a | -attached}]
```

Parameter	Description
{-h - help}	Shows the applicable built-in usage.
-d	 Runs the command in debug mode. Use only if you troubleshoot the command itself. Best Practice - If you use this parameter, then redirect the output to a file, or use the script command to save the entire CLI session.
<object Name></object 	Prints only the licenses attached to <object name="">. <object name=""> is the name of the Security Gateway / Cluster Member object as defined in SmartConsole.</object></object>
-all	Prints all the licenses in the license repository.
{-n - noheader}	Prints licenses with no header.
-x	Prints licenses with their signatures.
{-t - type}	Prints licenses with their type: Central or Local.
{-a - attached}	Shows to which object the license is attached. Useful, if the parameter "-all" is specified.

Example

```
[Expert@MGMT:0] # cplic db print -all
Retrieving license information from database ...
The following licenses appear in the database:
_____
Host
          Expiration Features
[Expert@MGMT:0]#
[Expert@MGMT:0]# cplic db_print -all -x -a
Retrieving license information from database ...
The following licenses appear in the database:
_____
Host
           Expiration Features
192.168.3.28 25Aug2019 xxxxxxxxxxxxxxxxxxxxxxxxx CPMP-XXX CK-XXXXXXXXXXX MGMT
[Expert@MGMT:0]#
```

cplic db_rm

Description

Removes a license from the license repository on the Management Server.

After you remove the license from the repository, it can no longer use it.

Warning - You can run this command ONLY after you detach the license with the "cplic del" on page 765 command.

Syntax

```
cplic db_rm {-h | -help}
cplic [-d] db_rm <Signature>
```

Parameters

Parameter	Description
{-h - help}	Shows the applicable built-in usage.
-d	 Runs the command in debug mode. Use only if you troubleshoot the command itself. Best Practice - If you use this parameter, then redirect the output to a file, or use the script command to save the entire CLI session.
<signature></signature>	The signature string within the license. To see the license signature string, run the <i>"cplic print" on page 769</i> command.

Example

[Expert@MGMT:0]# cplic db_rm 2f540abb-d3bcb001-7e54513e-kfyigpwn

cplic del

Description

Deletes a Check Point license on a host, including unwanted evaluation, expired, and other licenses.

This command can delete a license on both local computer, and on remote managed computers.

Syntax

```
cplic del {-h | -help}
cplic [-d] del [-F <Output File>] <Signature> <Object Name>
```

You can run this command:

- On a Management Server / Security Gateway / Cluster Member in Gaia Clish or the Expert mode
- On a Scalable Platform Security Group in Gaia gClish or the Expert mode

Parameter	Description
{-h -help}	Shows the applicable built-in usage.
-d	 Runs the command in debug mode. Use only if you troubleshoot the command itself. Best Practice - If you use this parameter, then redirect the output to a file, or use the script command to save the entire CLI session.
-F <output File></output 	Saves the command output to the specified file.
<signature></signature>	The signature string within the license. To see the license signature string, run the <i>"cplic print" on page 769</i> command.
<object Name></object 	The name of the Security Gateway / Cluster Member object as configured in SmartConsole.

cplic del <object name>

Description

Detaches a Central license from a remote managed Security Gateway or Cluster Member.

When you run this command, it automatically updates the license repository.

The Central license remains in the license repository as an unattached license.

Syntax

```
cplic del {-h | -help}
cplic [-d] del <Object Name> [-F <Output File>] [-ip <Dynamic IP
Address>] <Signature>
```

Parameter	Description
{-h -help}	Shows the applicable built-in usage.
-d	 Runs the command in debug mode. Use only if you troubleshoot the command itself. Best Practice - If you use this parameter, then redirect the output to a file, or use the <u>script</u> command to save the entire CLI session.
<object name=""></object>	The name of the Security Gateway / Cluster Member object as defined in SmartConsole.
-F < <i>Output File</i> >	Saves the command output to the specified file.
-ip <dynamic ip<br="">Address></dynamic>	Deletes the license on the DAIP Security Gateway with the specified IP address. Note - If this parameter is used, then object name must be a DAIP Security Gateway.
<signature></signature>	The signature string within the license. To see the license signature string, run the <i>"cplic print" on page 769</i> command.

cplic get

Description

Retrieves all licenses from managed Security Gateways and Cluster Members into the license repository on the Management Server.

This command helps synchronize the license repository with the managed Security Gateways and Cluster Members.

When you run this command, it updates the license repository with all local changes.

Syntax

```
cplic get {-h | -help}
cplic [-d] get
    -all
    <IP Address>
    <Host Name>
```

Parameter	Description
{-h - help}	Shows the applicable built-in usage.
-d	 Runs the command in debug mode. Use only if you troubleshoot the command itself. Best Practice - If you use this parameter, then redirect the output to a file, or use the script command to save the entire CLI session.
-all	Retrieves licenses from all Security Gateways and Cluster Members in the managed network.
<ip Address></ip 	The IP address of the Security Gateway / Cluster Member, from which licenses are to be retrieved.
<host Name></host 	The name of the Security Gateway / Cluster Member object as defined in SmartConsole, from which licenses are to be retrieved.

Example

If the Security Gateway with the object name MyGW contains four Local licenses, and the license repository contains two other Local licenses, the command "cplic get MyGW" produces output similar to this:

```
[Expert@MGMT:0]# cplic get MyGW
Get retrieved 4 licenses.
Get removed 2 licenses.
[Expert@MGMT:0]#
```

cplic print

Description

Prints details of the installed Check Point licenses on the local Check Point computer.

Note - On a Security Gateway / Cluster Member / Scalable Platform Security Group, this command prints all installed licenses (both Local and Central).

Syntax

```
cplic print {-h | -help}
cplic [-d] print[{-n | -noheader}] [-x] [{-t | -type}] [-F <Output
File>] [{-p | -preatures}] [-D]
```

You can run this command:

- On a Management Server / Security Gateway / Cluster Member in Gaia Clish or the Expert mode
- On a Scalable Platform Security Group in Gaia gClish or the Expert mode

Parameter	Description
{-h -help}	Shows the applicable built-in usage.
-d	 Runs the command in debug mode. Use only if you troubleshoot the command itself. Best Practice - If you use this parameter, then redirect the output to a file, or use the script command to save the entire CLI session.
{-n -noheader}	Prints licenses with no header.
-x	Prints licenses with their signature.
{-t -type]	Prints licenses showing their type: Central or Local.
-F < <i>Output File</i> >	Saves the command output to the specified file.
{-p -preatures}	Prints licenses resolved to primitive features.
- D	On a Multi-Domain Server, prints only Domain licenses.

Example 1

Example 2

cplic put

Description

Installs one or more Local licenses on a Check Point computer.

Note - You get the license details in the <u>Check Point User Center</u>.

Syntax

```
cplic put {-h | -help}
cplic [-d] put [{-o | -overwrite}] [{-c | -check-only}] [{-s | -
select}] [-F <Output File>] [{-P | -Pre-boot}] [{-k | -kernel-
only}] -1 <License File> [<Host>] [<Expiration Date>]
[<Signature>] [<SKU/Features>]
```

You can run this command:

- On a Management Server / Security Gateway / Cluster Member in Gaia Clish or the Expert mode
- On a Scalable Platform Security Group in Gaia gClish or the Expert mode

Parameter	Description
{-h -help}	Shows the applicable built-in usage.
-d	 Runs the command in debug mode. Use only if you troubleshoot the command itself. Best Practice - If you use this parameter, then redirect the output to a file, or use the script command to save the entire CLI session.
<pre>{-o - overwrite}</pre>	On a Security Gateway / Cluster Member / Scalable Platform Security Group, this command erases only the local licenses, but not central licenses that are installed remotely.
<pre>{-c -check- only}</pre>	Verifies the license. Checks if the IP of the license matches the Check Point computer and if the signature is valid.
{-s - select}	Selects only the local license whose IP address matches the IP address of the Check Point computer.

Parameter	Description
-F <output File></output 	Saves the command output to the specified file.
{-P -Pre- boot}	Use this option after you have upgraded and before you reboot the Check Point computer. Use of this option will prevent certain error messages.
{-K - kernel-only}	Pushes the current valid licenses to the kernel. For use by Check Point Support only.
-l <license File></license 	Name of the file that contains the license.
<host></host>	Hostname or IP address of the Security Gateway / Cluster Member / Scalable Platform Security Group for a local license. Hostname or IP address of the Security Management Server / Domain Management Server for a central license.
<expiration Date></expiration 	The license expiration date.
<signature></signature>	The signature string within the license. Case sensitive. The hyphens are optional.
< SKU/Features>	The SKU of the license summarizes the features included in the license. For example: CPSUITE-EVAL-3DES-vNG

Copy and paste the parameters from the license received from the User Center:

Parameter	Description	
host	The IP address of the external interface (in quad-dot notation). The last part cannot be 0 or 255.	
expiration date	The license expiration date. It can be never.	
signature	The license signature string. Case sensitive. The hyphens are optional.	
SKU/features	A string listing the SKU and the Certificate Key of the license. The SKU of the license summarizes the features included in the license. For example: CPSB-SWB CPSB-ADNC-M CK0123456789ab	

Example

```
[Expert@HostName:0]# cplic put -1 License.lic
Host Expiration SKU
192.168.2.3 14Jan2016 CPSB-SWB CPSB-ADNC-M CK0123456789ab
[Expert@HostName:0]#
```

cplic put <object name>

Description

Attaches one or more Central or Local licenses to a remote managed Security Gateways and Cluster Members.

When you run this command, it automatically updates the license repository.

Note

- You get the license details in the <u>Check Point User</u> <u>Center</u>.
- You can attach more than one license.

[<Signature>] [<SKU/Feature>]

Syntax

```
cplic put {-h | -help}
cplic [-d] put <Object Name> [-ip<Dynamic IP Address> ] [-F
<Output File>] -1 <License File> [<Host>] [<Expiration Date>]
```

Parameter	Description		
{-h -help}	Shows the applicable built-in usage.		
-d	 Runs the command in debug mode. Use only if you troubleshoot the command itself. Best Practice - If you use this parameter, then redirect the output to a file, or use the script command to save the entire CLI session. 		
<object name=""></object>	The name of the Security Gateway / Cluster Member object, as defined in SmartConsole.		
-ip <dynamic IP Address></dynamic 	 Installs the license on the Security Gateway with the specified IP address. This parameter is used to install a license on a Security Gateway with dynamically assigned IP address (DAIP). Note - If you use this parameter, then the object name must be that of a DAIP Security Gateway. 		
-F <output File></output 	Saves the command output to the specified file.		
-l <license File></license 	Installs the licenses from the <i><license file=""></license></i> .		
<host></host>	Hostname or IP address of the Security Management Server / Domain Management Server.		
<expiration Date></expiration 	The license expiration date.		
<signature></signature>	The license signature string. Case sensitive. The hyphens are optional.		
< <i>SKU/Features</i> >	The SKU of the license summarizes the features included in the license. For example: CPSUITE-EVAL-3DES-VNG		

Copy and paste the parameters from the license received from the User Center:

Parameter	Description	
host	The IP address of the external interface (in quad-dot notation). The last part cannot be 0 or 255.	
expiration date	The license expiration date. It can be never.	
signature	The license signature string. Case sensitive. The hyphens are optional.	
SKU/features	A string listing the SKU and the Certificate Key of the license. The SKU of the license summarizes the features included in the license. For example: CPSB-SWB CPSB-ADNC-M CK0123456789ab	

cplic upgrade

Description

Upgrades licenses in the license repository with licenses in the specified license file.

Note - You get this license file in the <u>Check Point User Center</u>.

Syntax

```
cplic upgrade {-h | -help}
cplic [-d] upgrade -l <Input File>
```

Parameters

Parameter	Description
{-h - help}	Shows the applicable built-in usage.
-l <input File></input 	Upgrades the licenses in the license repository and Check Point Security Gateways / Cluster Members to match the licenses in the specified file.

Example

This example explains the procedure to upgrade the licenses in the license repository.

There are two Software Blade licenses in the input file:

- One license does not match any license on a remote managed Security Gateway.
- The other license matches an NGX-version license on a managed Security Gateway that has to be upgraded.

Workflow in this example:

1. Upgrade the Security Management Server to the latest version.

Ensure that there is connectivity between the Security Management Server and the Security Gateways with the previous product versions.

2. Import all licenses into the license repository.

You can also do this after you upgrade the products on the remote Security Gateways.

3. Run this command:

cplic get -all

Example:

```
[Expert@MyMGMT]# cplic get -all
Getting licenses from all modules ...
MyGW:
Retrieved 1 licenses
```

4. To see all the licenses in the repository, run this command:

```
cplic db_print -all -a
```

Example:

5. In the <u>Check Point User Center</u>, view the licenses for the products that were upgraded from version NGX to a Software Blades license.

You can also create new upgraded licenses.

6. Download a file containing the upgraded licenses.

Only download licenses for the products that were upgraded from version NGX to Software Blades.

If you did not import the version NGX licenses into the repository, import the version NGX licenses now.

Use this command:

cplic get -all

8. Run the license upgrade command:

```
cplic upgrade -1 < Input File>
```

- The licenses in the downloaded license file and in the license repository are compared.
- If the certificate keys and features match, the old licenses in the repository and in the remote Security Gateways are updated with the new licenses.
- A report of the results of the license upgrade is printed.

cppkg

Description

Manages the SmartUpdate software packages repository on the Security Management Server.



R Important - Installing software packages with the SmartUpdate is not supported for Security Gateways running on Gaia OS.

Syntax

```
cppkg
      add <options>
      {del | delete} <options>
      get
      getroot
      print
      setroot <options>
```

Notes:

- You can run this command only in the Expert mode.
- On a Multi-Domain Server, you must run this command in the context of the MDS (run mdsenv).

Parameter	Description	
add < <i>options</i> >	Adds a SmartUpdate software package to the repository. See " <i>cppkg add</i> " on page 781.	
{del delete} <options></options>	Deletes a SmartUpdate software package from the repository. See <i>"ppkg delete" on page 782</i> .	
get	Updates the list of the SmartUpdate software packages in the repository. See <i>"cppkg get" on page 784</i> .	
getroot	Shows the path to the root directory of the repository (the value of the environment variable \$SUROOT). See "cppkg getroot" on page 785.	
print	Prints the list of SmartUpdate software packages in the repository. See " <i>cppkg print</i> " on page 786.	
setroot < <i>options</i> >	Configures the path to the root directory of the repository. See "cppkg setroot" on page 787.	

cppkg add

Description

Adds a SmartUpdate software package to the SmartUpdate software packages repository.

Notes:

- You can run this command only in the Expert mode.
- On a Multi-Domain Server, you must run this command in the context of the MDS (run the mdsenv command).
- This command does not overwrite existing packages. To overwrite an existing package, you must first delete the existing package.
- You get the SmartUpdate software packages from the <u>Check Point Support</u> <u>Center</u>.

Syntax

cppkg add <Full Path to Package | DVD Drive [Product]>

Parameters

Parameter	Description
<full path="" to<br="">Package></full>	Specifies the full local path on the computer to the SmartUpdate software package.
DVD Drive [Product]	Specifies the DVD root path. Example: /mnt/CPR80

Example - Adding R77.20 HFA_75 (R77.20.75) firmware package for 1100 Appliances

[Expert@MGMT:0] Vendor	# cppkg print Product	Version	OS	Minor Version
[Expert@MGMT:0]	#			
<pre>[Expert@MGMT:0]# cppkg add /var/log/CP1100_6.0_4_0tgz Adding package to the repository Getting the package type Extracting the package files Copying package to the repository Package was successfully added to the repository [Expert@MGMT:0]#</pre>				
[Expert@MGMT:0] Vendor		Version	OS	Minor Version
Check Point [Expert@MGMT:0]		R77.20Gaia	Embedded	R77.20

ppkg delete

Description

Deletes SmartUpdate software packages from the SmartUpdate software packages repository.



- You can run this command only in the Expert mode.
- On a Multi-Domain Server, you must run this command in the context of the MDS (run the mdsenv command).

Syntax

```
cppkg del ["<Vendor>" "<Product>" "<Major Version>" "<OS>" "<Minor
Version>"]
cppkg delete ["<Vendor>" "<Product>" "<Major Version>" "<OS>"
```

```
"<Minor Version>"]
```

Parameters

Parameter	Description	
del delete	When you do not specify optional parameters, the command runs in the interactive mode. The command shows the menu with applicable options.	
" <vendor>"</vendor>	Specifies the package vendor. Enclose in double quotes.	
"< Product>"	Specifies the product name. Enclose in double quotes.	
" <major Version>"</major 	Specifies the package Major Version. Enclose in double quotes.	
"< <i>OS</i> >"	Specifies the package OS. Enclose in double quotes.	
" <minor Version>"</minor 	Specifies the package Minor Version. Enclose in double quotes.	

Notes:

- To see the values for the optional parameters, run the "cppkg print" on page 786 command.
- You must specify all optional parameters, or no parameters.

Example 1 - Interactive mode

Example 2 - Manually deleting the specified package

cppkg get


Description

Updates the list of the SmartUpdate software packages in the SmartUpdate software packages repository based on the real content of the repository.

Notes:

- You can run this command only in the Expert mode.
- On a Multi-Domain Server, you must run this command in the context of the MDS (run the mdsenv command).

Syntax



Example

[Expert@MGMT:0]# cppkg get		
Update successfully completed		
[Expert@MGMT:0]#		

cppkg getroot

Description

Shows the path to the root directory of the SmartUpdate software packages repository (the value of the environment variable \$SUROOT)

Notes:

- You can run this command only in the Expert mode.
- On a Multi-Domain Server, you must run this command in the context of the MDS (run the mdsenv command).

Syntax

cppkg getroot

Example

```
[Expert@MGMT:0] # cppkg getroot
[cppkg 7119 4128339728]@MGMT[29 May 19:16:06] Current repository root is set to :
/var/log/cpupgrade/suroot
[Expert@MGMT:0] #
```

cppkg print

Description

Prints the list of SmartUpdate software packages in the SmartUpdate software packages repository.

Notes:

- You can run this command only in the Expert mode.
- On a Multi-Domain Server, you must run this command in the context of the MDS (run the mdsenv command).

Syntax

cppkg print

Example - R77.20 HFA_75 (R77.20.75) firmware package for 1100 Appliances

[Expert@MGMT:0]# cppkg print			
Vendor	Product	Version	OS	Minor Version
Check Point [Expert@MGMT:0	CP1100]#	R77.20Gaia	Embedded	R77.20

cppkg setroot

Description

Configures the path to the root directory of the SmartUpdate software packages repository.

Notes:

- You can run this command only in the Expert mode.
- On a Multi-Domain Server, you must run this command in the context of the MDS (run the mdsenv command).
- The default path is: /var/log/cpupgrade/suroot
- When changing repository root directory:
 - This command copies the software packages from the old repository to the new repository. A package in the new location is overwritten by a package from the old location, if the packages have the same name.
 - This command updates the value of the environment variable \$SUROOT in the Check Point Profile shell scripts (\$CPDIR/tmp/.CPprofile.sh and \$CPDIR/tmp/.CPprofile.csh).

Syntax

cppkg setroot <Full Path to Repository Root Directory>

Example

cpprod_util

Description

This utility works with Check Point Registry (\$CPDIR/registry/HKLM_registry.data) without manually opening it:

- Shows which Check Point products and features are enabled on this Check Point computer.
- Enables and disables Check Point products and features on this Check Point computer.

Syntax on a Management Server in Gaia Clish or the Expert mode

```
cpprod_util CPPROD_GetValue "<Product>" "<Parameter>" {0|1}
cpprod_util CPPROD_SetValue "<Product>" "<Parameter>" {1|4}
"<Value>" {0|1}
cpprod_util -dump
```

Parameter	Description
CPPROD_ GetValue	 Gets the configuration status of the specified product or feature: 0 - Disabled 1 - Enabled
CPPROD_ SetValue	Sets the configuration for the specified product or feature. Important - Do not run these commands unless explicitly instructed by Check Point Support or R&D to do so.
"< Product>"	Specifies the product or feature.
"< Parameter >"	Specifies the configuration parameter for the specified product or feature.
" <value>"</value>	 Specifies the value of the configuration parameter for the specified product or feature: One of these integers: 0, 1, 4 A string
dump	Creates a dump file of the Check Point Registry (\$CPDIR/registry/HKLM_registry.data) in the current working directory. The name of the output file is RegDump.

Notes

- If you run the "cpprod util" command without parameters, it prints:
 - The list of all available products and features (for example, "FwIsFirewallMgmt", "FwIsLogServer", "FwIsStandAlone")
 - The type of the expected argument when you configure a product or feature ("noparameter", "string-parameter", or "integer-parameter")
 - The type of the returned output ("status-output", or "no-output")
- To redirect the output of the "cpprod_util" command, it is necessary to redirect the stderr to stdout.

cpprod util <options> > <output file> 2>&1

Example:

cpprod_util > /tmp/output_of_cpprod_util.txt 2>&1

Examples

Example - Showing a list of all installed Check Point Products Packages on a Management Server

[Expert@MGMT:0]# cpprod uti	1 CPPROD GetInstalledProducts
CPFC	—
IDA	
MGMT	
FW1	
SecurePlatform	
NGXCMP	
EdgeCmp	
SFWCMP	
SFWR75CMP	
SFWR77CMP	
FLICMP	
R75CMP	
R7520CMP	
R7540CMP	
R76CMP	
R77CMP	
PROVIDER-1	
Reporting Module	
SmartLog	
CPinfo	
VSEC	
DIAG	
[Expert@MGMT:0]#	
1	

Example - Checking if this Check Point computer is configured as a Management Server

[Expert@MGMT:0]# cpprod_util FwIsFirewallMgmt
1
[Expert@MGMT:0]#

Example - Checking if this Check Point computer is configured as a Standalone

[Expert@MGMT:0]# cpprod_util FwIsStandAlone
0
[Expert@MGMT:0]#

Example - Checking if this Management Server is configured as a Primary in High Availability

```
[Expert@MGMT:0]# cpprod_util FwIsPrimary
1
[Expert@MGMT:0]#
```

Example - Checking if this Management Server is configured as Active in High Availability

```
[Expert@MGMT:0]# cpprod_util FwIsActiveManagement
1
[Expert@MGMT:0]#
```

Example - Checking if this Management Server is configured as Backup in High Availability

```
[Expert@MGMT:0]# cpprod_util FwIsSMCBackup
1
[Expert@MGMT:0]#
```

Example - Checking if this Check Point computer is configured as a dedicated Log Server

```
[Expert@MGMT:0]# cpprod_util FwIsLogServer
1
[Expert@MGMT:0]#
```

Example - Checking if on this Management Server the SmartProvisioning blade is enabled

```
[Expert@MGMT:0]# cpprod_util FwIsAtlasManagement
1
[Expert@MGMT:0]#
```

Example - Checking if on this Management Server the SmartEvent Server blade is enabled

```
[Expert@MGMT:0]# cpprod_util RtIsAnalyzerServer
1
[Expert@MGMT:0]#
```

Example - Checking if on this Management Server the SmartEvent Correlation Unit blade is enabled

```
[Expert@MGMT:0]# cpprod_util RtIsAnalyzerCorrelationUnit
1
[Expert@MGMT:0]#
```

Example - Checking if on this Management Server the Endpoint Policy Management blade is enabled

```
[Expert@MGMT:0]# cpprod_util UepmIsInstalled
1
[Expert@MGMT:0]#
```

Example - Checking if this Management Server is configured as Endpoint Policy Server

[Expert@MGMT:0]# cpprod_util UepmIsPolicyServer
0
[Expert@MGMT:0]#

cprid

Description

Manages the Check Point Remote Installation Daemon (cprid).

This daemon is used for remote upgrade and installation of Check Point products on the managed Security Gateways.



- You can run this command only in the Expert mode.
- On a Multi-Domain Server, you must run these commands in the context of the MDS (run mdsenv).

Commands

Syntax	Description
cpridstart	Starts the Check Point Remote Installation Daemon (cprid).
cpridstop	Stops the Check Point Remote Installation Daemon (cprid).
run_cprid_ restart	Stops and then starts the Check Point Remote Installation Daemon (cprid).

cprinstall

Description

Performs installation of Check Point product packages and associated operations on remote managed Security Gateways.

8

Important - Installing software packages with this command is not supported for Security Gateways that run on Gaia OS.

Notes:

- This command requires a license for SmartUpdate.
- You can run this command only in the Expert mode.
- On a Multi-Domain Server, you must run this command in the context of the applicable Domain Management Server:

```
mdsenv <IP Address or Name of Domain Management Server>
```

- On the remote Security Gateways these are required:
 - SIC Trust must be established between the Security Management Server and the Security Gateway.
 - The cpd daemon must run.
 - The cprid daemon must run.

Syntax

cprinstall
 boot <options>
 cprestart <options>
 cpstart <options>
 cpstop <options>
 delete <options>
 get <options>
 install <options>
 revert <options>
 show <options>
 snapshot <options>
 transfer <options>
 uninstall <options>
 uninstall <options>
 verify <options>

Parameter	Description
boot	Reboots the managed Security Gateway.
< <i>options</i> >	See <i>"cprinstall boot" on page 797</i> .
cprestart	Runs the cprestart command on the managed Security Gateway.
< <i>options</i> >	See "cprinstall cprestart" on page 798.
cpstart	Runs the cpstart command on the managed Security Gateway.
< <i>options</i> >	See "cprinstall cpstart" on page 799.
cpstop	Runs the cpstop command on the managed Security Gateway.
< <i>options</i> >	See "cprinstall cpstop" on page 800.
delete	Deletes a snapshot (backup) file on the managed Security Gateway.
<options></options>	See "cprinstall delete" on page 801.
get < <i>options</i> >	 Gets details of the products and the operating system installed on the managed Security Gateway. Updates the management database on the Security Management Server.
	See "cprinstall get" on page 802.
install < <i>options</i> >	Installs Check Point products on the managed Security Gateway. See "cprinstall install" on page 803.
revert	Restores the managed Security Gateway that runs on SecurePlatform OS from a snapshot saved on that Security Gateway.
<options></options>	See "cprinstall revert" on page 806.
show	Displays all snapshot (backup) files on the managed Security Gateway that runs on SecurePlatform OS.
< <i>options</i> >	See "cprinstall show" on page 807.
snapshot < <i>options</i> >	Creates a snapshot on the managed Security Gateway that runs on SecurePlatform OS and saves it on that Security Gateway. See <i>"cprinstall snapshot" on page 808</i> .
transfer	Transfers a software package from the repository to the managed Security Gateway without installing the package.
<options></options>	See <i>"cprinstall transfer" on page 809</i> .
uninstall <options></options>	Uninstalls Check Point products on the managed Security Gateway. See "cprinstall uninstall" on page 811.

Parameter	Description
verify <options></options>	 Confirms these operations were successful: If a specific product can be installed on the managed Security Gateway. That the operating system and currently installed products the managed Security Gateway are appropriate for the software package. That there is enough disk space to install the product the managed Security Gateway. That there is a CPRID connection with the managed Security Gateway. See "cprinstall verify" on page 813.

cprinstall boot

Description

Reboots the managed Security Gateway.

Notes:

- You must run this command from the Expert mode.
- On a Multi-Domain Server, you must run this command in the context of the applicable Domain Management Server:

mdsenv <IP Address or Name of Domain Management Server>

Syntax

cprinstall boot <Object Name>

Parameters

Parameter	Description
<object Name></object 	The name of the Security Gateway object as configured in SmartConsole.

Example

[Expert@MGMT]# cprinstall boot MyGW

cprinstall cprestart

Description

Runs the cprestart command on the managed Security Gateway.



- You must run this command from the Expert mode.
- On a Multi-Domain Server, you must run this command in the context of the applicable Domain Management Server:

mdsenv <IP Address or Name of Domain Management Server>

 All Check Point products on the managed Security Gateway must be of the same version.

Syntax

cprinstall cprestart <Object Name>

Parameters

Parameter	Description
<object Name></object 	The name of the Security Gateway object as configured in SmartConsole.

Example

[Expert@MGMT:0]# cprinstall cprestart MyGW

cprinstall cpstart

Description

Runs the cpstart command on the managed Security Gateway.

Notes:

- You must run this command from the Expert mode.
- On a Multi-Domain Server, you must run this command in the context of the applicable Domain Management Server:

mdsenv <IP Address or Name of Domain Management Server>

 All Check Point products on the managed Security Gateway must be of the same version.

Syntax

cprinstall cpstart <Object Name>

Parameters

Parameter	Description
<object Name></object 	The name of the Security Gateway object as configured in SmartConsole.

Example

[Expert@MGMT]# cprinstall cpstart MyGW

cprinstall cpstop

Description

Runs the cpstop command on the managed Security Gateway.

Notes:

- You must run this command from the Expert mode.
- On a Multi-Domain Server, you must run this command in the context of the applicable Domain Management Server:

mdsenv <IP Address or Name of Domain Management Server>

 All Check Point products on the managed Security Gateway must be of the same version.

Syntax

cprinstall cpstop {-proc | -nopolicy} <Object Name>

Parameters

Parameter	Description
-proc	Kills the Check Point daemons and Security Servers, while it maintains the active Security Policy running in the Check Point kernel. Rules with generic <i>Allow</i> , <i>Drop</i> or <i>Reject</i> action based on services, continue to work.
-nopolicy	Kills the Check Point daemons and Security Servers and unloads the Security Policy from the Check Point kernel.
<object Name></object 	The name of the Security Gateway object as configured in SmartConsole.

Example

[Expert@MGMT]# cprinstall cpstop -proc MyGW

cprinstall delete

Description

Deletes a snapshot (backup) file on the managed Security Gateway that runs on SecurePlatform OS.



- You must run this command from the Expert mode.
- On a Multi-Domain Server, you must run this command in the context of the applicable Domain Management Server:

mdsenv <IP Address or Name of Domain Management Server>

Syntax

cprinstall delete <Object Name> <Snapshot File>

Parameters

Parameter	Description
<object name=""></object>	The name of the Security Gateway object as configured in SmartConsole.
<snapshot File></snapshot 	Specifies the name of the snapshot (backup) on SecurePlatform OS.

Example

[Expert@MGMT]# cprinstall delete MyGW Snapshot25Apr2017

cprinstall get

Description

- Gets details of the products and the operating system installed on the managed Security Gateway.
- Updates the management database on the Security Management Server.

Notes:

- You must run this command from the Expert mode.
- On a Multi-Domain Server, you must run this command in the context of the applicable Domain Management Server:

```
mdsenv <IP Address or Name of Domain Management Server>
```

Syntax

cprinstall get <Object Name>

Parameters

Parameter	Description
<object Name></object 	The name of the Security Gateway object as configured in SmartConsole.

Example:

```
[Expert@MGMT] # cprinstall get MyGW
Checking cprid connection...
Verified
Operation completed successfully
Updating machine information...
Update successfully completed
'Get Gateway Data' completed successfully
Operating system Major Version Minor Version
  -----
                                     _____
            R75.20R75.20
SecurePlatform
                     Major Version
Vendor
            Product
                                         Minor Version
_____
Check Point VPN-1 Power/UTM R75.20R75.20Check Point
                                                 SecurePlatform
R75.20R75.20Check Point SmartPortal R75.20R75.20
[Expert@MGMT]#
```

cprinstall install

Description

Installs Check Point products on the managed Security Gateway.

Important - Installing software packages with this command is not supported for Security Gateways that run Gaia OS.

Notes:

- Before transferring the software package, this command runs the "cprinstall verify" on page 813 command.
- On a Multi-Domain Server, you must run this command in the context of the applicable Domain Management Server:

```
mdsenv <IP Address or Name of Domain Management Server>
```

To see the values for the package attributes, run the "cppkg print" on page 786 command.

Syntax

```
cprinstall install [-boot] [-backup] [-skip_transfer] <Object
Name> "<Vendor>" "<Product>" "<Major Version>" "<Minor Version>"
```

Parameter	Description
-boot	Reboots the managed Security Gateway after installing the package. Note - Only reboot after ALL products have the same version. Reboot is canceled in certain scenarios.
-backup	Creates a snapshot on the managed Security Gateway before installing the package. Note - Only on Security Gateways that runs on SecurePlatform OS.
-skip_ transfer	Skip the transfer of the package.
<object Name></object 	The name of the Security Gateway object as configured in SmartConsole.
" <vendor>"</vendor>	<pre>Specifies the package vendor. Enclose in double quotes. Example: checkpoint Check Point</pre>
" <product>"</product>	<pre>Specifies the product name. Enclose in double quotes. Examples: SVNfoundation firewall floodgate CP1100 VPN-1 Power/UTM SmartPortal</pre>
" <major Version>"</major 	Specifies the package Major Version. Enclose in double quotes.
" <minor Version>"</minor 	Specifies the package Minor Version. Enclose in double quotes.

Example

[Expert@MGMT]# cprinstall install -boot MyGW "checkpoint" "firewall" "R75" "R75.20" Installing firewall R75.20 on MyGW... Info : Testing Check Point Gateway Info : Test completed successfully. Info : Transferring Package to Check Point Gateway Info : Extracting package on Check Point Gateway Info : Installing package on Check Point Gateway Info : Product was successfully applied. Info : Rebooting the Check Point Gateway Info : Checking boot status Info : Reboot completed successfully. Info : Checking Check Point Gateway Info : Operation completed successfully. [Expert@MGMT]#

cprinstall revert

Description

Restores the managed Security Gateway that runs on SecurePlatform OS from a snapshot saved on that Security Gateway.

Notes:

- You must run this command from the Expert mode.
- On a Multi-Domain Server, you must run this command in the context of the applicable Domain Management Server:

mdsenv <IP Address or Name of Domain Management Server>

Syntax

```
cprinstall revert <Object Name> <Snapshot File>
```

Parameter	Description
<object Name></object 	The name of the Security Gateway object as configured in SmartConsole.
<snapshot File></snapshot 	Name of the SecurePlatform snapshot file. To see the names of the saved snapshot files, run the " <i>cprinstall show</i> " on page 807 command.

cprinstall show

Description

Displays all snapshot (backup) files on the managed Security Gateway that runs on SecurePlatform OS.

Notes:

- You must run this command from the Expert mode.
- On a Multi-Domain Server, you must run this command in the context of the applicable Domain Management Server:

mdsenv <IP Address or Name of Domain Management Server>

Syntax

cprinstall show <Object Name>

Parameters

Parameter	Description
<object Name></object 	The name of the Security Gateway object as configured in SmartConsole.

Example

[Expert@MGMT]#	cprinstall	show	GW1
SU_backup.tzg			
[Expert@MGMT]#			

cprinstall snapshot

Description

Creates a snapshot on the managed Security Gateway that runs on SecurePlatform OS and saves it on that Security Gateway.

Notes:

- You must run this command from the Expert mode.
- On a Multi-Domain Server, you must run this command in the context of the applicable Domain Management Server:

mdsenv <IP Address or Name of Domain Management Server>

Syntax

cprinstall snapshot <Object Name> <Snapshot File>

Parameter	Description
<object Name></object 	The name of the Security Gateway object as configured in SmartConsole.
<snapshot File></snapshot 	Name of the SecurePlatform snapshot file. To see the names of the saved snapshot files, run the " <i>cprinstall show</i> " on page 807 command.

cprinstall transfer

Description

Transfers a software package from the repository to the managed Security Gateway without installing the package.



- You must run this command from the Expert mode.
- On a Multi-Domain Server, you must run this command in the context of the applicable Domain Management Server:

mdsenv <IP Address or Name of Domain Management Server>

To see the values for the package attributes, run the "cppkg print" on page 786 command.

Syntax

```
cprinstall transfer <Object Name> "<Vendor>" "<Product>" "<Major
Version>" "<Minor Version>"
```

Parameter	Description
<object name=""></object>	The name of the Security Gateway object as configured in SmartConsole.
" <vendor>"</vendor>	Specifies the package vendor. Enclose in double quotes. Example: checkpoint Check Point
" <product>"</product>	<pre>Specifies the product name. Enclose in double quotes. Examples: SVNfoundation firewall floodgate CP1100</pre>
" <major Version>"</major 	Specifies the package major version. Enclose in double quotes.
" <minor Version>"</minor 	Specifies the package minor version. Enclose in double quotes.

cprinstall uninstall

Description

Uninstalls Check Point products on the managed Security Gateway.

Important - Uninstalling software packages with this command is not supported for Security Gateways running on Gaia OS.

Notes:

- You must run this command from the Expert mode.
- On a Multi-Domain Server, you must run this command in the context of the applicable Domain Management Server:

```
mdsenv <IP Address or Name of Domain Management Server>
```

- Before uninstalling product packages, this command runs the "cprinstall verify" on page 813 command.
- After uninstalling a product package, you must run the "cprinstall get" on page 802 command.
- To see the values for the package attributes, run the *"cppkg print" on page 786* command.

Syntax

cprinstall uninstall [-boot] <Object Name> "<Vendor>" "<Product>"
"<Major Version>" "<Minor Version>"

Parameters

Parameter	Description	
-boot	Reboots the managed Security Gateway after uninstalling the package. Note - Reboot is canceled in certain scenarios.	
<object name=""></object>	The name of the Security Gateway object as configured in SmartConsole.	
" <vendor>"</vendor>	<pre>Specifies the package vendor. Enclose in double quotes. Example: checkpoint Check Point</pre>	
" <product>"</product>	<pre>Specifies the product name. Enclose in double quotes. Examples: SVNfoundation firewall floodgate CP1100</pre>	
" <major Version>"</major 	Specifies the package major version. Enclose in double quotes.	
" <minor Version>"</minor 	Specifies the package minor version. Enclose in double quotes.	

Example

[Expert@MGMT]# cprinstall uninstall MyGW "checkpoint" "firewall" "R75.20" "R75.20" Uninstalling firewall R75.20 from MyGW... Info : Removing package from Check Point Gateway Info : Product was successfully applied. Operation Success. Please get network object data to complete the operation. [Expert@MGMT]# [Expert@MGMT]#

cprinstall verify

Description

Confirms these operations were successful:

- If a specific product can be installed on the managed Security Gateway.
- That the operating system and currently installed products the managed Security Gateway are appropriate for the software package.
- That there is enough disk space to install the product the managed Security Gateway.
- That there is a CPRID connection with the managed Security Gateway.

```
Notes:
```

- You must run this command from the Expert mode.
- On a Multi-Domain Server, you must run this command in the context of the applicable Domain Management Server:

mdsenv <IP Address or Name of Domain Management Server>

• To see the values for the package attributes, run the *"cppkg print" on page 786* command.

Syntax

```
cprinstall verify <Object Name> "<Vendor>" "<Product>" "<Major
Version>" ["<Minor Version>"]
```

Parameters

Parameter	Description	
<object name=""></object>	The name of the Security Gateway object as configured in SmartConsole.	
" <vendor>"</vendor>	<pre>Specifies the package vendor. Enclose in double quotes. Example: checkpoint Check Point</pre>	
" <product>"</product>	<pre>Specifies the product name. Enclose in double quotes. Examples: SVNfoundation firewall floodgate CP1100 VPN-1 Power/UTM SmartPortal</pre>	
" <major Version>"</major 	Specifies the package major version. Enclose in double quotes.	
" <minor Version>"</minor 	Specifies the package minor version. Enclose in double quotes. This parameter is optional.	

Example 1 - Verification succeeds

```
[Expert@MGMT]# cprinstall verify MyGW "checkpoint" "SVNfoundation" "R75.20"
Verifying installation of SVNfoundation R75.20 on MyGW...
Info : Testing Check Point Gateway.
Info : Test completed successfully.
Info : Installation Verified, The product can be installed.
```

Example 2 - Verification fails

```
[Expert@MGMT]# cprinstall verify MyGW "checkpoint" "SVNfoundation" "R75.20"
Verifying installation of SVNfoundation R75.20 on MyGW...
Info : Testing Check Point Gateway
Info : SVN Foundation R75 is already installed on 192.0.2.134
Operation Success. Product cannot be installed, did not pass dependency check.
```

cpstart

Description

Manually starts all Check Point processes and applications.



- For the cprid daemon, use the "cprid" on page 793 command.
- For manually starting specific Check Point processes, see <u>sk97638</u>.

Syntax

cpstat

Description

Shows the status and statistics information for Check Point applications.

Syntax on a Management Server in Gaia Clish or the Expert mode

```
cpstat [-d] [-h <Host>] [-p <Port>] [-s <SICname>] [-f <Flavor>]
[-o <Polling Interval> [-c <Count>] [-e <Period>]] <Application
Flag>
```

I Note - You can write the parameters in the syntax in any order.

Parameter	Description
-d	 Runs the command in debug mode. Use only if you troubleshoot the command itself. Best Practice - If you use this parameter, then redirect the output to a file, or use the script command to save the entire CLI session. The output shows the SNMP queries and SNMP responses for the applicable SNMP OIDs.
-h < <i>Host</i> >	Optional. When you run this command on a Management Server, this parameter specifies the managed Security Gateway / ClusterXL object. < <i>Host</i> > is an IPv4 address, a resolvable hostname, or a DAIP object name. The default is localhost.
-p < <i>Port</i> >	Optional. Port number of the Application Monitoring (AMON) server. The default port is 18192.
-s <sicname></sicname>	Optional. Secure Internal Communication (SIC) name of the Application Monitoring (AMON) server.

Parameter	Description
-f <flavor></flavor>	Optional. Specifies the type of the information to collect. If you do not specify a flavor explicitly, the command uses the first flavor in the <application flag="">. To see all flavors, run the cpstat command without any parameters.</application>
-o <polling Interval></polling 	 Optional. Specifies the polling interval (in seconds) - how frequently the command collects and shows the information. Examples: 0 - The command shows the results only once and the stops (this is the default value). 5 - The command shows the results every 5 seconds in the loop. 30 - The command shows the results every 30 seconds in the loop. N - The command shows the results every N seconds in the loop. Use this parameter together with the "-c <count>" parameter and the "-e <period>" parameter.</period></count> Example:
-c <count></count>	 Optional. Specifies how many times the command runs and shows the results before it stops. You must use this parameter together with the "-o <polling interval="">" parameter.</polling> Examples: 0 - The command shows the results repeatedly every <polling interval=""> (this is the default value).</polling> 10 - The command shows the results 10 times every <polling interval=""> and then stops.</polling> 20 - The command shows the results 20 times every <polling interval=""> and then stops.</polling> N - The command shows the results N times every <polling interval=""> and then stops.</polling> N - The command shows the results N times every <polling interval=""> and then stops.</polling>

Parameter	Description
-e < <i>Period</i> >	Optional. Specifies the time (in seconds), over which the command calculates the statistics. You must use this parameter together with the "-o <polling Interval>" parameter. You can use this parameter together with the "-c <count>" parameter. Example: Cpstat os -f perf -o 2 -c 2 -e 60</count></polling
<application Flag></application 	Mandatory. See the table below with flavors for the application flags.

These flavors are available for the application flags

• Note - The available flags depend on the enabled Software Blades. Some flags are supported only by a Security Gateway / ClusterXL, and some flags are supported only by a Management Server.

Feature or Software Blade	Flag	Flavors
List of enabled Software Blades	blades	<pre>fw, ips, av, urlf, vpn, cvpn, aspm, dlp, appi, anti_bot, default, content_awareness, threat-emulation, default</pre>
Operating System	os	<pre>default, ifconfig, routing, routing6, memory, old_memory, cpu, disk, perf, multi_cpu, multi_disk, raidInfo, sensors, power_supply, hw_info, all, average_cpu, average_memory, statistics, updates, licensing, connectivity, vsx</pre>
Firewall	fw	<pre>default, interfaces, policy, perf, hmem, kmem, inspect, cookies, chains, fragments, totals, totals64, ufp, http, ftp, telnet, rlogin, smtp, pop3, sync, log_ connection, all</pre>

cpstat

Feature or Software Blade	Flag	Flavors
HTTPS Inspection	https_ inspection	default, hsm_status, all
Identity Awareness	identityServer	default, authentication, logins, ldap, components, adquery, idc, muh
Application Control	appi	<pre>default, subscription_status, update_status, RAD_status, top_ last_hour, top_last_day, top_last_ week, top_last_month</pre>
URL Filtering	urlf	<pre>default, subscription_status, update_status, RAD_status, top_ last_hour, top_last_day, top_last_ week, top_last_month</pre>
IPS	ips	default, statistics, all
Anti-Virus	ci	default
Threat Prevention	antimalware	<pre>default, scanned_hosts, scanned_ mails, subscription_status, update_status, ab_prm_contracts, av_prm_contracts, ab_prm_ contracts, av_prm_contracts</pre>

Feature or Software Blade	Flag	Flavors
Threat Emulation	threat- emulation	<pre>default, general_statuses, update_ status, scanned_files, malware_ detected, scanned_on_cloud, malware_on_cloud, average_process_ time, emulated_file_size, queue_ size, peak_size, file_type_stat_ file_scanned, file_type_stat_ malware_detected, file_type_stat_ cloud_scanned, file_type_stat_ cloud_malware_scanned, file_type_ stat_filter_by_analysis, file_ type_stat_cache_hit_rate, file_ type_stat_error_count, file_type_ stat_no_resource_count, contract, downloads_information_current, downloading_file_information, queue_table, history_te_incidents, history_te_comp_hosts</pre>
Threat Extraction	scrub	<pre>default, subscription_status, threat_extraction_statistics</pre>
Mobile Access	cvpn	cvpnd, sysinfo, products, overall
VSX	VSX	<pre>default, stat, traffic, conns, cpu, all, memory, cpu_usage_per_ core</pre>
IPsec VPN	vpn	default, product, IKE, ipsec, traffic, compression, accelerator, nic, statistics, watermarks, all
Data Loss Prevention	dlp	default, dlp, exchange_agents, fingerprint
Content Awareness	ctnt	default
QoS	fg	all
High Availability	ha	default, all
Policy Server for Remote Access VPN clients	polsrv	default, all

cpstat

Feature or Software Blade	Flag	Flavors
Desktop Policy Server for Remote Access VPN clients	dtps	default, all
LTE / GX	gx	<pre>default, contxt_create_info, contxt_delete_info, contxt_update_ info, contxt_path_mng_info, GXSA_ GPDU_info, contxt_initiate_info, gtpv2_create_info, gtpv2_delete_ info, gtpv2_update_info, gtpv2_ path_mng_info, gtpv2_cmd_info, all</pre>
Management Server	mg	default, log_server, indexer
Certificate Authority	са	default, crl, cert, user, all
SmartEvent	cpsemd	default
SmartEvent Correlation Unit	cpsead	default
Log Server	ls	default
CloudGuard Controller	vsec	default
SmartReporter	svr	default
Provisioning Agent	PA	default
Thresholds configured with the "threshold_ config" command	thresholds	default, active_thresholds, destinations, error
Historical status values	persistency	product, TableConfig, SourceConfig

Examples

Example - CPU utilization

```
[Expert@HostName:0]# cpstat -f cpu os
CPU User Time (%): 1
CPU System Time (%): 0
CPU Idle Time (%): 99
CPU Usage (%): 1
CPU Queue Length: -
CPU Interrupts/Sec: 172
CPUs Number: 8
[Expert@HostName:0]#
```

Example - Performance

[Expert@HostName:0]# cpstat os -f perf -	o 2 -c 2 -e 60
Total Virtual Memory (Bytes): Active Virtual Memory (Bytes): Total Real Memory (Bytes): Active Real Memory (Bytes): Free Real Memory (Bytes):	12417720320 3741331456 8231063552 3741331456 4489732096
Memory Swaps/Sec:	-
Memory To Disk Transfers/Sec:	-
CPU User Time (%):	0
CPU System Time (%): CPU Idle Time (%):	0 100
CPU Usage (%):	0
CPU Queue Length:	-
CPU Interrupts/Sec:	135
CPUs Number:	8
Disk Servicing Read\Write Requests Time:	
Disk Requests Queue:	-
Disk Free Space (%): Disk Total Free Space (Bytes):	61 12659716096
Disk Available Free Space (Bytes):	11606188032
Disk Total Space (Bytes):	20477751296
Total Virtual Memory (Bytes):	12417720320
Active Virtual Memory (Bytes):	3741556736
Total Real Memory (Bytes): Active Real Memory (Bytes):	8231063552 3741556736
Free Real Memory (Bytes):	4489506816
Memory Swaps/Sec:	-
Memory To Disk Transfers/Sec:	-
CPU User Time (%):	3
CPU System Time (%):	0
CPU Idle Time (%): CPU Usage (%):	97 3
CPU Queue Length:	-
CPU Interrupts/Sec:	140
CPUs Number:	8
Disk Servicing Read\Write Requests Time:	-
Disk Requests Queue:	-
Disk Free Space (%):	61
Disk Total Free Space (Bytes): Disk Available Free Space (Bytes):	12659716096 11606188032
Disk Total Space (Bytes):	
	20477751296

Example - List of current connected sessions on a Management Server

cpstop

Description

Manually stops all Check Point processes and applications.

Notes:

- For the cprid daemon, use the "cprid" on page 793 command.
- For manually stopping specific Check Point processes, see <u>sk97638</u>.

Syntax

cpstop

cpview

Overview of CPView

Description

CPView is a text based built-in utility on a Check Point computer.

CPView Utility shows statistical data that contain both general system information (CPU, Memory, Disk space) and information for different Software Blades (only on a Security Gateway / ClusterXL / Scalable Platform Security Group).

The CPView continuously updates the data in easy to access views.

On a Security Gateway / ClusterXL / Scalable Platform Security Group, you can use this statistical data to monitor the performance.

For more information, see <u>sk101878</u>.

Syntax

```
cpview --help
```

CPView User Interface

The CPView user interface has three sections:

Section	Description
Header	This view shows the time the statistics in the third view are collected. It updates when you refresh the statistics.
Navigation	This menu bar is interactive. Move between menus with the arrow keys and mouse. A menu can have sub-menus and they show under the menu bar.
View	This view shows the statistics collected in that view. These statistics update at the refresh rate.

Using CPView

Use these keys to navigate the CPView:

Key	Description
Arrow keys	Moves between menus and views. Scrolls in a view.
Home	Returns to the Overview view.
Enter	Changes to the View Mode . On a menu with sub-menus, the Enter key moves you to the lowest level sub- menu.
Esc	Returns to the Menu Mode.
Q	Quits CPView.

Use these keys to change CPView interface options:

Key	Description
R	Opens a window where you can change the refresh rate. The default refresh rate is 2 seconds.
W	Changes between wide and normal display modes. In wide mode, CPView fits the screen horizontally.
S	Manually sets the number of rows or columns.
М	Switches on/off the mouse.
Ρ	Pauses and resumes the collection of statistics.

Use these keys to save statistics, show help, and refresh statistics:

Кеу	Description
С	Saves the current page to a file. The file name format is: cpview_ <id cpview="" of="" process="" the="">.cap<number of="" the<br="">capture></number></id>
н	Shows a tooltip with CPView options.
Space bar	Immediately refreshes the statistics.

cpwd_admin

Description

The Check Point WatchDog (Cpwd) is a process that invokes and monitors critical processes such as Check Point daemons on the local computer, and attempts to restart them if they fail.

Among the processes monitored by Watchdog are fwm, fwd, cpd, DAService, and others.

The list of monitored processes depends on the installed and configured Check Point products and Software Blades.

The Check Point WatchDog writes monitoring information to the $pliced_pdled_p$

The $cpwd_admin$ utility shows the status of the monitored processes, and configures the Check Point WatchDog.

Monitoring	Description
Passive	WatchDog restarts the process only when the process terminates abnormally. In the output of the cpwd_admin list command, the MON column shows N for passively monitored processes.
Active	WatchDog checks the process status every predefined interval. WatchDog makes sure the process is alive, as well as properly functioning (not stuck on deadlocks, frozen, and so on). In the output of the cpwd_admin list command, the MON column shows Y for actively monitored processes. The list of actively monitored processes is predefined by Check Point. Users cannot change or configure it.

There are two types of Check Point WatchDog monitoring

Syntax on a Management Server in Gaia Clish or the Expert mode

cpwd_admin
config < <i>options</i> >
del <options></options>
detach < <i>options</i> >
exist
flist <options></options>
getpid < <i>options</i> >
kill
list <options></options>
monitor_list
start <options></options>
start_monitor
stop < <i>options</i> >
stop_monitor

Parameter	Description
config	Configures the Check Point WatchDog.
<options></options>	See "cpwd_admin config" on page 830.
del	Temporarily deletes a monitored process from the WatchDog database of monitored processes.
<options></options>	See "cpwd_admin del" on page 833.
detach	Temporarily detaches a monitored process from the WatchDog monitoring.
< <i>options</i> >	See <i>"cpwd_admin detach" on page 834</i> .
exist	Checks whether the WatchDog process cpwd is alive. See "cpwd_admin exist" on page 835.
flist <options></options>	Saves the status of all monitored processes to a <pre>\$CPDIR/tmp/cpwd_ list_<epoch timestamp="">.lst file. See "cpwd_admin flist" on page 836.</epoch></pre>
getpid	Shows the PID of a monitored process.
<options></options>	See <i>"cpwd_admin getpid" on page 838</i> .

Parameter	Description
kill <options></options>	 Terminates the WatchDog process cpwd. See "cpwd_admin kill" on page 839. Important - Do not run this command unless explicitly instructed by Check Point Support or R&D to do so.
list	Prints the status of all monitored processes on the screen. See "cpwd_admin list" on page 840.
monitor_	Prints the status of actively monitored processes on the screen.
list	See "cpwd_admin monitor_list" on page 843.
start	Starts a process as monitored by the WatchDog.
<options></options>	See "cpwd_admin start" on page 844.
start_ monitor	Starts the active WatchDog monitoring - WatchDog monitors the predefined processes actively. See " <i>cpwd_admin start_monitor</i> " on page 846.
stop	Stops a monitored process.
< <i>options</i> >	See <i>"cpwd_admin stop" on page 847</i> .
stop_	Stops the active WatchDog monitoring - WatchDog monitors all processes only passively.
monitor	See "cpwd_admin stop_monitor" on page 849.

cpwd_admin config

Description

Configures the Check Point WatchDog.

Important - After changing the WatchDog configuration parameters, you must restart the WatchDog process with the "cpstop" and "cpstart" commands (which restart all Check Point processes).

Syntax on a Management Server in Gaia Clish or the Expert mode

```
cpwd_admin config
-h
-a <options>
-d <options
-p
-r
```

Parameters

Parameter	Description
-h	Shows built-in usage.
<pre>-a <configuration_parameter_1>=<value_ 1=""> <configuration_parameter_2>=<value_ 2=""> <configuration_parameter_ n="">=<value_n></value_n></configuration_parameter_></value_></configuration_parameter_2></value_></configuration_parameter_1></pre>	 Adds the WatchDog configuration parameters. Note - Spaces are not allowed between the name of the configuration parameter, the equal sign, and the value.
<pre>-d <configuration_parameter_1> <configuration_parameter_2> <configuration_parameter_n></configuration_parameter_n></configuration_parameter_2></configuration_parameter_1></pre>	Deletes the WatchDog configuration parameters that user added with the "cpwd_admin config -a" command.
-р	Shows the WatchDog configuration parameters that user added with the "cpwd_admin config -a" command.
-r	Restores the default WatchDog configuration.

These are the available configuration parameters and the accepted values:

cpwd_admin config

Configuration Parameter	Accepted Values	Description				
no_limit	 Range: -1, 0, >0 Default: 5 	 If rerun_mode=1, specifies the maximum number of times the WatchDog tries to restart a process. -1 - Always tries to restart 0 - Never tries to restart >0 - Tries this number of times 				
num_of_procs	num_of_procs Range: 30 Configures the maximum number of proc - 20000 managed by the WatchDog. Default: 10000					
rerun_mode	0■ 1 (default)	 Configures whether the WatchDog restarts processes after they fail: 0 - Does not restart a failed process. Monitor and log only. 1 - Restarts a failed process (this is the default). 				
reset_ startups	 Range: > 0 Default: 3600 	Configures the time (in seconds) the WatchDog waits after the process starts and before the WatchDog resets the process's startup_counter to 0. To see the process's startup counter, in the output of the cpwd_admin list command, refer to the #START column.				
sleep_mode	0■ 1 (default)	 Configures how the WatchDog restarts the process: 0 - Ignores timeout and restarts the process immediately 1 - Waits for the duration of sleep_timeout 				
sleep_ timeout	 Range: 0 - 3600 Default: 60 	If rerun_mode=1, specifies how much time (in seconds) passes from a process failure until WatchDog tries to restart it.				
stop_timeout	Range: > 0Default: 60	Configures the time (in seconds) the WatchDog waits for a process stop command to complete.				

Configuration Parameter	Accepted Values	Description			
zero_timeout	 Range: > 0 Default: 7200 	After failing no_limit times to restart a process, the WatchDog waits zero_timeout seconds before it tries again. The value of the zero_timeout must be greater than the value of the timeout.			

The WatchDog saves the user defined configuration parameters in the

\$CPDIR/registry/HKLM registry.data file in the ": (Wd Config" section:

```
("CheckPoint Repository Set"
 : (SOFTWARE
   : (CheckPoint
      : (CPshared
       :CurrentVersion (6.0)
        : (6.0
        . . . . . .
          : (reserved
          . . . . . .
            : (Wd
                : (Wd Config
                     :Configuration_Parameter_1 ("[4]Value_1"):Configuration_Parameter_2 ("
[4]Value_2")
                )
            )
          ... ...
```

```
[Expert@HostName:0] # cpwd admin config -p
cpWatchDog doesn't have configuration parameters
[Expert@HostName:0]#
[Expert@HostName:0]# cpwd admin config -a sleep timeout=120 no limit=12
[Expert@HostName:0]#
[Expert@HostName:0]# cpwd_admin config -p
cpWatchDog Configuration parameters are:
sleep timeout : 120
no limit : 12
[Expert@HostName:0]#
[Expert@HostName:0]# cpstop ; cpstart
[Expert@HostName:0]#
[Expert@HostName:0]# cpwd admin config -r
cpWatchDog doesn't have configuration parameters
[Expert@HostName:0]#
[Expert@HostName:0] # cpstop ; cpstart
[Expert@HostName:0]#
[Expert@HostName:0]# cpwd admin config -p
cpWatchDog doesn't have configuration parameters
[Expert@HostName:0]#
```

cpwd_admin del

Description

Temporarily deletes a monitored process from the WatchDog database of monitored processes.

Notes:

- WatchDog stops monitoring the detached process, but the process stays alive.
- The "cpwd_admin list" on page 840 command does not show the deleted process anymore.
- This change applies until all Check Point services restart during boot, or with the "cpstart" on page 815 command.

Syntax on a Management Server in Gaia Clish or the Expert mode

```
cpwd_admin del -name <Application Name>
```

Parameters

Parameter	Description				
<application Name></application 	Name of the monitored Check Point process as you see in the output of the "cpwd_admin list" on page 840 command in the leftmost column APP. Examples: FWM FWD CPD CPM				

```
[Expert@HostName:0]# cpwd_admin del -name FWD
cpwd_admin:
successful Del operation
[Expert@HostName:0]#
```

cpwd_admin detach

Description

Temporarily detaches a monitored process from the WatchDog monitoring.



- WatchDog stops monitoring the detached process, but the process stays alive.
- The "cpwd_admin list" on page 840 command does not show the detached process anymore.
- This change applies until all Check Point services restart during boot, or with the "cpstart" on page 815 command.

Syntax on a Management Server in Gaia Clish or the Expert mode

```
cpwd admin detach -name <Application Name>
```

Parameters

Parameter	Description				
<application Name></application 	Name of the monitored Check Point process as you see in the output of the "cpwd_admin list" on page 840 command in the leftmost column APP. Examples: FWM FWD CPD CPM				

```
[Expert@HostName:0]# cpwd_admin detach -name FWD
cpwd_admin:
successful Detach operation
[Expert@HostName:0]#
```

cpwd_admin exist

Description

Checks whether the WatchDog process cpwd is alive.

Syntax on a Management Server in Gaia Clish or the Expert mode

```
cpwd_admin exist
```

```
[Expert@HostName:0]# cpwd_admin exist
 cpwd_admin: cpWatchDog is running
[Expert@HostName:0]#
```

cpwd_admin flist

Description

Saves the status of all WatchDog monitored processes to a file.

Syntax on a Management Server in Gaia Clish or the Expert mode

cpwd_admin flist [-full]

Parameters

Parameter	Description
-full	Shows the verbose output.

Output

Column	Description				
APP	Shows the WatchDog name of the monitored process.				
PID	Shows the PID of the monitored process.				
STAT	Shows the status of the monitored process:				
	 E - executing T - terminated 				
#START	Shows how many times the WatchDog started the monitored process.				
START_TIME	Shows the time when the WatchDog started the monitored process for the last time.				
SLP/LIMIT	In verbose output, shows the values of the <pre>sleep_timeout and no_ limit configuration parameters (see "cpwd_admin config" on page 830).</pre>				
MON	Shows how the WatchDog monitors this process (see the explanation for the <i>"cpwd_admin" on page 827</i>):				
	 Y - Active monitoring N - Passive monitoring 				
COMMAND	Shows the command the WatchDog run to start this process.				

```
[Expert@HostName:0]# cpwd_admin flist
/opt/CPshrd-R82/tmp/cpwd_list_1564617600.lst
[Expert@HostName:0]#
```

cpwd_admin getpid

Description

Shows the PID of a WatchDog monitored process.

Syntax on a Management Server in Gaia Clish or the Expert mode

```
cpwd_admin getpid -name <Application Name>
```

Parameters

Parameter	Description					
<application Name></application 	Name of the monitored Check Point process as you see in the output of the "cpwd_admin list" on page 840 command in the leftmost column APP. Examples:					
	■ FWM					
	■ FWD					
	■ CPD					
	■ CPM					

```
[Expert@HostName:0]# cpwd_admin getpid -name FWD
5640
[Expert@HostName:0]#
```

cpwd_admin kill

Description

Terminates the WatchDog process cpwd.



Important - Do not run this command unless explicitly instructed by Check Point Support or R&D to do so.

To restart the WatchDog process, you must restart all Check Point services with the *"cpstop" on page 824* and *"cpstart" on page 815* commands.


Syntax on a Management Server in Gaia Clish or the Expert mode

cpwd_admin kill

cpwd_admin list

Description

Prints the status of all WatchDog monitored processes on the screen.



Syntax on a Management Server in Gaia Clish or the Expert mode

```
cpwd_admin list [-full]
```

Parameters

Parameter	Description			
-full	Shows the verbose output.			

Output

Column	Description				
APP	Shows the WatchDog name of the monitored process.				
PID	Shows the PID of the monitored process.				
STAT	Shows the status of the monitored process:				
	 E - executing T - terminated 				
#START	Shows how many times the WatchDog started the monitored process.				
START_TIME	Shows the time when the WatchDog started the monitored process for the last time.				
SLP/LIMIT	In verbose output, shows the values of the <pre>sleep_timeout and no_ limit configuration parameters (see "cpwd_admin config" on page 830).</pre>				
MON	Shows how the WatchDog monitors this process (see the explanation for the "cpwd_admin" on page 827):				
	 Y - Active monitoring N - Passive monitoring 				
COMMAND	Shows the command the WatchDog run to start this process.				

Examples

Example - Default output on a Management Server

[Expert@Ho	stName:	0]# cp	wd_admin	list			
APP	PID	STAT	#START	START_TIME		MON	COMMAND
CPVIEWD	19738	E	1	[17:50:44]	31/5/2019	Ν	cpviewd
HISTORYD	0	Т	0	[17:54:44]	31/5/2019	Ν	cpview historyd
CPD	19730	E	1	[17:54:45]	31/5/2019	Y	cpd
SOLR	19935	E	1	[17:50:55]	31/5/2019	Ν	java solr /opt/CPrt-
R82/conf/j	etty.xm	1					
RFL	19951	Е	1	[17:50:55]	31/5/2019	Ν	LogCore
SMARTVIEW	19979	E	1	[17:50:55]	31/5/2019	Ν	SmartView
INDEXER	20032	E	1	[17:50:55]	31/5/2019	Ν	/opt/CPrt-R82/log indexer/log
indexer							
SMARTLOG S	erver 2	0100	E 1	[17:50	0:55] 31/5/	2019	N /opt/CPSmartLog-
R82/smartl	og serv	er					
CP3DLOGD		Е	1	[17:50:55]	31/5/2019	Ν	cp3dlogd
EPM	20251	Е	1	[17:50:56]	31/5/2019	Ν	startEngine
DASERVICE	20404	Е	1	[17:50:59]	31/5/2019	Ν	DAService script
[Expert@Ho	stName:	0]#					

Example - Verbose output on a Management Server

[Expert@Ho APP	stName:0]# cpwd_admin list -full PID STAT #START START_TIME	SLP/LIMIT	MON
CPVIEWD	19738 E 1 [17:50:44] 31/5/2019 PATH = /opt/CPshrd-R82/bin/cpviewd COMMAND = cpviewd	60/5	N
HISTORYD	0 T 0 [17:54:44] 31/5/2019 PATH = /opt/CPshrd-R82/bin/cpview_historyd COMMAND = cpview_historyd	60/5	N
CPD	19730 E 1 [17:54:45] 31/5/2019 PATH = /opt/CPshrd-R82/bin/cpd COMMAND = cpd	60/5	Y
SOLR	19935 E 1 [17:50:55] 31/5/2019 PATH = /opt/CPrt-R82/bin/java_solr COMMAND = java_solr /opt/CPrt-R82/conf/jett	60/5 y.xml	N
RFL	19951 E 1 [17:50:55] 31/5/2019 PATH = /opt/CPrt-R82/bin/LogCore COMMAND = LogCore	60/5	N
SMARTVIEW	19979 E 1 [17:50:55] 31/5/2019 PATH = /opt/CPrt-R82/bin/SmartView COMMAND = SmartView	60/5	N
INDEXER	20032 E 1 [17:50:55] 31/5/2019 PATH = /opt/CPrt-R82/log_indexer/log_indexe COMMAND = /opt/CPrt-R82/log_indexer/log_ind	r	N
SMARTLOG_S	ERVER 20100 E 1 [17:50:55] 31/5/2 PATH = /opt/CPSmartLog-R82/smartlog_server COMMAND = /opt/CPSmartLog-R82/smartlog_serv ENV = LANG=C		N
CP3DLOGD	20237 E 1 [17:50:55] 31/5/2019 PATH = /opt/CPuepm-R82/bin/cp3dlogd COMMAND = cp3dlogd	60/5	Ν
EPM	20251 E 1 [17:50:56] 31/5/2019 PATH = /opt/CPuepm-R82/bin/startEngine COMMAND = startEngine	60/5	N
DASERVICE	PATH = /opt/CPda/bin/DAService_script COMMAND = DAService_script	60/5	N

cpwd_admin monitor_list

Description

Prints the status of actively monitored processes on the screen.

See the explanation about the active monitoring in "cpwd_admin" on page 827.

Syntax on a Management Server in Gaia Clish or the Expert mode

cpwd_admin monitor_list

```
[Expert@HostName:0]# cpwd_admin monitor_list
cpwd_admin:
APP FILE_NAME NO_MSG_TIMES LAST_MSG_TIME
CPD CPD_5420_4714.mntr 0/10 [19:00:33] 31/5/2019
[Expert@HostName:0]#
```

cpwd_admin start

Description

Starts a process as monitored by the WatchDog.

Syntax on a Management Server in Gaia Clish or the Expert mode

```
cpwd_admin start -name <Application Name> -path "<Full Path to
Executable>" -command "<Command Syntax>" [-env {inherit | <Env_
Var>=<Value>] [-slp_timeout <Timeout>] [-retry_limit {<Limit> |
u}]
```

Parameters

Parameter	Description
-name <application Name></application 	Name, under which the cpwd_admin list command shows the monitored process in the leftmost column APP. Examples:
	 FWM FWD CPD CPM
-path " <full path<br="">to Executable>"</full>	The full path (with or without Check Point environment variables) to the executable including the executable name. Must enclose in double quotes. Examples:
	 For FWM: "\$FWDIR/bin/fwm" For FWD: "/opt/CPsuite-R82/fw1/bin/fw" For CPD: "\$CPDIR/bin/cpd" For CPM: "/opt/CPsuite- R82/fw1/scripts/cpm.sh" For SICTUNNEL: "/opt/CPshrd-R82/bin/cptnl"

Parameter	Description
-command " <command Syntax>"</command 	The command and its arguments to run. Must enclose in double quotes. Examples:
	 For FWM: "fwm" For FWM on Multi-Domain Server: "fwm mds" For FWD: "fwd" For CPD: "cpd" For CPM: "/opt/CPsuite- R82/fw1/scripts/cpm.sh -s" For SICTUNNEL: "/opt/CPshrd-R82/bin/cptnl -c "/opt/CPuepm-R82/engine/conf/cptnl_ srv.conf"
-env {inherit <env_ Var>=<value>}</value></env_ 	 Configures whether to inherit the environment variables from the shell. inherit - Inherits all the environment variables (WatchDog supports up to 80 environment variables) <<u>Env_Var>=<value></value></u> - Assigns the specified value to the specified environment variable
-slp_timeout < <i>Timeout</i> >	Configures the specified value of the "sleep_timeout" configuration parameter. See "cpwd_admin config" on page 830.
-retry_limit {< <i>Limit</i> > u}	<pre>Configures the value of the "retry_limit" configuration parameter. See "cpwd_admin config" on page 830. <_Limit> - Tries to restart the process the specified number of times u - Tries to restart the process unlimited number of times</pre>

Example

For the list of process and the applicable syntax, see $\frac{sk97638}{2}$.

cpwd_admin start_monitor

Description

Starts the active WatchDog monitoring. WatchDog monitors the predefined processes actively.

See the explanation for the "cpwd_admin" on page 827 command.

Syntax on a Management Server in Gaia Clish or the Expert mode

```
cpwd_admin start_monitor
```

```
[Expert@HostName:0]# cpwd_admin start_monitor
cpwd_admin:
CPWD has started to perform active monitoring on Check Point services/processes
[Expert@HostName:0]#
```

cpwd_admin stop

Description

Stops a WatchDog monitored process.

Important - This change does **not** survive reboot.

Syntax on a Management Server in Gaia Clish or the Expert mode

```
cpwd_admin stop -name <Application Name> [-path "<Full Path to
Executable>" -command "<Command Syntax>" [-env {inherit | <Env_
Var>=<Value>]
```

Parameters

Parameter	Description
-name <application Name></application 	Name under which the cpwd_admin list command shows the monitored process in the leftmost column APP. Examples: FWM FWD CPD CPM
-path " <full path<br="">to Executable>"</full>	The full path (with or without Check Point environment variables) to the executable including the executable name. Must enclose in double quotes. Examples: For FWM: "\$FWDIR/bin/fwm" For FWD: "/opt/CPsuite-R82/fw1/bin/fw" For CPD: "\$CPDIR/bin/cpd_admin"
-command "< <i>Command</i> Syntax>"	The command and its arguments to run. Must enclose in double quotes. Examples: For FWM: "fw kill fwm" For FWD: "fw kill fwd" For CPD: "cpd_admin stop"

Parameter	Description
-env {inherit <env_var>=<value>}</value></env_var>	Configures whether to inherit the environment variables from the shell.
	 inherit - Inherits all the environment variables (WatchDog supports up to 80 environment variables) <<u>Env_Var>=</u><<u>Value></u> - Assigns the specified value to the specified environment variable

Example

For the list of process and the applicable syntax, see $\frac{sk97638}{sk97638}$.

cpwd_admin stop_monitor

Description

Stops the active WatchDog monitoring. WatchDog monitors all processes only passively.

See the explanation for the "cpwd_admin" on page 827 command.

Syntax on a Management Server in Gaia Clish or the Expert mode

cpwd_admin stop_monitor

```
[Expert@HostName:0]# cpwd_admin stop_monitor
cpwd_admin:
CPWD has stopped performing active monitoring on Check Point services/processes
[Expert@HostName:0]#
```

dbedit

Description

Edits the management database - the *\$FWDIR/conf/objects 5 0.C* file - on the Security Management Server or Domain Management Server. See skl3301.



R Important - Do NOT run this command, unless explicitly instructed by Check Point Support or R&D to do so. Otherwise, you can corrupt settings in the management database.

Syntax

dbedit -help

```
dbedit [-globallock] [{-local | -s <Management Server>}] [{-u
<Username> | -c <Certificate>}] [-p <Password>] [-f <File Name>
[ignore script failure] [-continue updating]] [-r "<Open Reason
Text>"] [-d <Database Name>] [-listen] [-readonly] [-session]
```

Note:

On a Multi-Domain Server, you must run this command in the context of the applicable Domain Management Server:

mdsenv <IP Address or Name of Domain Management Server>

Parameter	Description
-help	Prints the general help.
-globallock	When you work with the dbedit utility, it partially locks the management database. If a user configures objects in SmartConsole at the same time, it causes problems in the management database. This option does not let SmartConsole, or a dbedit user to make changes in the management database. When you specify this option, the dbedit commands run on a copy of the management database. After you make the changes with the dbedit commands and run the savedb command, the dbedit utility saves and commits your changes to the actual management database.
-local	Connects to the localhost (127.0.0.1) without using username/password. If you do not specify this parameter, the dbedit utility asks how to connect.

Parameter	Description
-s <management_ Server></management_ 	Specifies the Security Management Server - by IP address or HostName. If you do not specify this parameter, the dbedit utility asks how to connect.
-u < <i>Username</i> >	Specifies the username, with which the dbedit utility connects to the Security Management Server. Mandatory parameter when you specify the "-s <management_ Server>" parameter.</management_
-c < Certificate>	Specifies the user's certificate file, with which the dbedit utility connects to the Security Management Server. Mandatory parameter when you specify the "-s <management_ Server>" parameter.</management_
-p < <i>Password</i> >	Specifies the user's password, with which the dbedit utility connects to the Security Management Server. Mandatory parameter when you specify the "-s <management_ Server>" and "-u <username>" parameters.</username></management_
-f <file_ Name></file_ 	<pre>Specifies the file that contains the applicable dbedit internal commands (see the section "dbedit Internal Commands" below): create <object_type> <object_name> modify <table_name> <object_name> <field_name> <value> update <table_name> <object_name> delete <table_name> <object_name> print <table_name> <object_name> quit Note - Each command is limited to 4096 characters.</object_name></table_name></object_name></table_name></object_name></table_name></value></field_name></object_name></table_name></object_name></object_type></pre>
ignore_ script_ failure	Continues to execute the dbedit internal commands in the file and ignores errors. You can use it when you specify the "-f < <i>File_Name</i> >" parameter.
-continue_ updating	Continues to update the modified objects, even if the operation fails for some of the objects (ignores the errors and runs the update_all command at the end of the script). You can use it when you specify the "-f <file_name>" parameter.</file_name>
-r " <open_ Reason_ Text>"</open_ 	Specifies the reason for opening the database in read-write mode (default mode).

dbedit

Parameter	Description
-d <database_ Name></database_ 	Specifies the name of the database, to which the dbedit utility should connect (for example, mdsdb).
-listen	The dbedit utility "listens" for changes (use this mode for advanced troubleshooting with the assistance of Check Point Support). The dbedit utility prints its internal messages when a change occurs in the management database.
-readonly	Specifies to open the management database in read-only mode.
-session	Session Connectivity.

dbedit Internal Commands

Note - To see the available tables, class names (object types), attributes and values, connect to Management Server with Database Tool (GuiDBEdit Tool) (see <u>sk13009</u>).

Command	Description, Syntax, Examples
-h	Description: Prints the general help. Syntax: dbedit> -h
-q	Description: Quits from dbedit.
quit	Syntax:
	dbedit> -q
	dbedit> quit [-update_all -noupdate]
	Examples:
	 Exit the utility and commit the remaining modified objects (interactive mode):
	dbedit> quit
	Exit the utility and update all the remaining modified objects:
	dbedit> quit -update_all
	Exit the utility and discard all modifications:
	dbedit> quit -no_update

Command	Description, Syntax, Examples
update	Description: Saves the specified object in the specified table (for example, "network_objects", "services", "users"). Syntax: dbedit> update <table_name> <object_name> Example: Save the object My_Service in the table services: dbedit> update services My_Service</object_name></table_name>
update_all	Description: Saves all the modified objects. Syntax: dbedit> update_all
_print_set	<pre>Description: Prints the specified object from the specified table (for example, "network_objects", "services", "users") as it appears in the \$FWDIR/conf/objects_5_0.C file (sets of attributes). Syntax: dbedit> _print_set <table_name> <object_name> Example: Print the object My_Obj from the table network_objects: dbedit> print_network_objects My_Obj</object_name></table_name></pre>
print	<pre>Description: Prints the list of attributes of the specified object from the specified table (for example, "network_objects", "properties", "services", "users"). Syntax: dbedit> print <table_name> <object_name> Examples: Print the object My_Obj from the table network_objects (in "Network Objects"): dbedit> print network_objects my_obj Print the object firewall_properties from the table properties (in "Global Properties"): dbedit> print properties firewall_properties</object_name></table_name></pre>

Command	Description, Syntax, Examples	
printxml	Description: Prints in XML format the list of attributes of the specified object from the specified table (for example, "network_objects", "properties", "services", "users"). You can export the settings from a Management Server to an XML file that you can use later with external automation systems. Syntax:	
	<pre>dbedit> printxml <table_name> [<object_name>]</object_name></table_name></pre>	
	Examples:	
	Print the object My_Obj from the table network_objects:	
	dbedit> printxml network_objects my_obj	
	 Print the object <i>firewall_properties</i> from the table <i>properties</i> (in "Global Properties"): 	
	<pre>dbedit> printxml properties firewall_ properties</pre>	
printbyuid	Description: Prints the attributes of the object specified by its UID (appears in the \$FWDIR/conf/objects_5_0.C file at the beginning of the object as "chkpf_uid ({})"). Syntax:	
	dbedit> printbyuid { <i>object_id</i> }	
	Example: Print the attributes of the object with the specified UID:	
	dbedit> printbyuid {D3833F1D-0A58-AA42-865F- 39BFE3C126F1}	

Command	Description, Syntax, Examples
query	Description: Prints all the objects in the specified table. Optionally, you can query for objects with specific attribute and value - query is separated by a comma after "query <table_name>" (spaces are not allowed between the <attribute> and '<value>'). Syntax:</value></attribute></table_name>
	<pre>dbedit> query <table_name> [,</table_name></pre>
	Examples:
	Print all objects in the table users:
	dbedit> query users
	 Print all objects in the table <i>network_objects</i> that are defined as Management Servers:
	<pre>dbedit> query network_objects, management='true'</pre>
	Print all objects in the table services with the name ssh:
	<pre>command_sdbedit> query services, name='ssh'</pre>
	Print all objects in the table services with the port 22:
	dbedit> query services, port='22'
	Print all objects with the IP address 10.10.10.10.
	<pre>dbedit> query network_objects, ipaddr='10.10.10'</pre>
whereused	Description: Checks where the specified object used in the database. Prints the number of places, where this object is used and relevant information about each such place. Syntax:
	dbedit> whereused <table_name> <object_name></object_name></table_name>
	Example: Check where the object <i>My_Obj</i> is used:
	dbedit> whereused network_objects My_Obj

Command	Description, Syntax, Examples
create	Description: Creates an object of specified type (with its default values) in the database. Restrictions apply to the object's name:
	 Object names can have a maximum of 100 characters. Objects names can contain only ASCII letters, numbers, and dashes. Reserved words will be blocked by the Management Server (refer to sk40179).
	Syntax:
	<pre>dbedit> create <object_type> <object_name></object_name></object_type></pre>
	Example: Create the service object <i>My_Service</i> of the type <i>tcp_service</i> (with its default values):
	dbedit> create tcp_service my_service
delete	Description: Deletes an object from the specified table. Syntax:
	<pre>dbedit> delete <table_name> <object_name></object_name></table_name></pre>
	Example: Delete the service object <i>My_Service</i> from the table <i>services</i> :
	dbedit> delete services my_service

Command	Description, Syntax, Examples
modify	Description: Modifies the value of specified attribute in the specified object in the specified table (for example, "network_objects", "services", "users") in the management database. Syntax:
	<pre>dbedit> modify <table_name> <object_name> <field_ name=""> <value></value></field_></object_name></table_name></pre>
	Examples:
	 Modify the color to red in the object My_Service in the table services:
	dbedit> modify services My_Service color red
	Add a comment to the object MyObj:
	dbedit> modify network_objects MyObj comments "Created by fwadmin with dbedit"
	Set the value of the global property ike_use_largest_possible_ subnets in the table properties to false:
	<pre>dbedit> modify properties firewall_properties ike_use_largest_possible_subnets false</pre>
	Create a new interface on the Security Gateway My_FW and modify its attributes - set the IP address / Mask and enable Anti- Spoofing on interface with "Element Index"=3 (check the attributes of the object My_FW in Database Tool (GuiDBEdit Tool) (see <u>sk13009</u>)):

Command	Description, Syntax, Examples
	<pre>dbedit> addelement network_objects My_FW interfaces interface dbedit> modify network_objects My_FW interfaces:3:officialname NAME_OF_INTERFACE dbedit> modify network_objects My_FW interfaces:3:ipaddr IP_ADDRESS dbedit> modify network_objects My_FW interfaces:3:netmask NETWORK_MASK dbedit> modify network_objects My_FW interfaces:3:security:netaccess:access specific dbedit> modify network_objects My_FW interfaces:3:security:netaccess:allowed network_objects:group_name dbedit> modify network_objects My_FW interfaces:3:security:netaccess:perform_anti_ spoofing true dbedit> modify network_objects MyObj FieldA LINKSYS</pre>
	 In the Owned Object MyObj change the value of FieldB to NewVal:
	dbedit> modify network_objects MyObj FieldA:FieldB NewVal
	In the Linked Object MyObj change the value of FieldA from B to C:
	dbedit> modify network_objects MyObj FieldA B:C

Command	Description, Syntax, Examples
lock	Description:Locks the specified object (by administrator) in the specified table (forexample, "network_objects", "services", "users") from beingmodified by other users.For example, if you connect from a remote computer to thisManagement Server with admin1 and lock an object, you are be able toconnect with admin2, but are not able to modify the locked object, untiladmin1 releases the lock.Syntax:
	<pre>dbedit> lock <table_name> <object_name></object_name></table_name></pre>
	Example: Lock the object <i>My_Service_Obj</i> in the table <i>services</i> in the database:
	dbedit> lock services My_Service_Obj
addelement	Description: Adds a specified multiple field / container (with specified value) to a specified object in specified table. Syntax: dbedit> addelement <table_name> <object_name> <field_name> <value></value></field_name></object_name></table_name>
	Examples:
	Add the element BranchObjectClass with the value Organization to a multiple field Read in the object My_Obj in the table Idap:
	dbedit> addelement ldap My_Obj Read:BranchObjectClass Organization
	 Add the service MyService to the group of services MyServicesGroup in the table services:
	<pre>dbedit> addelement services MyServicesGroup '' services:MyService</pre>
	Add the network MyNetwork to the group of networks MyNetworksGroup in the table network_objects:
	<pre>dbedit> addelement network_objects MyNetworksGroup '' network_objects:MyNetwork</pre>

Command	Description, Syntax, Examples
rmelement	Description: Removes a specified multiple field / container (with specified value) from a specified object in specified table. Syntax: dbedit> rmelement <object name=""></object>
	<pre><field_name> <value></value></field_name></pre>
	Examples:
	 Remove the service MyService from the group of services MyServicesGroup from the table services:
	dbedit> rmelement services MyServicesGroup '' services:MyService
	Remove the network MyNetwork from the group of networks MyNetworksGroup from the table network_objects:
	dbedit> rmelement network_objects MyNetworksGroup '' network_objects:MyNetwork
	Remove the element <i>BranchObjectClass</i> with the value Organization from the multiple field <i>Read</i> in the object <i>My_Obj</i> in the table <i>Idap</i> :
	dbedit> rmelement ldap my_obj Read:BranchObjectClass Organization
rename	Description: Renames the specified object in specified table. Syntax:
	<pre>dbedit> rename <table_name> <object_name> <new_ object_name=""></new_></object_name></table_name></pre>
	Example: Rename the network object <i>london</i> to <i>chicago</i> in the table <i>network_objects</i> :
	dbedit> rename network_objects london chicago

Command	Description, Syntax, Examples
rmbyindex	Description: Removes an element from a container by element's index. Syntax: dbedit> rmbyindex <table_name> <object_name> <field name=""> <index number=""></index></field></object_name></table_name>
	Example: Remove the element <i>backup_log_servers</i> from the container <i>log_servers</i> by element index <i>1</i> in the table <i>network_objects</i> :
	<pre>dbedit> rmbyindex network_objects g log_ servers:backup_log_servers 1</pre>
add_owned_ remove_name	Description: Adds an owned object (and removes its name) to a specified owned object field (or container). Syntax:
	<pre>dbedit> add_owned_remove_name <table_name> <object_name> <field_name> <value></value></field_name></object_name></table_name></pre>
	Example: Add the owned object <i>My_Gateway</i> (and remove its name) to the owned object field (or container) <i>my_external_products</i> :
	dbedit> add_owned_remove_name network_objects My_ Gateway additional_products owned:my_external_ products
is_delete_ allowed	Description: Checks if the specified object can be deleted from the specified table (object cannot be deleted if it is used by other objects). Syntax:
	<pre>dbedit> is_delete_allowed <table_name> <object_ name=""></object_></table_name></pre>
	Example:
	dbedit> is_delete_allowed network_objects MyObj
	Check if the object <i>MyObj</i> can be deleted from the table <i>network_objects</i> :

Command	Description, Syntax, Examples
set_pass	Description: Sets specified password for specified user. Notes:
	 The password must contain at least 4 characters and no more than 50 characters.
	This command cannot change the administrator's password.
	Syntax:
	dbedit> set_pass <username> <password></password></username>
	Example: Set the password 1234 for the user abcd:
	dbedit> set_pass abcd 1234
savedb	Description: Saves the database. You can run this command only when the database is locked globally (when you start the dbedit utility with the "dbedit -globallock" command). Syntax:
	dbedit> savedb
savesession	Description: Saves the session. You can run this command only when you start the dbedit utility in session mode (with the "dbedit -session" command). Syntax:
	dbedit> savesession

fw

Description

- Performs various operations on Security or Audit log files.
- Kills the specified Check Point processes.
- Manages the Suspicious Activity Monitoring (SAM) rules.
- Manages the Suspicious Activity Policy editor.

Syntax

fw [-d]
fetchlogs <options></options>
hastat <options></options>
kill <options></options>
log <options></options>
logswitch <options></options>
lslogs < <i>options</i> >
mergefiles <options></options>
repairlog < <i>options</i> >
sam <options></options>
<pre>sam_policy <options></options></pre>

Parameters

Parameter	Description
-d	 Runs the command in debug mode. Use only if you troubleshoot the command itself. Best Practice - If you use this parameter, then redirect the output to a file, or use the script command to save the entire CLI session.
fetchlogs < <i>options</i> >	Fetches the specified Check Point log files - Security (\$FWDIR/log/*.log*) or Audit (\$FWDIR/log/*.adtlog*), from the specified Check Point computer. See "fw fetchlogs" on page 865.
hastat < <i>options</i> >	Shows information about Check Point computers in High Availability configuration and their states. See <i>"fw hastat" on page 868</i> .

Parameter	Description
kill <options></options>	Kills the specified Check Point process. See <i>"fw kill" on page 869</i> .
log <options></options>	Shows the content of Check Point log files - Security (\$FWDIR/log/*.log) or Audit (\$FWDIR/log/*.adtlog). See "fw log" on page 870.
logswitch < <i>options</i> >	Switches the current active Check Point log file - Security (\$FWDIR/log/fw.log) or Audit (\$FWDIR/log/fw.adtlog). See "fw logswitch" on page 880.
lslogs < <i>options</i> >	Shows a list of Check Point log files - Security (\$FWDIR/log/*.log*) or Audit (\$FWDIR/log/*.adtlog*), located on the local computer or a remote computer. See "fw lslogs" on page 884.
mergefiles <options></options>	Merges several Check Point log files - Security (\$FWDIR/log/*.log) or Audit (\$FWDIR/log/*.adtlog), into a single log file. See "fw mergefiles" on page 887.
repairlog < <i>options</i> >	Rebuilds pointer files for Check Point log files - Security (\$FWDIR/log/*.log) or Audit (\$FWDIR/log/*.adtlog). See "fw repairlog" on page 890.
sam <options></options>	Manages the Suspicious Activity Monitoring (SAM) rules. See "fw sam" on page 892.
sam_policy < <i>options</i> > or samp < <i>options</i> >	 Manages the Suspicious Activity Policy editor that works with these type of rules: Suspicious Activity Monitoring (SAM) rules. Rate Limiting rules.
	See "fw sam_policy" on page 901.

fw fetchlogs

Description

Fetches the specified Security log files (\$FWDIR/log/*.log*) or Audit log files (\$FWDIR/log/*.adtlog*) from the specified Check Point server.

Important:

- You can run this command in the Expert mode or in Gaia Clish (Gaia gClish on Scalable Platforms).
- On Scalable Platforms (ElasticXL, Maestro, and Chassis), you must connect to the Gaia Portal of the applicable Security Group.

Syntax

```
fw [-d] fetchlogs [-f <Name of Log File 1>] [-f <Name of Log File
2>]... [-f <Name of Log File N>] <Target>
```

Parameter	Description		
-d	 Runs the command in debug mode. Use only if you troubleshoot the command itself. Best Practice - If you use this parameter, then redirect the output to a file, or use the script command to save the entire CLI session. 		
-f <name of Log File N></name 	 Specifies the name of the log file to fetch. Need to specify name only. Notes: If you do not specify the log file name explicitly, the command transfers all Security log files (\$FWDIR/log/*.log*) and all Audit log files (\$FWDIR/log/*.adtlog*). The specified log file name can include wildcards * and ? (for example, 2017-0?-*.log). If you enter a wildcard, you must enclose it in double quotes or single quotes. You can specify multiple log files in one command. You must use the -f parameter for each log file name pattern. This command also transfers the applicable log pointer files. 		
<target></target>	 Specifies the remote Check Point server, with which this local Check Point server has established SIC trust. If you run this command on a Security Management Server or Domain Management Server, then <<i>Target></i> is the applicable object's name or main IP address of the Check Point server as configured in SmartConsole. If you run this command on a Security Gateway or Cluster Member, then <<i>Target></i> is the main IP address of the applicable object as configured in SmartConsole. 		

Notes:

- This command moves the specified log files from the \$FWDIR/log/ directory on the specified Check Point server. Meaning, it deletes the specified log files on the specified Check Point server after it copies them successfully.
- This command moves the specified log files to the \$FWDIR/log/ directory on the local Check Point server, on which you run this command.
- This command cannot fetch the active log files \$FWDIR/log/fw.log or \$FWDIR/log/fw.adtlog.

To fetch these active log files:

1. Perform log switch on the applicable Check Point server:

fw logswitch [-audit] [-h <IP Address or Hostname>]

2. Fetch the rotated log file from the applicable Check Point server:

```
fw fetchlogs -f <Log File Name> <IP Address or Hostname>
```

This command renames the log files it fetched from the specified Check Point server. The new log file name is the concatenation of the Check Point server's name (as configured in SmartConsole), two underscore (_) characters, and the original log file name (for example: MyGW 2019-06-01 000000.log).

Example - Fetching log files from a Management Server

```
[Expert@HostName:0]# fw lslogs MyGW
     Size Log file name
        23KB 2019-05-16_000000.log
9KB 2019-05-17_000000.log
        11KB 2019-05-18 000000.log
      5796KB 2019-06-01_000000.log
      4610KB fw.log
[Expert@HostName:0]#
[Expert@HostName:0] # fw fetchlogs -f 2019-06-01_000000 MyGW
File fetching in process. It may take some time...
File MyGW 2019-06-01 000000.log was fetched successfully
[Expert@HostName:0]#
[Expert@HostName:0] # ls $FWDIR/log/MyGW*
/opt/CPsuite-R82/fw1/log/MyGW 2019-06-01 000000.log
/opt/CPsuite-R82/fw1/log/MyGW_2019-06-01_000000.logaccount_ptr
/opt/CPsuite-R82/fw1/log/MyGW_2019-06-01_000000.loginitial_ptr
/opt/CPsuite-R82/fw1/log/MyGW_2019-06-01_000000.logptr
[Expert@HostName:0]#
[Expert@HostName:0] # fw lslogs MyGW
     Size Log file name
        23KB 2019-05-16 000000.log
        9KB 2019-05-17_000000.log
11KB 2019-05-18_000000.log
      4610KB fw.log
[Expert@HostName:0]#
```

fw hastat

Description

Shows information about Check Point computers in High Availability configuration and their states.

Note - This command is outdated. On Management Servers, run the "cpstat" on page 816 command.

Syntax

```
fw hastat [<Target1>] [<Target2>] ... [<TargetN>]
```

Parameters

Parameter	Description
<target1> <target2> <targetn></targetn></target2></target1>	Specifies the Check Point computers to query. If you run this command on the Management Server, you can enter the applicable IP address, or the resolvable HostName of the managed Security Gateway or Cluster Member. If you do not specify the target, the command queries the local computer.

Example - Querying the cluster members from the Management Server

```
[Expert@MGMT:0]# fw hastat 192.168.3.52
HOST NUMBER HIGH AVAILABILITY STATE MACHINE STATUS
192.168.3.52 1 active OK
[Expert@MGMT:0]#
[Expert@MGMT:0]# fw hastat 192.168.3.53
HOST NUMBER HIGH AVAILABILITY STATE MACHINE STATUS
192.168.3.53 2 stand-by OK
[Expert@MGMT:0]#
[Expert@MGMT:0]# fw hastat 192.168.3.52 192.168.3.53
HOST NUMBER HIGH AVAILABILITY STATE MACHINE STATUS
192.168.3.52 1 active OK
192.168.3.53 2 stand-by OK
[Expert@MGMT:0]#
```

fw kill

Description

Kills the specified Check Point processes.

Important:

- Make sure the killed process is restarted, or restart it manually. See <u>sk97638</u>.
- You can run this command in the Expert mode or in Gaia Clish (Gaia gClish on Scalable Platforms).
- On Scalable Platforms (ElasticXL, Maestro, and Chassis), you must connect to the Gaia Portal of the applicable Security Group.

Syntax

```
fw [-d] kill [-t <Signal Number>] <Name of Process>
```

Parameters

Parameter	Description		
-d	 Runs the command in debug mode. Use only if you troubleshoot the command itself. Best Practice - If you use this parameter, then redirect the output to a file, or use the script command to save the entire CLI session. 		
-t <signal Number></signal 	Specifies which signal to send to the Check Point process. For the list of available signals and their numbers, run the kill -1 command. For information about the signals, see the manual pages for the <u>kill</u> and <u>signal</u> . If you do not specify the signal explicitly, the command sends Signal 15 (SIGTERM). Note - Processes can ignore some signals.		
<name of<br="">Process></name>	Specifies the name of the Check Point process to kill. To see the names of the processes, run the ps auxwf command.		

Example

fw kill fwd

fw log

Description

Shows the content of Check Point log files - Security (SFWDIR/log/*.log) or Audit (SFWDIR/log/*.adtlog).

Important:

- You can run this command in the Expert mode or in Gaia Clish (Gaia gClish on Scalable Platforms).
- On Scalable Platforms (ElasticXL, Maestro, and Chassis), you must connect to the Gaia Portal of the applicable Security Group.

Syntax

```
fw log {-h | -help}
fw [-d] log [-a] [-b "<Start Timestamp>" "<End Timestamp>"] [-c
<Action>] [{-f | -t}] [-g] [-H] [-h <Origin>] [-i] [-k {<Alert
Name> | all}] [-1] [-m {initial | semi | raw}] [-n] [-o] [-p] [-q]
[-S] [-s "<Start Timestamp>"] [-e "<End Timestamp>"] [-u
<Unification Scheme File>] [-w] [-x <Start Entry Number>] [-y <End
Entry Number>] [-z] [-#] [<Log File>]
```

Parameter	Description	
{-h -help}	Shows the built-in usage. Note - The built-in usage does not show some of the parameters described in this table.	
-d	 Runs the command in debug mode. Use only if you troubleshoot the command itself. Best Practice - If you use this parameter, then redirect the output to a file, or use the script command to save the entire CLI session. 	
-a	Shows only Account log entries.	

Parameter	Description			
-b " <start Timestamp>" "<end Timestamp>"</end </start 	 Shows only entries that were logged between the specified start and end times. The <start timestamp=""> and <end timestamp=""> may be a date, a time, or both.</end></start> If date is omitted, then the command assumes the current date. Enclose the "<start timestamp="">" and "<end timestamp=""> in single or double quotes (-b 'XX' 'YY", or -b "XX" "YY).</end></start> You cannot use the "-b" parameter together with the "-s" or "-e" parameters. See the date and time format below. 			
-c <action></action>	<pre>Shows only events with the specified action. One of these: accept drop reject encrypt decrypt vpnroute keyinst authorize deauthorize authcrypt ctl Notes: The fw log command always shows the Control (ctl) actions. For login action, use the authcrypt.</pre>			
-e " <end Timestamp>"</end 	 Shows only entries that were logged before the specified time. Notes: The <end timestamp=""> may be a date, a time, or both.</end> Enclose the <end timestamp=""> in single or double quotes (-e '', or -e "").</end> You cannot use the "-e" parameter together with the "-b" parameter. See the date and time format below. 			

Parameter	Description		
-f	 This parameter: 1. Shows the saved entries that match the specified conditions. 2. After the command reaches the end of the currently opened log file, it continues to monitor the log file indefinitely and shows the new entries that match the specified conditions. Note - Applies only to the <i>active</i> log file \$FWDIR/log/fw.log or \$FWDIR/log/fw.adtlog 		
-g	Does not show delimiters. The default behavior is: Show a colon (:) after a field name Show a semi-colon (;) after a field value		
-Н	Shows the High Level Log key.		
-h < <i>Origin</i> >	Shows only logs that were generated by the Security Gateway with the specified IP address or object name (as configured in SmartConsole).		
-i	Shows log UID.		
-k { <alert Name> all}</alert 	<pre>Shows entries that match a specific alert type:</pre>		
-1	Shows both the date and the time for each log entry. The default is to show the date only once above the relevant entries, and then specify the time for each log entry.		

Parameter	Description		
-m	Specifies the log unification mode:		
	 initial - Complete unification of log entries. The command shows one unified log entry for each ID. This is the default. If you also specify the -f parameter, then the output does not show any updates, but shows only entries that relate to the start of new connections. To shows updates, use the semi parameter. semi - Step-by-step unification of log entries. For each log entry, the output shows an entry that unifies this entry with all previously encountered entries with the same ID. raw - No log unification. The output shows all log entries. 		
-n	Does not perform DNS resolution of the IP addresses in the log file (this is the default behavior). This significantly speeds up the log processing.		
-0	Shows detailed log chains - shows all the log segments in the log entry.		
-p	Does not perform resolution of the port numbers in the log file (this is the default behavior). This significantly speeds up the log processing.		
-q	Shows the names of log header fields.		
-S	Shows the Sequence Number.		
-s " <start Timestamp>"</start 	 Shows only entries that were logged after the specified time. Notes: The <start timestamp=""> may be a date, a time, or both.</start> If the date is omitted, then the command assumed the current date. Enclose the <start timestamp=""> in single or double quotes (-s '', or -s "").</start> You cannot use the "-s" parameter together with the "-b" parameter. See the date and time format below. 		

Parameter	Description		
-t	This parameter:		
	 Does not show the saved entries that match the specified conditions. After the command reaches the end of the currently opened log file, it continues to monitor the log file indefinitely and shows the new entries that match the specified conditions. 		
	Note - Applies only to the <i>active</i> log file <pre>\$FWDIR/log/fw.log or \$FWDIR/log/fw.adtlog</pre>		
-u <unification Scheme File></unification 	Specifies the path and name of the log unification scheme file. The default log unification scheme file is: \$FWDIR/conf/log_unification_scheme.C		
-w	Shows the flags of each log entry (different bits used to specify the "nature" of the log - for example, control, audit, accounting, complementary, and so on).		
-x <start Entry Number></start 	Shows only entries from the specified log entry number and below, counting from the beginning of the log file.		
-y <end entry<br="">Number></end>	Shows only entries until the specified log entry number, counting from the beginning of the log file.		
-z	In case of an error (for example, wrong field value), continues to show log entries. The default behavior is to stop.		
-#	Show confidential logs in clear text.		
<log file=""></log>	Specifies the log file to read. If you do not specify the log file explicitly, the command opens the \$FWDIR/log/fw.log log file. You can specify a switched log file.		

Date and Time format

Part of timestamp	Format	Example
Date only	MMM DD, YYYY	June 11, 2018
Time only Note - In this case, the command assumes the current date.	HH:MM:SS	14:20:00
Date and Time	MMM DD, YYYY hh:MM:SS	June 11, 2018 14:20:00

Output

Each output line consists of a single log entry, whose fields appear in this format:

Note - The fields that show depends on the connection type.

HeaderDateHour ContentVersion HighLevelLogKey Uuid SequenceNum Flags Action Origin IfDir InterfaceName LogId ...

This table describes some of the fields.

Field Header	Description	Example
HeaderDateHour	Date and Time	12Jun2018 12:56:42
ContentVersion	Version	5
HighLevelLogKey	High Level Log Key	<max_null>, or empty</max_null>
Uuid	Log UUID	(0x5b1f99cb,0x0,0x3403a8c0,0xc00000 00)
SequenceNum	Log Sequence Number	1

Field Header	Description	Example
Flags	Internal flags that specify the "nature" of the log - for example, control, audit, accounting, complementary, and so on	428292
Action	Action performed on this connection	<pre>accept dropreject encrypt decrypt vpnroute keyinst authorize deauthorize authcrypt ctl</pre>
Origin	Object name of the Security Gateway that generated this log	МуGW
IfDir	Traffic direction through interface: < - Outbound (sent by a Security Gateway) > - Inbound (received by a Security Gateway) 	

Field Header	Description	Example
InterfaceName	Name of the Security Gateway interface, on which this traffic was logged If a Security Gateway performed some internal action (for example, log switch), then the log entry shows daemon	<pre>eth0 daemon N/A</pre>
LogId	Log ID	0
Alert	Alert Type	<pre>alert mail snmp_trap spoof user_alert user_auth</pre>
OriginSicName	SIC name of the Security Gateway that generated this log	CN=MyGW,O=MyDomain_ Server.checkpoint.com.s6t98x
inzone	Inbound Security Zone	Local
outzone	Outbound Security Zone	External
service_id	Name of the service used to inspect this connection	ftp

fw log

Field Header	Description	Example
src	Object name or IP address of the connection's source computer	MyHost
dst	Object name or IP address of the connection's destination computer	MyFTPServer
proto	Name of the connection's protocol	tcp
sport_svc	Source port of the connection	64933
ProductName	Name of the Check Point product that generated this log	 VPN-1 & FireWall-1 Application Control FloodGate-1
ProductFamily	Name of the Check Point product family that generated this log	Network

Examples

Example 1 - Show all log entries with both the date and the time for each log entry

fw log -l

Example 2 - Show all log entries that start after the specified timestamp

<pre>[Expert@MyGW:0]# fw log -l -s "June 12, 2018 12:33:00" 12Jun2018 12:33:00 5 N/A 1 accept MyGW > N/A LogId: <max_null>; ContextNum: <max_null>; OriginSicName: CN=MyGW,O=MyDomain_ Server.checkpoint.com.s6t98x; fg-1_client_in_rule_name: Default; fg-1_client_out_rule_name: Default; fg-1_server_in_rule_name: Host Redirect; fg-1_server_out_rule_name: ; ProductName: FG; ProductFamily: Network;</max_null></max_null></pre>
12Jun2018 12:33:39 5 N/A 1 drop MyGW < eth0 LogId: 0; ContextNum: <max_null>; OriginSicName: CN=MyGW,O=MyDomain_ Server.checkpoint.com.s6t98x; inzone: Local; outzone: External; service_id: ftp; src: MyGW; dst: MyFTPServer; proto: tcp; UP_match_ table: TABLE_START; ROW_START: 0; match_id: 2; layer_uuid: 4e26fc30-b345-4c96-b8d7-9db6aa7cdd89; layer_name: MyPolicy Network; rule_ uid: 802020d9-5cd-4c74-8e92-47e1boeb72e5; rule_name: ; ROW_END: 0; UP_match_table: TABLE_END; UP_action_table: TABLE_START; ROW_ START: 0; action: 0; ROW_END: 0; UP_action_table: TABLE_END; ProductName: VPN-1 & FireWall-1; svc: ftp; sport_svc: 64933; ProductFamily: Network;</max_null>
··· ··· ···
[Expert@MyGW:0]#

Example 3 - Show all log entries between the specified timestamps

```
[Expert@MyGW:0]# fw log -1 -b "June 12, 2018 12:33:00" 'June 12, 2018 12:34:00'
12Jun2018 12:33:00 5 N/A 1 accept MyGW > N/A LogId: <max_null>; ContextNum: <max_null>; OriginSicName: CN=MyGW,O=MyDomain_
Server.checkpoint.com.s6t98x; fg-1_client_in_rule_name: Default; fg-1_client_out_rule_name: Default; fg-1_server_in_rule_name: Host
Redirect; fg-1_server_out_rule_name: ; ProductName: FG; ProductFamily: Network;
12Jun2018 12:33:39 5 N/A 1 drop MyGW < eth0 LogId: 0; ContextNum: <max_null>; OriginSicName: CN=MyGW,O=MyDomain_
Server.checkpoint.com.s6t98x; inzone: Local; outzone: External; service_id: ftp; src: MyGW; dst: MyFTPServer; proto: tcp; UP_match_
table: TABLE_START; ROW_START: 0; match_id: 2; layer_uuid: 4e26fc30-b345-4c96-b8d7-9db6aa7cdd89; layer_name: MyPolicy Network; rule_
uid: 802020d9-5cdc-4c74-8e92-47e1b0eb72e5; rule_name: ; ROW_END: 0; UP_match_table: TABLE_END; UP_action_table: TABLE_START; ROW_
START: 0; action: 0; ROW_END: 0; UP_action_table: TABLE_END; ProductName: VPN-1 & FireWall-1; svc: ftp; sport_svc: 64933;
ProductFamily: Network;
12Jun2018 12:33:45 5 N/A 1 ctl MyGW > LogId: <max_null>; ContextNum: <max_null>; OriginSicName: CN=MyGW,O=MyDomain_
Server.checkpoint.com.s6t98x; description: Contracts; reason: Could not reach
"https://productcoverage.checkpoint.com/ProductCoverageService". Check DNS and Proxy configuration on the gateway.; Severity: 2;
status: Failed; version: 1.0; failure_impact: Contracts may be out-of-date; update_service: 1; ProductName: Security
Gateway/Management; ProductFamily: Network;
[Expert@WGW:0]#
```

Example 4 - Show all log entries with action "drop"

```
[Expert@MyGW:0] # fw log -l -c drop
12Jun2018 12:33:39 5 N/A 1 drop MyGW < eth0 LogId: 0; ContextNum: <max_null>; OriginSicName: CN=MyGW,O=MyDomain_
Server.checkpoint.com.s6t98x; inzone: Local; outzone: External; service_id: ftp; src: MyGW; dst: MyFTPServer; proto: tcp; UP_match_
table: TABLE_START, ROW_START: 0; match_id: 2; layer_uuid: 4e26fc30-b345-4c96-b8d7-9db6aa7cdd89; layer_name: MyPolicy Network; rule_
uid: 802020d9-5cdc-4c74-8e92-47e1b0eb72e5; rule_name: ; ROW_END: 0; UP_match_table: TABLE_END; UP_action_table: TABLE_START; ROW_
START: 0; action: 0; ROW_END: 0; UP_action_table: TABLE_END; ProductName: VPN-1 & FireWall-1; svc: ftp; sport_svc: 64933;
ProductFamily: Network;
[Expert@MyGW:0]#
```

Example 5 - Show all log entries with action "drop", show all field headers, and show log flags

```
[Expert@MyGW:0] # fw log -l -q -w -c drop
HeaderDateHour: 12Jun2018 12:33:39; ContentVersion: 5; HighLevelLogKey: <max_null>; LogUid: ; SequenceNum: 1; Flags: 428292; Action:
drop; Origin: MyGW; IfDir: <; InterfaceName: eth0; Alert: ; LogId: 0; ContextVum: <max_null>; OriginSicName: CN=MyGW,O=MyDomain_
Server.checkpoint.com.s6t98x; inzone: Local; outzone: External; service_id: ftp; src: MyGW; dst: MyFTPServer; proto: tcp; UP_match_
table: TABLE_START; ROW_START: 0; match_id: 2; layer_uuid: 4e26fc30-b345-4c96-b8d7-9db6aa7cdd89; layer_name: MyPOlicy Network; rule_
uid: 802020d9-5cdc-4c74-8e92-47e1b0eb72e5; rule_name: ; ROW_END: 0; UP_match_table: TABLE_END; UP_action_table: TABLE_START; ROW_
START: 0; action: 0; ROW_END: 0; UP_action_table: TABLE_END; ProductName: VPN-1 & FireWall-1; svc: ftp; sport_svc: 64933;
ProductFamily: Network;
[Expert@MyGW:0] #
```

Example 6 - Show only log entries from 0 to 10 (counting from the beginning of the log file)

[Expert@MyGW:0]# fw log -1 -x 0 -y 10 [Expert@MyGW:0]#

fw logswitch

Description

Switches the current active log file:

- 1. Closes the current active log file
- 2. Renames the current active log file
- 3. Creates a new active log file with the default name

Notes:

- By default, this command switches the active Security log file -\$FWDIR/log/fw.log
- You can specify to switch the active Audit log file \$FWDIR/log/fw.adtlog

Important:

- You can run this command in the Expert mode or in Gaia Clish (Gaia gClish on Scalable Platforms).
- On Scalable Platforms (ElasticXL, Maestro, and Chassis), you must connect to the Gaia Portal of the applicable Security Group.

Syntax

```
fw [-d] logswitch
      [-audit] [<Name of Switched Log>]
      -h <Target> [[+ | -]<Name of Switched Log>]
```

Parameter	Description
-d	 Runs the command in debug mode. Use only if you troubleshoot the command itself. Best Practice - If you use this parameter, then redirect the output to a file, or use the script command to save the entire CLI session.
-audit	Specifies to switch the active Audit log file (\$FWDIR/log/fw.adtlog). You can use this parameter only on a Management Server.

Parameter	Description
-h <target></target>	Specifies the remote computer, on which to switch the log. Notes:
	 The local and the remote computers must have established SIC trust. The remote computer can be a Security Gateway, a Log Server, or a Security Management Server in High Availability deployment. You can specify the remote managed computer by its main IP address or Object Name as configured in SmartConsole.
<name of<br="">Switched</name>	Specifies the name of the switched log file. Notes:
Log>	 If you do not specify this parameter, then a default name is: <yyyy-mm-dd_hhmmss>.log <yyyy-mm-dd_hhmmss>.adtlog</yyyy-mm-dd_hhmmss></yyyy-mm-dd_hhmmss> For example, 2018-03-26_174455.log If you specify the name of the switched log file, then the name of the switch log file is: <specified_log_name>.log <specified_log_name>.adtlog</specified_log_name></specified_log_name> The log switch operation fails if the specified name for the switched log matches the name of an existing log file. The maximum length of the specified name of the switched log file is 230 characters.
+	 Specifies to <i>copy</i> the active log from the remote computer to the local computer. Notes: If you specify the name of the switched log file, you must write it immediately after <i>this</i> + (plus) parameter. The command copies the active log from the remote computer and saves it in the \$FWDIR/log/ directory on the local computer. The default name of the saved log file is: <gateway_object_name><yyyy-mm-dd_hhmmss>.log</yyyy-mm-dd_hhmmss></gateway_object_name> For example, <i>MyGW_2018-03-26_174455.log</i> If you specify the name of the switched log file, then the name of the saved log file is: <gateway_object_name><specified_log_name>.log</specified_log_name></gateway_object_name> When this command copies the log file from the remote computer, it compresses the file.

Parameter	Description
-	Specifies to <i>transfer</i> the active log from the remote computer to the local computer. Notes:
	 The command saves the copied active log file in the \$FWDIR/log/directory on the local computer and then deletes the switched log file on the remote computer. If you specify the name of the switched log file, you must write it immediately after this - (minus) parameter. The default name of the saved log file is: <gateway_object_name>_<yyyy-mm-dd_hhmmss>.log</yyyy-mm-dd_hhmmss></gateway_object_name> For example, <i>MyGW_2018-03-26_174455.log</i> If you specify the name of the switched log file, then the name of the saved log file is: <gateway_object_name>_<specified_log_name>.log</specified_log_name></gateway_object_name> When this command transfers the log file from the remote computer, it compresses the file. As an alternative, you can use the "fw fetchlogs" on page 865 command.

Compression

When this command transfers the log files from the remote computer, it compresses the file with the gzip command (see RFC 1950 to RFC 1952 for details). The algorithm is a variation of LZ77 method. The compression ratio varies with the content of the log file and is difficult to predict. Binary data are not compressed. Text data, such as user names and URLs, are compressed.

Example - Switching the active Security log on a Security Management Server or Security Gateway

```
[Expert@MGMT:0]# fw logswitch
Log file has been switched to: 2018-06-13_182359.log
[Expert@MGMT:0]#
```

Example - Switching the active Audit log on a Security Management Server

```
[Expert@MGMT:0]# fw logswitch -audit
Log file has been switched to: 2018-06-13_185711.adtlog
[Expert@MGMT:0]#
```

Example - Switching the active Security log on a managed Security Gateway and copying the switched log

```
[Expert@MGMT:0]# fw logswitch -h MyGW +
Log file has been switched to: 2018-06-13_185451.log
[Expert@MGMT:0]#
[Expert@MGMT:0]# ls $FWDIR/log/*.log
/opt/CPsuite-R82/fw1/log/MyGW__2018-06-13_185451.log
[Expert@MGMT:0]#
[Expert@MgGW:0]# ls $FWDIR/log/*.log
/opt/CPsuite-R82/fw1/log/fw.log
/opt/CPsuite-R82/fw1/log/fw.log
/opt/CPsuite-R82/fw1/log/2018-06-13_185451.log
[Expert@MyGW:0]#
```

fw Islogs

Description

Shows a list of Security log files (\$FWDIR/log/*.log) and Audit log files (\$FWDIR/log/*.adtlog) residing on the local computer or a remote computer.

Important:

- You can run this command in the Expert mode or in Gaia Clish (Gaia gClish on Scalable Platforms).
- On Scalable Platforms (ElasticXL, Maestro, and Chassis), you must connect to the Gaia Portal of the applicable Security Group.

Syntax

```
fw [-d] lslogs [-f <Name of Log File 1>] [-f <Name of Log File 2>]
... [-f <Name of Log File N>] [-e] [-r] [-s {name | size | stime |
etime}] [<Target>]
```

Parameter	Description
-d	 Runs the command in debug mode. Use only if you troubleshoot the command itself. Best Practice - If you use this parameter, then redirect the output to a file, or use the script command to save the entire CLI session.
-f <name of Log File></name 	 Specifies the name of the log file to show. Need to specify name only. Notes: If the log file name is not specified explicitly, the command shows all Security log files (\$FWDIR/log/*.log). File names may include * and ? as wildcards (for example, 2019-0?-*). If you enter a wildcard, you must enclose it in double quotes or single quotes. You can specify multiple log files in one command. You must use the "-f" parameter for each log file name pattern: -f <name 1="" file="" log="" of=""> -f <name 2="" file="" log="" of="">f <name file="" log="" n="" of=""></name></name></name>

Parameter	Description
-e	Shows an extended file list. It includes the following information for each log file:
	 Size - The total size of the log file and its related pointer files Creation Time - The time the log file was created Closing Time - The time the log file was closed Log File Name - The file name
-r	Reverses the sort order (descending order).
-s {name size	Specifies the sort order of the log files using one of the following sort options:
stime etime}	 name - The file name size - The file size stime - The time the log file was created (this is the default option) etime - The time the log file was closed
<target></target>	Specifies the remote Check Point computer, with which this local Check Point computer has established SIC trust.
	 If you run this command on a Security Management Server or Domain Management Server, then <target> is the applicable object's name or main IP address of the Check Point Computer as configured in SmartConsole.</target> If you run this command on a Security Gateway or Cluster Member, then <target> is the main IP address of the applicable object as configured in SmartConsole.</target>

Example 1 - Default output

```
[Expert@HostName:0]# fw lslogs
Size Log file name
9KB 2019-06-14_000000.log
11KB 2019-06-15_000000.log
9KB 2019-06-16_000000.log
10KB 2019-06-17_000000.log
9KB fw.log
[Expert@HostName:0]#
```

Example 2 - Showing all log files

```
[Expert@HostName:0]# fw lslogs -f "*"
Size Log file name
9KB fw.adtlog
9KB fw.log
9KB 2019-05-29_000000.adtlog
9KB 2019-05-29_000000.log
9KB 2019-05-20_000000.adtlog
9KB 2019-05-20_000000.log
[Expert@HostName:0]#
```

Example 3 - Showing only log files specified by the patterns

```
[Expert@HostName:0]# fw lslogs -f "2019-06-14*" -f '2019-06-15*'
Size Log file name
9KB 2019-06-14_000000.adtlog
9KB 2019-06-14_000000.log
11KB 2019-06-15_000000.adtlog
11KB 2019-06-15_000000.log
[Expert@HostName:0]#
```

Example 4 - Showing only log files specified by the patterns and their extended information

```
[Expert@HostName:0]# fw lslogs -f "2019-06-14*" -f '2019-06-15*'
Size Log file name
9KB 2019-06-14_000000.adtlog
9KB 2019-06-14_000000.log
11KB 2019-06-15_000000.adtlog
11KB 2019-06-15_000000.log
[Expert@HostName:0]#
```

Example 5 - Showing only log files specified by the patterns, sorting by name in reverse order

```
[Expert@HostName:0]# fw lslogs -f "2019-06-14*" -f '2019-06-15*' -e -s name -r
Size Creation Time Closing Time Log file name
11KB 14Jun2018 0:00:00 15Jun2018 0:00:00 2019-06-15_000000.log
11KB 14Jun2018 0:00:00 15Jun2018 0:00:00 2019-06-15_000000.adtlog
9KB 13Jun2018 18:23:59 14Jun2018 0:00:00 2019-06-14_000000.log
9KB 13Jun2018 0:00:00 14Jun2018 0:00:00 2019-06-14_000000.adtlog
[Expert@HostName:0]#
```

Example 6 - Showing only log files specified by the patterns, from a managed Security Gateway with main IP address 192.168.3.53

fw mergefiles

Description

Merges several Security log files (*\$FWDIR/log/*.log*) into a single log file.

Merges several Audit log files (SFWDIR/log/*.adtlog) into a single log file.

Important:

Do not merge the active Security file \$FWDIR/log/fw.log with other Security switched log files.

Switch the active Security file *\$FWDIR/log/fw.log* (with the *"fw logswitch" on page 880* command) and only then merge it with other Security switched log files.

Do not merge the active Audit file \$FWDIR/log/fw.adtlog with other Audit switched log files.

Switch the active Audit file *\$FWDIR/log/fw.adtlog* (with the *"fw logswitch"* on page 880 command) and only then merge it with other Audit switched log files.

- This command unifies logs entries with the same Unique-ID (UID). If you rotate the current active log file before all the segments of a specific log arrive, this command merges the records with the same Unique ID from two different files, into one fully detailed record.
- If the size of the final merged log file exceeds 2GB, this command creates a list of merged files, where the size of each merged file size is not more than 2GB. The user receives this warning:

```
Warning: The size of the files you have chosen to merge
is greater than 2GB. The merge will produce two or more
files.
```

The names of merged files are:

- <Name of Merged Log File>.log
- <Name of Merged Log File>_1.log
- <Name of Merged Log File> 2.log
- • • • • •
- <Name of Merged Log File>_N.log

Important:

- You can run this command in the Expert mode or in Gaia Clish (Gaia gClish on Scalable Platforms).
- On Scalable Platforms (ElasticXL, Maestro, and Chassis), you must connect to the Gaia Portal of the applicable Security Group.

Syntax

```
fw [-d] mergefiles {-h | -help}
fw [-d] mergefiles [-r] [-s] [-t <Time Conversion File>] <Name of
Log File 1> <Name of Log File 2> ... <Name of Log File N> <Name of
Merged Log File>
```

Parameter	Description
-d	 Runs the command in debug mode. Use only if you troubleshoot the command itself. Best Practice - If you use this parameter, then redirect the output to a file, or use the script command to save the entire CLI session.
{-h -help}	Shows the built-in usage.
-r	Removes duplicate entries.
-s	Sorts the merged file by the Time field in log records.
-t <time conversion<br="">File></time>	Specifies a full path and name of a file that instructs this command how to adjust the times during the merge. This is required if you merge log files from Log Servers configured with different time zones. The file format is:
	<pre><ip #1="" address="" log="" of="" server=""> <signed #1="" date="" in="" seconds="" time=""> <ip #2="" address="" log="" of="" server=""> <signed #2="" date="" in="" seconds="" time=""></signed></ip></signed></ip></pre>
	 You must specify the absolute path and the file name.
	 The name of the time conversion file cannot exceed 230 characters.

Parameter	Description
<name 1="" file="" log="" of=""> <name file<br="" log="" of="">N></name></name>	 Specifies the log files to merge. Notes: You must specify the absolute path and the name of the input log files. The name of the input log file cannot exceed 230 characters.
<name log<br="" merged="" of="">File></name>	 Specifies the output merged log file. Notes: The name of the merged log file cannot exceed 230 characters. If a file with the specified name already exists, the command stops and asks you to remove the existing file, or to specify another name. The size of the merged log file cannot exceed 2 GB. In such scenario, the command creates several merged log files, each not exceeding the size limit.

Example - Merging Security log files

```
[Expert@HostName:0]# ls -1 $FWDIR/*.log
-rw-rw-r-- 1 admin root 189497 Sep 7 00:00 2019-09-07_000000.log
-rw-rw-r-- 1 admin root 14490 Sep 9 09:52 2019-09-09_000000.log
-rw-rw-r-- 1 admin root 30796 Sep 10 10:56 2019-09-10_000000.log
-rw-rw-r-- 1 admin root 24503 Sep 10 13:08 fw.log
[Expert@HostName:0]#
[Expert@HostName:0]# fw mergefiles -s $FWDIR/2019-09-07_000000.log $FWDIR/2019-09-09_000000.log
$FWDIR/2019-09-10_000000.log /var/log/2019-Sep-Merged.log
[Expert@HostName:0]# ls -1 /var/log/2019-Sep-Merged.log*
-rw-rw---- 1 admin root 213688 Sep 10 13:18 /var/log/2019-Sep-Merged.log
-rw-rw---- 1 admin root 8192 Sep 10 13:18 /var/log/2019-Sep-Merged.log
-rw-rw---- 1 admin root 80 Sep 10 13:18 /var/log/2019-Sep-Merged.logLuuidDB
-rw-rw---- 1 admin root 2264 Sep 10 13:18 /var/log/2019-Sep-Merged.logaccount_ptr
-rw-rw---- 1 admin root 4448 Sep 10 13:18 /var/log/2019-Sep-Merged.logInitial_ptr
-rw-rw---- 1 admin root 4448 Sep 10 13:18 /var/log/2019-Sep-Merged.logptr
[Expert@HostName:0]#
```

fw repairlog

Description

Check Point Security log file (*\$FWDIR/log/*.log*) and Audit log files (*\$FWDIR/log/*.adtlog*) are databases, with special pointer files.

If these log pointer files become corrupted (which causes the inability to read the log file), this command can rebuild them.

Log File Type	Log File Location	Log Pointer Files
Security log	\$FWDIR/log/*.log	*.logptr *.logaccount_ptr *.loginitial_ptr *.logLuuidDB
Audit log	\$FWDIR/log/*.adtlog	<pre>*.adtlogptr *.adtlogaccount_ptr *.adtloginitial_ptr *.adtlogLuuidDB</pre>

Important:

- You can run this command in the Expert mode or in Gaia Clish (Gaia gClish on Scalable Platforms).
- On Scalable Platforms (ElasticXL, Maestro, and Chassis), you must connect to the Gaia Portal of the applicable Security Group.

Syntax

```
fw [-d] repairlog [-u] <Name of Log File>
```

Parameter	Description
-d	 Runs the command in debug mode. Use only if you troubleshoot the command itself. Best Practice - If you use this parameter, then redirect the output to a file, or use the script command to save the entire CLI session.
-u	Specifies to rebuild the unification chains in the log file.
<name file="" log="" of=""></name>	The name of the log file to repair.

Example - Repairing the Audit log file

fw repairlog -u 2019-06-17_000000.adtlog

fw sam

Description

Manages the Suspicious Activity Monitoring (SAM) rules. You can use the SAM rules to block connections to and from IP addresses without the need to change or reinstall the Security Policy. For more information, see <u>sk112061</u>.

You can create the Suspicious Activity Rules in two ways:

- In SmartConsole from Monitoring Results
- In CLI with the fw sam command
- Notes:
 - See the "fw sam_policy" on page 901 and "sam_alert" on page 999 commands.
 - SAM rules consume some CPU resources on Security Gateway.
 - Best Practice The SAM Policy rules consume some CPU resources on Security Gateway. Set an expiration for rules that gives you time to investigate, but does not affect performance. Keep only the required SAM Policy rules. If you confirm that an activity is risky, edit the Security Policy, educate users, or otherwise handle the risk.
 - Logs for enforced SAM rules (configured with the fw sam command) are stored in the \$FWDIR/log/sam.dat file.

By design, the file is purged when the number of stored entries reaches 100,000.

This data log file contains the records in one of these formats:

<type>,<actions>,<expire>,<ipaddr>

<type>,<actions>,<expire>,<src>,<dst>,<dport>,<ip p>

- SAM Requests are stored on the Security Gateway in the kernel table sam_ requests.
- IP Addresses that are blocked by SAM rules, are stored on the Security Gateway in the kernel table sam blocked ips.

Note - To configure SAM Server settings for a Security Gateway or Cluster:

- 1. Connect with SmartConsole to the applicable Security Management Server or Domain Management Server.
- 2. From the left navigation panel, click Gateways & Servers.
- 3. Open the Security Gateway or Cluster object.
- 4. From the left tree, click **Other > SAM**.
- 5. Configure the settings.
- 6. Click OK.
- 7. Install the Access Control Policy on this Security Gateway or Cluster object.

Important:

- You can run this command in the Expert mode or in Gaia Clish (Gaia gClish on Scalable Platforms).
- In a Cluster, you must configure all the Cluster Members in the same way.
- On Scalable Platforms (ElasticXL, Maestro, and Chassis), you must connect to the Gaia Portal of the applicable Security Group.
- VSNext mode and Traditional VSX mode do not support Suspicious Activity Monitoring (SAM) Rules. See <u>sk79700</u>.

Syntax

• To add or cancel a SAM rule according to criteria:

```
fw [-d] sam [-v] [-s <SAM Server>] [-S <SIC Name of SAM
Server>] [-f <Security Gateway>] [-t <Timeout>] [-l <Log
Type>] [-C] [-e <key=val>]+ [-r] -{n|i|I|j|J} <Criteria>
```

To delete all SAM rules:

```
fw [-d] sam [-v] [-s <SAM Server>] [-S <SIC Name of SAM
Server>] [-f <Security Gateway>] -D
```

To monitor all SAM rules:

```
fw [-d] sam [-v] [-s <SAM Server>] [-S <SIC Name of SAM
Server>] [-f <Security Gateway>] [-r] -M -{i|j|n|b|q} all
```

• To monitor SAM rules according to criteria:

```
fw [-d] sam [-v] [-s <SAM Server>] [-S <SIC Name of SAM
Server>] [-f <Security Gateway>] [-r] -M -{i|j|n|b|q}
<Criteria>
```

Parameter	Description
-d	 Runs the command in debug mode. Use only if you troubleshoot the command itself. Best Practice - If you use this parameter, then redirect the output to a file, or use the script command to save the entire CLI session.

Parameter	Description
-v	Enables verbose mode. In this mode, the command writes one message to <i>stderr</i> for each Security Gateway, on which the command is enforced. These messages show whether the command was successful or not.
-s <sam Server></sam 	Specifies the IP address (in the X.X.X.X format) or resolvable HostName of the Security Gateway that enforces the command. The default is localhost.
-S <sic Name of SAM Server></sic 	 Specifies the SIC name for the SAM server to be contacted. It is expected that the SAM server has this SIC name, otherwise the connection fails. Notes: If you do not explicitly specify the SIC name, the connection continues without the SIC names comparison. For more information about enabling the SIC, refer to the OPSEC API Specification. On VSX Gateway, run the <i>fw vsx showncs -vs <vsid></vsid></i> command to show the SIC name for the applicable Virtual System.

Parameter	Description	
-f <security Gateway></security 	Specifies the Security Gateway, on which to enforce the action. <security gateway=""> can be one of these:</security>	
	 All - Default. Specifies to enforce the action on all managed Security Gateways, where SAM Server runs. You can use this syntax only on Security Management Server or Domain Management Server. <i>localhost</i> - Specifies to enforce the action on this local Check Point computer (on which the fw sam command is executed). You can use this syntax only on Security Gateway or StandAlone. <i>Gateways</i> - Specifies to enforce the action on all objects defined as Security Gateways, on which SAM Server runs. You can use this syntax only on Security Management Server or Domain Management Server. <i>Name of Security Gateway object</i> - Specifies to enforce the action on this specific Security Gateway object. You can use this syntax only on Security Management Server or Domain Management Server. <i>Name of Group object</i> - Specifies to enforce the action on all specific Security Gateways in this Group object. Notes: 	
	 You can use this syntax only on Security Management Server or Domain Management Server. VSX Gateways and VSX Cluster Members do not support Suspicious Activity Monitoring (SAM) Rules. See <u>sk79700</u>. 	
-D	 Cancels all inhibit ("-i", "-j", "-I", "-J") and notify ("-n") parameters. Notes: To "uninhibit" the inhibited connections, run the fw sam command with the "-C" or "-D" parameters. It is also possible to use this command for active SAM requests. 	
-C	 Cancels the fw sam command to inhibit connections with the specified parameters. Notes: These connections are no longer inhibited (no longer rejected or dropped). The command parameters must match the parameters in the original fw sam command, except for the -t <timeout> parameter.</timeout> 	

Parameter	Description
-t <timeout></timeout>	Specifies the time period (in seconds), during which the action is enforced. The default is forever, or until you cancel the fw sam command.
-l <log Type></log 	Specifies the type of the log for enforced action:
	 nolog - Does not generate Log / Alert at all short_noalert - Generates a Log short_alert - Generates an Alert long_noalert - Generates a Log long_alert - Generates an Alert (this is the default)
-e <key=val>+</key=val>	Specifies rule information based on the keys and the provided values. Multiple keys are separated by the plus sign (+). Available keys are (each is limited to 100 characters):
	 name - Security rule name comment - Security rule comment originator - Security rule originator's username
-r	Specifies not to resolve IP addresses.
-n	 Specifies to generate a "Notify" long-format log entry. Notes: This parameter generates an alert when connections that match
	 the specified services or IP addresses pass through the Security Gateway. This action does not inhibit / close connections.
-i	Inhibits (drops or rejects) new connections with the specified parameters. Notes:
	Each inhibited connection is logged according to the log type.Matching connections are rejected.
-I	Inhibits (drops or rejects) new connections with the specified parameters, and closes all existing connections with the specified parameters. Notes:
	 Matching connections are rejected. Each inhibited connection is logged according to the log type.
-j	Inhibits (drops or rejects) new connections with the specified parameters. Notes:
	 Matching connections are dropped. Each inhibited connection is logged according to the log type.

Parameter	Description
-J	Inhibits new connections with the specified parameters, and closes all existing connections with the specified parameters. Notes:
	 Matching connections are dropped. Each inhibited connection is logged according to the log type.
-b	Bypasses new connections with the specified parameters.
-d	Quarantines new connections with the specified parameters.
-М	Monitors the active SAM requests with the specified actions and criteria.
all	Gets all active SAM requests. This is used for monitoring purposes only.
<criteria></criteria>	Criteria are used to match connections. The criteria and are composed of various combinations of the following parameters:
	 Source IP Address Source Netmask Destination IP Address
	 Destination Netmask Port (see <u>IANA Service Name and Port Number Registry</u>)
	 Protocol Number (see <u>IANA Protocol Numbers</u>)

Parameter	Description
	Possible combinations are (see the explanations below this table):
	<pre>src <ip> dst <ip> dst <ip> any <ip> subsrc <ip <netmask=""> subdst <ip <netmask=""> subany <ip <netmask=""> subany <ip <netmask=""> subarv <src <dest="" <port="" <protocol="" ip=""> subsrv <src <src="" ip="" netmask=""> <dest <dest="" ip="" netmask=""> <port <protocol=""> subsrvs <src <src="" ip="" netmask=""> <dest <port="" <protocol="" ip=""> subsrvs <src <src="" ip="" netmask=""> <dest <port="" <protocol="" ip=""> subsrvs <src <src="" ip="" netmask=""> <dest <port="" <protocol="" ip=""> subsrvs <src <src="" ip="" netmask=""> <dest <port="" <protocol="" ip=""> </dest></src></dest></src></dest></src></dest></src></port></dest></src></src></ip></ip></ip></ip></ip></ip></ip></ip></pre>
	<pre><protocol> dstsrv <dest ip=""> <port> <protocol> subdstsrv <dest ip=""> <dest netmask=""> <port> <protocol> srcpr <ip> <protocol> dstpr <ip> <protocol> subsrcpr <ip> <netmask> <protocol> generic <key=val></key=val></protocol></netmask></ip></protocol></ip></protocol></ip></protocol></port></dest></dest></protocol></port></dest></protocol></pre>

Explanation for the <*Criteria*> syntax

Parameter	Description
<pre>src <ip></ip></pre>	Matches the Source IP address of the connection.
dst <ip></ip>	Matches the Destination IP address of the connection.
any < <i>IP</i> >	Matches either the Source IP address or the Destination IP address of the connection.
<pre>subsrc <ip> <netmask></netmask></ip></pre>	Matches the Source IP address of the connections according to the netmask.
subdst <ip> <netmask></netmask></ip>	Matches the Destination IP address of the connections according to the netmask.

Parameter	Description
subany <ip> <netmask></netmask></ip>	Matches either the Source IP address or Destination IP address of connections according to the netmask.
srv <src ip=""> <dest ip=""> <port> <protocol></protocol></port></dest></src>	Matches the specific Source IP address, Destination IP address, Service (port number) and Protocol.
subsrv <src ip=""> <netmask> <dest ip=""> <netmask> <port> <protocol></protocol></port></netmask></dest></netmask></src>	Matches the specific Source IP address, Destination IP address, Service (port number) and Protocol. Source and Destination IP addresses are assigned according to the netmask.
subsrvs <i><src ip=""> <src< i=""> Netmask> <i><dest ip=""> <port></port></dest></i> <i><protocol></protocol></i></src<></src></i>	Matches the specific Source IP address, source netmask, destination netmask, Service (port number) and Protocol.
subsrvd <i><src ip=""> <dest ip=""></dest></src></i> <i><dest netmask=""> <port></port></dest></i> <i><protocol></protocol></i>	Matches specific Source IP address, Destination IP, destination netmask, Service (port number) and Protocol.
dstsrv <dest ip=""> <service> <protocol></protocol></service></dest>	Matches specific Destination IP address, Service (port number) and Protocol.
subdstsrv < <i>Dest IP</i> > <netmask> <port> <protocol></protocol></port></netmask>	Matches specific Destination IP address, Service (port number) and Protocol. Destination IP address is assigned according to the netmask.
<pre>srcpr <ip> <protocol></protocol></ip></pre>	Matches the Source IP address and protocol.
dstpr <ip> <protocol></protocol></ip>	Matches the Destination IP address and protocol.
subsrcpr <ip> <netmask> <protocol></protocol></netmask></ip>	Matches the Source IP address and protocol of connections. Source IP address is assigned according to the netmask.
subdstpr <ip> <netmask> <protocol></protocol></netmask></ip>	Matches the Destination IP address and protocol of connections. Destination IP address is assigned according to the netmask.

Parameter	Description
generic < <i>key=val</i> >+	Matches the GTP connections based on the specified keys and provided values. Multiple keys are separated by the plus sign (+). Available keys are:
	<pre>service=gtp imsi msisdn apn tunl_dst tunl_dport tunl_proto</pre>

fw sam_policy

Description

Manages the Suspicious Activity Policy editor that works with these types of rules:

Suspicious Activity Monitoring (SAM) rules.

See sk112061: How to create and view Suspicious Activity Monitoring (SAM) Rules.

Rate Limiting rules.

See sk182350 - How to configure Rate Limiting rules for DoS Mitigation.

Also, see these commands:

- "fw sam" on page 892
- "sam_alert" on page 999

Notes:

- These commands are interchangeable:
 - For IPv4: "fw sam policy" and "fw samp".
 - For IPv6: "fw6 sam_policy" and "fw6 samp".
- You can run these commands in Gaia Clish, or Expert mode.
- Security Gateway stores the SAM Policy rules in the \$FWDIR/database/sam policy.db file.
- Security Gateway stores the SAM Policy management settings in the \$FWDIR/database/sam_policy.mng file.

Important:

- Configuration you make with these commands, survives reboot.
- You can run this command in the Expert mode or in Gaia Clish (Gaia gClish on Scalable Platforms).
- In a Cluster, you must configure all the Cluster Members in the same way.
- On Scalable Platforms (ElasticXL, Maestro, and Chassis), you must connect to the Gaia Portal of the applicable Security Group.
- VSNext mode and Traditional VSX mode do not support Suspicious Activity Monitoring (SAM) Rules. See <u>sk79700</u>.

Best Practice - The SAM Policy rules consume some CPU resources on Security Gateway. Set an expiration for rules that gives you time to investigate, but does not affect performance. Keep only the required SAM Policy rules. If you confirm that an activity is risky, edit the Security Policy, educate users, or otherwise handle the risk.

Syntax for IPv4

fw	[-d] sa	am_policy
	add	<options></options>
	bato	ch
	del	<options></options>
	get	<options></options>
fw	[-d] sa	amp
fw		amp <options></options>
fw		<options></options>
fw	add bato	<options></options>

Syntax for IPv6

fw6	[-d] s	sam_policy
	add	<options></options>
	bato	ch
	del	<options></options>
	get	<options></options>
fw6	[-d] s	samp
	add	<options></options>
	bato	ch
	del	<options></options>
	get	<options></options>

Parameter	Description
-d	 Runs the command in debug mode. Use only if you troubleshoot the command itself. Best Practice - If you use this parameter, then redirect the output to a file, or use the script command to save the entire CLI session.
add < <i>options</i> >	Adds one Rate Limiting rule one at a time. See "fw sam_policy add" on page 904.
batch	Adds or deletes many Rate Limiting rules at a time. See "fw sam_policy batch" on page 917.
del < <i>options</i> >	Deletes one configured Rate Limiting rule one at a time. See "fw sam_policy del" on page 919.
get < <i>options</i> >	Shows all the configured Rate Limiting rules. See "fw sam_policy get" on page 923.

fw sam_policy add

Description

The "fw sam_policy add" and "fw6 sam_policy add" commands:

- Add one Suspicious Activity Monitoring (SAM) rule at a time.
- Add one Rate Limiting rule at a time.

Notes:

- These commands are interchangeable:
 - For IPv4: "fw sam policy" and "fw samp".
 - For IPv6: "fw6 sam_policy" and "fw6 samp".
- You can run these commands in Gaia Clish, or Expert mode.
- Security Gateway stores the SAM Policy rules in the \$FWDIR/database/sam policy.db file.
- Security Gateway stores the SAM Policy management settings in the \$FWDIR/database/sam_policy.mng file.

Important:

- Configuration you make with these commands, survives reboot.
- You can run this command in the Expert mode or in Gaia Clish (Gaia gClish on Scalable Platforms).
- In a Cluster, you must configure all the Cluster Members in the same way.
- On Scalable Platforms (ElasticXL, Maestro, and Chassis), you must connect to the Gaia Portal of the applicable Security Group.
- VSNext mode and Traditional VSX mode do not support Suspicious Activity Monitoring (SAM) Rules. See <u>sk79700</u>.

Best Practice - The SAM Policy rules consume some CPU resources on Security Gateway. Set an expiration for rules that gives you time to investigate, but does not affect performance. Keep only the required SAM Policy rules. If you confirm that an activity is risky, edit the Security Policy, educate users, or otherwise handle the risk.

Syntax to configure a Suspicious Activity Monitoring (SAM) rule for IPv4

```
fw [-d] sam_policy add [-u] -a {d|n|b} [-l {r|a}] [-t <Timeout>]
[-f <Target>] [-n <"Rule Name">] [-c <"Rule Comment">] [-o <"Rule
Originator">] [-z "<Zone>"] ip <IP Filter Arguments>
```

Syntax to configure a Suspicious Activity Monitoring (SAM) rule for IPv6

```
fw6 [-d] sam_policy add [-u] -a {d|n|b} [-l {r|a}] [-t <Timeout>]
[-f <Target>] [-n <"Rule Name">] [-c <"Rule Comment">] [-o <"Rule
Originator">] [-z "<Zone>"] ip <IP Filter Arguments>
```

Syntax to configure a Rate Limiting rule for IPv4

```
fw [-d] sam_policy add [-u] -a {d|n|b} [-l {r|a}] [-t <Timeout>]
[-f <Target>] [-n <"Rule Name">] [-c <"Rule Comment">] [-o <"Rule
Originator">] [-z "<Zone>"] quota <Quota Filter Arguments>
```

Syntax to configure a Rate Limiting rule for IPv6

```
fw6 [-d] sam_policy add [-u] -a {d|n|b} [-l {r|a}] [-t <Timeout>]
[-f <Target>] [-n <"Rule Name">] [-c <"Rule Comment">] [-o <"Rule
Originator">] [-z "<Zone>"] quota <Quota Filter Arguments</pre>
```

Parameter	Description
-d	 Runs the command in debug mode. Use only if you troubleshoot the command itself. Best Practice - If you use this parameter, then redirect the output to a file, or use the script command to save the entire CLI session.
-u	Optional. Specifies that the rule category is User-defined. Default rule category is Auto.
-a {d n b}	 Mandatory. Specifies the rule action if the traffic matches the rule conditions: d - Drop the connection. n - Notify (generate a log) about the connection and let it through. b - Bypass the connection - let it through without checking it against the policy rules. Note - Rules with action set to <i>Bypass</i> cannot have a log or limit specification. Bypassed packets and connections do not count towards overall number of packets and connection for limit
	enforcement of type ratio.

Parameter	Description
-l {r a}	Optional. Specifies which type of log to generate for this rule for all traffic that matches:
	 -r - Generate a regular log -a - Generate an alert log
-t <timeout></timeout>	Optional. Specifies the time period (in seconds), during which the rule will be enforced. Default timeout is indefinite.
-f <target></target>	Optional. Specifies the target Security Gateways, on which to enforce the Rate Limiting rule. <target> can be one of these:</target>
	 all - This is the default option. Specifies that the rule should be enforced on all managed Security Gateways. Name of the Security Gateway or Cluster object - Specifies that the rule should be enforced only on this Security Gateway or Cluster object (the object name must be as defined in the SmartConsole). Name of the Group object - Specifies that the rule should be enforced on all Security Gateways that are members of this Group object (the object name must be as defined in the SmartConsole).
-n " <rule Name>"</rule 	Optional. Specifies the name (label) for this rule. Notes:
	 You must enclose this string in double quotes. The length of this string is limited to 128 characters. Before each space or a backslash character in this string, you must write a backslash (\) character. Example:
	"This\ is\ a\ rule\ name\ with\ a\ backslash\ \\"

Parameter	Description
-c " <rule Comment>"</rule 	Optional. Specifies the comment for this rule. Notes:
	 You must enclose this string in double quotes. The length of this string is limited to 128 characters. Before each space or a backslash character in this string, you must write a backslash (\) character. Example: "This\ is\ a\ comment\ with\ a\ backslash\ \\"
-o " <rule Originator >"</rule 	Optional. Specifies the name of the originator for this rule. Notes:
	 You must enclose this string in double quotes. The length of this string is limited to 128 characters. Before each space or a backslash character in this string, you must write a backslash (\) character. Example:
	"Created\ by\ John\ Doe"
-z " <zone>"</zone>	Optional. Specifies the name of the Security Zone for this rule. Notes:
	 You must enclose this string in double quotes. The length of this string is limited to 128 characters.
ip <ip Filter Arguments></ip 	Mandatory (use this ip parameter, or the quota parameter). Configures the <i>Suspicious Activity Monitoring (SAM)</i> rule. Specifies the IP Filter Arguments for the SAM rule (you must use at least one of these options):
	<pre>[-C] [-s <source ip=""/>] [-m <source mask=""/>] [-d <destination ip="">] [-M <destination mask="">] [-p <port>] [-r <protocol>]</protocol></port></destination></destination></pre>
	See the explanations below.

Parameter	Description
quota <quota Filter Arguments></quota 	Mandatory (use this quota parameter, or the ip parameter). Configures the <i>Rate Limiting</i> rule. Specifies the Quota Filter Arguments for the Rate Limiting rule (see the explanations below):
	<pre>[flush true] [flush true] [source-negated {true false}] source <source/> [destination-negated {true false}] destination <destination> [service-negated {true false}] service <protocol and="" numbers="" port=""> [<limit1 name=""> <limit1 value="">] [<limit2 name=""> <limit2 value="">][<limitn name=""> <limitn value="">] [track <track/>]</limitn></limitn></limit2></limit2></limit1></limit1></protocol></destination></pre>
	 Important: The Quota rules are not applied immediately to the Security Gateway. They are only registered in the Suspicious Activity Monitoring (SAM) policy database. To apply all the rules from the SAM policy database immediately, add "flush true" in the fw samp add command syntax. Explanation: For new connections rate (and for any rate limiting in general), when a rule's limit is violated, the Security Gateway also drops all packets that match the rule. The Security Gateway computes new connection rates on a per-second basis. At the start of the 1-second timer, the Security Gateway allows all packets, including packets for existing connections. If, at some point, during that 1 second period, there are too many new connections, then the Security Gateway blocks all remaining packets for the remainder of that 1-second interval. At the start of the next 1-second interval, the counters are reset, and the process starts over - the Security Gateway allows packets to pass again up to the point, where the rule's limit is violated.

Explanation for the *IP Filter Arguments* syntax for Suspicious Activity Monitoring (SAM) rules

Argument	Description
-C	Specifies that open connections should be closed.
-s <source ip=""/>	Specifies the Source IP address.
-m < <i>Source Mask</i> >	Specifies the Source subnet mask (in dotted decimal format - x.y.z.w).
-d <destination IP></destination 	Specifies the Destination IP address.
-M <destination Mask></destination 	Specifies the Destination subnet mask (in dotted decimal format - x.y.z.w).
-p < <i>Port</i> >	Specifies the port number (see <u>IANA Service Name and Port</u> <u>Number Registry</u>).
-r <protocol></protocol>	Specifies the protocol number (see <u>IANA Protocol Numbers</u>).

Explanation for the Quota Filter Arguments syntax for Rate Limiting rules

Argument	Description
flush true	Specifies to compile and load the quota rule to the SecureXL immediately.
<pre>[source-negated {true false}] source <source/></pre>	<pre>Specifies the source type and its value: any The rule is applied to packets sent from all sources. range:<ip address=""> or range:<ip address=""> or range:<ip address="" start="">-<ip address="" end=""> The rule is applied to packets sent from: Specified IPv4 addresses (x.y.z.w) Specified IPv6 addresses (xxx:yyyy::zzzz) cidr:<ip address="" v<prefix=""> The rule is applied to packets sent from: IPv4 address with Prefix from 0 to 32 IPv6 address with Prefix from 0 to 128 cc:<country code=""> The rule matches the country code to the source IP addresses assigned to this country, based on the Geo IP database. The rule matches the AS number> The rule matches the AS number of the organization to the source IP addresses that are assigned to this organization, based on the Geo IP database. The rule matches the AS number of the organization to the source IP addresses that are assigned to this organization, based on the Geo IP database. The rule matches the AS number of the organization to the source IP addresses that are assigned to this organization, based on the Geo IP database. The rule matches the AS number of the organization to the source IP addresses that are assigned to this organization, based on the Geo IP database. The valid syntax is ASnnnn, where nnnn is a number unique to the specific organization.</country></ip></ip></ip></ip></ip></pre>
	Notes:
	 Default is: source-negated false The source-negated true processes all source types, except the specified type.

Argument	Description
<pre>[destination-negated {true false}] destination <destination></destination></pre>	<pre>Specifies the destination type and its value: any The rule is applied to packets sent to all destinations. range:<ip address=""> or range:<ip address="" start="">-<ip address="" end=""> The rule is applied to packets sent to: Specified IPv4 addresses (x.y.z.w) Specified IPv6 addresses (xxx:yyyy::zzzz) cidr:<ip 0="" 128="" 32="" address="" cc:<country="" code="" from="" ipv6="" prefix="" to="" with=""> The rule matches the country code to the destination IP addresses assigned to this country, based on the Geo IP database. The two-letter codes are defined in ISO 3166-1 alpha-2. asn:<autonomous number="" system=""> The rule matches the AS number of the organization to the destination IP addresses that are assigned to this organization, based on the Geo IP database. The rule matches the AS number of the organization to the destination IP addresses that are assigned to this organization, based on the Geo IP database. The valid syntax is ASnnnn, where nnnn is a number unique to the specific organization. </autonomous></ip></ip></ip></ip></pre>
	 Default is: destination-negated false The destination-negated true will process all destination types except the specified type

Argument	Description
[service-negated {true false}] service <protocol and Port numbers></protocol 	Specifies the Protocol number (see <u>IANA Protocol</u> <u>Numbers</u>) and Port number (see <u>IANA Service</u> <u>Name and Port Number Registry</u>): <protocol></protocol> IP protocol number in the range 1-255 <protocol start="">-<protocol end=""></protocol></protocol>
	Range of IP protocol numbers <pre><protocol>/<port> IP protocol number in the range 1-255 and TCP/UDP port number in the range 1-65535 <pre><protocol>/<port start="">-<port end=""> IP protocol number and range of TCP/UDP port numbers from 1 to 65535</port></port></protocol></pre></port></protocol></pre>
	Notes:
	 Default is: service-negated false The service-negated true will process all traffic except the traffic with the specified protocols and ports

Argument	Description
<pre>[<limit 1="" name=""> <limit 1<br="">Value>] [<limit 2="" name=""> <limit 2="" value="">] [<limit n="" name=""> <limit n<br="">Value>]</limit></limit></limit></limit></limit></limit></pre>	<pre>Specifies quota limits and their values. Note - Separate multiple quota limits with spaces. concurrent-conns <value> Specifies the maximum number of concurrent-conns-ratio <value> Specifies the maximum ratio of the concurrent-conns value to the total number of active connections through the Security Gateway, expressed in parts per 65536 (formula: N / 65536). pkt-rate <value> Specifies the maximum number of packets per second that match this rule. pkt-rate-ratio <value> Specifies the maximum ratio of the <i>pkt-rate</i> value to the rate of all connections through the Security Gateway, expressed in parts per 65536 (formula: N / 65536). byte-rate <value> Specifies the maximum total number of bytes per second in packets that match this rule. byte-rate <value> Specifies the maximum total number of bytes per second in packets that match this rule. byte-rate-ratio <value> Specifies the maximum ratio of the <i>byte-rate</i> value to the bytes per second rate of all connections through the Security Gateway, expressed in parts per 65536 (formula: N / 65536). new-conn-rate <value> Specifies the maximum number of connections per second that match the rule. new-conn-rate-ratio <value> Specifies the maximum ratio of the <i>new- conn-rate</i> -ratio <value> Specifies the maximum ratio of the <i>new- conn-rate</i> -ratio <value> Specifies the maximum ratio of the <i>new- conn-rate</i> value to the rate of all connections per second through the Security Gateway, expressed in parts per 65536 (formula: N / 65536).</value></value></value></value></value></value></value></value></value></value></value></pre>

Argument	Description
[track < <i>Track</i> >]	 Specifies the tracking option: source counts connections, packets, and bytes for specific source IP address, and not cumulatively for this rule. source-service counts connections, packets, and bytes for specific source IP address, and for specific
	IP protocol and destination port, and not cumulatively for this rule.

Examples

Example 1 - Rate Limiting rule with a range

fw sam_policy add -a d -l r -t 3600 quota service any source range:172.16.7.11-172.16.7.13 new-conn-rate 5 flush true

Explanations:

- This rule drops packets for all connections (-a d) that exceed the quota set by this rule, including packets for existing connections.
- This rule logs packets (-1 r) that exceed the quota set by this rule.
- This rule will expire in 3600 seconds (-t 3600).
- This rule limits the rate of creation of new connections to 5 connections per second (new-conn-rate 5) for any traffic (service any) from the source IP addresses in the range 172.16.7.11 - 172.16.7.13 (source range:172.16.7.11-172.16.7.13).

Note - The limit of the total number of log entries per second is configured with the *fwaccel dos config set -n <rate>* command.

This rule will be compiled and loaded on the SecureXL, together with other rules in the Suspicious Activity Monitoring (SAM) policy database immediately, because this rule includes the "flush true" parameter.

Example 2 - Rate Limiting rule with a service specification

fw sam_policy add -a n -l r quota service 1,50-51,6/443,17/53 service-negated true source cc:QQ byte-rate 0

Explanations:

- This rule logs and lets through all packets (-a n) that exceed the quota set by this rule.
- This rule does not expire (the timeout parameter is not specified). To cancel it, you must delete it explicitly.
- This rule applies to all packets except (service-negated true) the packets with IP protocol number 1, 50-51, 6 port 443 and 17 port 53 (service 1, 50-51, 6/443, 17/53).
- This rule applies to all packets from source IP addresses that are assigned to the country with specified country code (cc:QQ).
- This rule does not let any traffic through (byte-rate 0) except the packets with IP protocol number 1, 50-51, 6 port 443 and 17 port 53.
- This rule will not be compiled and installed on the SecureXL immediately, because it does not include the "flush true" parameter.

Example 3 - Rate Limiting rule with ASN

fw sam_policy -a d quota source asn:AS64500,cidr:[::FFFF:COA8:1100]/120 service any pkt-rate 0

Explanations:

- This rule drops (-a d) all packets that match this rule.
- This rule does not expire (the timeout parameter is not specified). To cancel it, you must delete it explicitly.
- This rule applies to packets from the Autonomous System number 64500 (asn:AS64500).
- This rule applies to packets from source IPv6 addresses FFFF:C0A8:1100/120 (cidr: [::FFFF:C0A8:1100]/120).
- This rule applies to all traffic (service any).
- This rule does not let any traffic through (pkt-rate 0).
- This rule will not be compiled and installed on the SecureXL immediately, because it does not include the "flush true" parameter.

Example 4 - Rate Limiting rule with an Allow List

fw sam_policy add -a b quota source range:172.16.8.17-172.16.9.121 service 6/80

Explanations:

• This rule bypasses (-a b) all packets that match this rule.

Note - The Access Control Policy and other types of security policy rules still apply.

- This rule does not expire (the timeout parameter is not specified). To cancel it, you must delete it explicitly.
- This rule applies to packets from the source IP addresses in the range 172.16.8.17 172.16.9.121 (range:172.16.8.17-172.16.9.121).
- This rule applies to packets sent to TCP port 80 (service 6/80).
- This rule will not be compiled and installed on the SecureXL immediately, because it does not include the "flush true" parameter.

Example 5 - Rate Limiting rule with tracking

fw sam_policy add -a d quota service any source-negated true source cc:QQ concurrent-conns-ratio 655 track source

Explanations:

- This rule drops (-a d) all packets that match this rule.
- This rule does not log any packets (the -1 r parameter is not specified).
- This rule does not expire (the timeout parameter is not specified). To cancel it, you must delete it explicitly.
- This rule applies to all traffic (service any).
- This rule applies to all sources except (source-negated true) the source IP addresses that are assigned to the country with specified country code (cc:QQ).
- This rule limits the maximum number of concurrent active connections to 655/65536=~1% (concurrent-conns-ratio 655) for any traffic (service any) except (service-negated true) the connections from the source IP addresses that are assigned to the country with specified country code (cc:QQ).
- This rule counts connections, packets, and bytes for traffic only from sources that match this rule, and not cumulatively for this rule.
- This rule will not be compiled and installed on the SecureXL immediately, because it does not include the "flush true" parameter.

fw sam_policy batch

Description

The "fw sam_policy batch" and "fw6 sam_policy batch" commands:

- Add and delete many Suspicious Activity Monitoring (SAM) rules at a time.
- Add and delete many Rate Limiting rules at a time.

Notes:

- These commands are interchangeable:
 - For IPv4: "fw sam policy" and "fw samp".
 - For IPv6: "fw6 sam_policy" and "fw6 samp".
- You can run these commands in Gaia Clish, or Expert mode.
- Security Gateway stores the SAM Policy rules in the \$FWDIR/database/sam policy.db file.
- Security Gateway stores the SAM Policy management settings in the \$FWDIR/database/sam policy.mng file.

Important:

- Configuration you make with these commands, survives reboot.
- You can run this command in the Expert mode or in Gaia Clish (Gaia gClish on Scalable Platforms).
- In a Cluster, you must configure all the Cluster Members in the same way.
- On Scalable Platforms (ElasticXL, Maestro, and Chassis), you must connect to the Gaia Portal of the applicable Security Group.
- VSNext mode and Traditional VSX mode do not support Suspicious Activity Monitoring (SAM) Rules. See <u>sk79700</u>.

Best Practice - The SAM Policy rules consume some CPU resources on Security Gateway. Set an expiration for rules that gives you time to investigate, but does not affect performance. Keep only the required SAM Policy rules. If you confirm that an activity is risky, edit the Security Policy, educate users, or otherwise handle the risk.

Procedure

- 1. Start the batch mode
 - For IPv4, run:

fw sam policy batch << EOF

For IPv6, run:

```
fw6 sam_policy batch << EOF</pre>
```

- 2. Enter the applicable commands
 - Enter one "add" or "del" command on each line, on as many lines as necessary.

Start each line with only "add" or "del" parameter (not with "fw samp").

- Use the same set of parameters and values as described in these commands:
 - "fw sam_policy add" on page 904
 - "fw sam_policy del" on page 919
- Terminate each line with a Return (ASCII 10 Line Feed) character (press Enter).

3. End the batch mode

Type EOF and press Enter.

Example of a Rate Limiting rule for IPv4

```
[Expert@HostName]# fw samp batch <<EOF
add -a d -l r -t 3600 -c "Limit\ conn\ rate\ to\ 5\ conn/sec from\ these\ sources" quota service
any source range:172.16.7.13-172.16.7.13 new-conn-rate 5
del <501f6ef0,00000000,cb38a8c0,0a0afffe>
add -a b quota source range:172.16.8.17-172.16.9.121 service 6/80
EOF
[Expert@HostName]#
```

fw sam_policy del

Description

The "fw sam_policy del" and "fw6 sam_policy del" commands:

- Delete one configured Suspicious Activity Monitoring (SAM) rule at a time.
- Delete one configured Rate Limiting rule at a time.

Notes:

- These commands are interchangeable:
 - For IPv4: "fw sam policy" and "fw samp".
 - For IPv6: "fw6 sam_policy" and "fw6 samp".
- You can run these commands in Gaia Clish, or Expert mode.
- Security Gateway stores the SAM Policy rules in the \$FWDIR/database/sam policy.db file.
- Security Gateway stores the SAM Policy management settings in the \$FWDIR/database/sam_policy.mng file.

Important:

- Configuration you make with these commands, survives reboot.
- You can run this command in the Expert mode or in Gaia Clish (Gaia gClish on Scalable Platforms).
- In a Cluster, you must configure all the Cluster Members in the same way.
- On Scalable Platforms (ElasticXL, Maestro, and Chassis), you must connect to the Gaia Portal of the applicable Security Group.
- VSNext mode and Traditional VSX mode do not support Suspicious Activity Monitoring (SAM) Rules. See <u>sk79700</u>.

Best Practice - The SAM Policy rules consume some CPU resources on Security Gateway. Set an expiration for rules that gives you time to investigate, but does not affect performance. Keep only the required SAM Policy rules. If you confirm that an activity is risky, edit the Security Policy, educate users, or otherwise handle the risk.

Syntax for IPv4

fw [-d] sam policy del '<Rule UID>'

Syntax for IPv6

fw6 [-d] sam policy del '<Rule UID>'

Parameter	Description
-d	 Runs the command in debug mode. Use only if you troubleshoot the command itself. Best Practice - If you use this parameter, then redirect the output to a file, or use the script command to save the entire CLI session.
' <rule uid="">'</rule>	Specifies the UID of the rule you wish to delete.
	 The quote marks and angle brackets ('<>') are mandatory. To see the Rule UID, run the "fw sam_policy get" on page 923 command.

Procedure

1. List all the existing rules in the Suspicious Activity Monitoring policy database

List all the existing rules in the Suspicious Activity Monitoring policy database.

For IPv4, run:

fw sam_policy get

For IPv6, run:

fw6 sam_policy get

The rules show in this format:

```
operation=add uid=<Value1, Value2, Value3, Value4> target=...
timeout=... action=... log= ... name= ... comment=...
originator= ... src_ip_addr=... req_tpe=...
```

Example for IPv4:

```
operation=add uid=<5ac3965f,00000000,3403a8c0,0000264a>
target=all timeout=300 action=notify log=log name=Test\ Rule
comment=Notify\ about\ traffic\ from\ 1.1.1.1
originator=John\ Doe src_ip_addr=1.1.1.1 req_tpe=ip
```

2. Delete a rule from the list by its UID

For IPv4, run:

```
fw [-d] sam policy del '<Rule UID>'
```

For IPv6, run:

fw6 [-d] sam policy del '<Rule UID>'

Example for IPv4:

fw samp del '<5ac3965f,00000000,3403a8c0,0000264a>'

3. Add the flush-only rule

For IPv4, run:

fw samp add -t 2 quota flush true

For IPv6, run:

fw6 samp add -t 2 quota flush true

Explanation:

The "fw samp del" and "fw6 samp del" commands only remove a rule from the persistent database. The Security Gateway continues to enforce the deleted rule until the next time you compiled and load a policy. To force the rule deletion immediately, you must enter a flush-only rule right after the "fw samp del" and "fw6 samp del" command. This flush-only rule immediately deletes the rule you specified in the previous step, and times out in 2 seconds.



Best Practice - Specify a short timeout period for the flush-only rules. This prevents accumulation of rules that are obsolete in the database.

fw sam_policy get

Description

The "fw sam_policy get" and "fw6 sam_policy get" commands:

- Show all the configured Suspicious Activity Monitoring (SAM) rules.
- Show all the configured Rate Limiting rules.

Notes:

- These commands are interchangeable:
 - For IPv4: "fw sam policy" and "fw samp".
 - For IPv6: "fw6 sam policy" and "fw6 samp".
- You can run these commands in Gaia Clish, or Expert mode.
- Security Gateway stores the SAM Policy rules in the \$FWDIR/database/sam policy.db file.
- Security Gateway stores the SAM Policy management settings in the \$FWDIR/database/sam policy.mng file.

Important:

- Configuration you make with these commands, survives reboot.
- You can run this command in the Expert mode or in Gaia Clish (Gaia gClish on Scalable Platforms).
- In a Cluster, you must configure all the Cluster Members in the same way.
- On Scalable Platforms (ElasticXL, Maestro, and Chassis), you must connect to the Gaia Portal of the applicable Security Group.
- VSNext mode and Traditional VSX mode do not support Suspicious Activity Monitoring (SAM) Rules. See <u>sk79700</u>.

Best Practice - The SAM Policy rules consume some CPU resources on Security Gateway. Set an expiration for rules that gives you time to investigate, but does not affect performance. Keep only the required SAM Policy rules. If you confirm that an activity is risky, edit the Security Policy, educate users, or otherwise handle the risk.

Syntax for IPv4

```
fw [-d] sam_policy get [-l] [-u '<Rule UID>'] [-k '<Key>' -t
<Type> [+{-v '<Value>'}] [-n]]
```

Syntax for IPv6

```
fw6 [-d] sam_policy get [-1] [-u '<Rule UID>'] [-k '<Key>' -t
<Type> [+{-v '<Value>'}] [-n]]
```

Parameters

Note - All these parameters are optional.

Parameter	Description
-d	 Runs the command in debug mode. Use only if you troubleshoot the command itself. Best Practice - If you use this parameter, then redirect the output to a file, or use the script command to save the entire CLI session.
-1	 Controls how to print the rules: In the default format (without "-1"), the output shows each rule on a separate line. In the list format (with "-1"), the output shows each parameter of a rule on a separate line. See "fw sam_policy add" on page 904.
-u ' <rule UID>'</rule 	Prints the rule specified by its Rule UID or its zero-based rule index. The quote marks and angle brackets ('<>') are mandatory.
-k '< <i>Key</i> >'	Prints the rules with the specified predicate key. The quote marks are mandatory.
-t <type></type>	Prints the rules with the specified predicate type. For Rate Limiting rules, you must always use "-t in".
+{-v ' <value>'}</value>	Prints the rules with the specified predicate values. The quote marks are mandatory.
-n	Negates the condition specified by these predicate parameters: -k -t +-v

Examples

Example 1 - Output in the default format

```
[Expert@HostName:0]# fw samp get
operation=add uid=<5ac3965f,00000000,3403a8c0,0000264a> target=all timeout=300 action=notify
log=log name=Test\ Rule comment=Notify\ about\ traffic\ from\ 1.1.1.1 originator=John\ Doe
src_ip_addr=1.1.1.1 req_tpe=ip
```

Example 2 - Output in the list format

```
[Expert@HostName:0] # fw samp get -1
uid
<5ac3965f,00000000,3403a8c0,0000264a>
target
all
timeout
2147483647
action
notify
log
log
name
Test\ Rule
comment
Notify\ about\ traffic\ from\ 1.1.1.1
originator
John\ Doe
src_ip_addr
1.1.1.1
req_type
ip
```

Example 3 - Printing a rule by its Rule UID

```
[Expert@HostName:0]# fw samp get -u '<5ac3965f,00000000,3403a8c0,0000264a>'
0
operation=add uid=<5ac3965f,00000000,3403a8c0,0000264a> target=all timeout=300 action=notify
log=log name=Test\ Rule comment=Notify\ about\ traffic\ from\ 1.1.1.1 originator=John\ Doe
src_ip_addr=1.1.1.1 req_tpe=ip
```

Example 4 - Printing rules that match the specified filters

```
[Expert@HostName:0]# fw samp get
no corresponding SAM policy requests
[Expert@HostName:0]#
[Expert@HostName:0]# fw samp add -a d -l r -t 3600 quota service any source
range:172.16.7.11-172.16.7.13 new-conn-rate 5 flush true
[Expert@HostName:0]#
[Expert@HostName:0]# fw samp add -a n -l r quota service 1,50-51,6/443,17/53 service-negated
true source cc:QQ byte-rate 0
[Expert@HostName:0]#
[Expert@HostName:0]# fw samp add -a b quota source range:172.16.8.17-172.16.9.121 service
6/80
[Expert@HostName:0]#
[Expert@HostName:0] # fw samp add -a d quota service any source-negated true source cc:QQ
concurrent-conns-ratio 655 track source
[Expert@HostName:0]#
[Expert@HostName:0] # fw samp get
operation=add uid=<5bab3acf,00000000,3503a8c0,00003ddc> target=all timeout=indefinite
action=drop service=any source-negated=true source=cc:QQ concurrent-conns-ratio=655
track=source req_type=quota
operation=add uid=<5bab3ac6,00000000,3503a8c0,00003dbf> target=all timeout=3586 action=drop
log=log service=any source=range:172.16.7.11-172.16.7.13 new-conn-rate=5 flush=true req
t.vpe=quot.a
operation=add uid=<5bab3acc,00000000,3503a8c0,00003dd7> target=all timeout=indefinite
action=bypass source=range:172.16.8.17-172.16.9.121 service=6/80 req type=quota
operation=add uid=<5bab3ac9,0000000,3503a8c0,00003dd5> target=all timeout=indefinite
action=notify log=log service=1,50-51,6/443,17/53 service-negated=true source=cc:QQ byte-
rate=0 req type=quota
[Expert@HostName:0]#
[Expert@HostName:0]# fw samp get -k 'service' -t in -v '6/80'
operation=add uid=<5bab3acc,0000000,3503a8c0,00003dd7> target=all timeout=indefinite
action=bypass source=range:172.16.8.17-172.16.9.121 service=6/80 req type=quota
[Expert@HostName:0]#
[Expert@HostName:0]# fw samp get -k 'service-negated' -t in -v 'true'
operation=add uid=<5bab3ac9,0000000,3503a8c0,00003dd5> target=all timeout=indefinite
action=notify log=log service=1,50-51,6/443,17/53 service-negated=true source=cc:QQ byte-
rate=0 req type=quota
[Expert@HostName:0]#
[Expert@HostName:0] # fw samp get -k 'source' -t in -v 'cc:QQ'
operation=add uid=<5bab3acf,00000000,3503a8c0,00003ddc> target=all timeout=indefinite
action=drop service=any source-negated=true source=cc:QQ concurrent-conns-ratio=655
track=source req_type=quota
operation=add uid=<5bab3ac9,0000000,3503a8c0,00003dd5> target=all timeout=indefinite
action=notify log=log service=1,50-51,6/443,17/53 service-negated=true source=cc:QQ byte-
rate=0 req_type=quota
[Expert@HostName:0]#
[Expert@HostName:0] # fw samp get -k source -t in -v 'cc:QQ' -n
operation=add uid=<5bab3ac6,0000000,3503a8c0,00003dbf> target=all timeout=3291 action=drop
log=log service=any source=range:172.16.7.11-172.16.7.13 new-conn-rate=5 flush=true req
type=quota
operation=add uid=<5bab3acc,00000000,3503a8c0,00003dd7> target=all timeout=indefinite
action=bypass source=range:172.16.8.17-172.16.9.121 service=6/80 reg type=quota
[Expert@HostName:0]#
[Expert@HostName:0] # fw samp get -k 'source-negated' -t in -v 'true'
operation=add uid=<5baa94e0,00000000,860318ac,000003016> target=all timeout=indefinite
action=drop service=any source-negated=true source=cc:QQ concurrent-conns-ratio=655
track=source req type=quota
[Expert@HostName:0]#
[Expert@HostName:0] # fw samp get -k 'byte-rate' -t in -v '0'
operation=add uid=<5baa9431,00000000,860318ac,00002efd> target=all timeout=indefinite
action=notify log=log service=1,50-51,6/443,17/53 service-negated=true source=cc:QQ byte-
rate=0 req type=quota
[Expert@HostName:0]#
[Expert@HostName:0] # fw samp get -k 'flush' -t in -v 'true'
operation=add uid=<5baa9422,00000000,860318ac,00002eea> target=all timeout=2841 action=drop
log=log service=any source=range:172.16.7.11-172.16.7.13 new-conn-rate=5 flush=true req
type=quota
[Expert@HostName:0]#
[Expert@HostName:0]# fw samp get -k 'concurrent-conns-ratio' -t in -v '655'
operation=add uid=<5baa94e0,00000000,860318ac,000003016> target=all timeout=indefinite
```

action=drop service=any source-negated=true source=cc:QQ concurrent-conns-ratio=655
track=source req_type=quota
[Expert@HostName:0]#

fwm

Description

Performs various management operations and shows various management information.

Notes:

- For debug instructions, see the description of the fwm process in sk97638.
- On a Multi-Domain Server, you must run these commands in the context of the applicable Domain Management Server.

Syntax



Parameter	Description
-d	 Runs the command in debug mode. Use only if you troubleshoot the command itself. Best Practice - If you use this parameter, then redirect the output to a file, or use the script command to save the entire CLI session.

Parameter	Description
dbload	Downloads the user database and network objects information to the specified targets
<options></options>	See "fwm dbload" on page 932.
exportcert	Export a SIC certificate of the specified object to file.
<options></options>	See "fwm exportcert" on page 933.
fetchfile	Fetches a specified OPSEC configuration file from the specified source computer.
<options></options>	See <i>"fwm fetchfile" on page 934</i> .
fingerprint	Shows the Check Point fingerprint.
<options></options>	See "fwm fingerprint" on page 936.
getpcap	Fetches the IPS packet capture data from the specified Security Gateway.
<options></options>	See "fwm getpcap" on page 938.
ikecrypt	Encrypts a secret with a key.
< <i>options</i> >	See <i>"fwm ikecrypt" on page 940</i> .
load < <i>options</i> >	This command is obsolete for R80 and higher. Use the "mgmt_cli" on page 985 command to load a policy to a managed Security Gateway. See "fwm load" on page 941.
logexport	Exports a Security log file (\$FWDIR/log/*.log) or Audit log file (\$FWDIR/log/*.adtlog) to an ASCII file.
<options></options>	See "fwm logexport" on page 942.
mds < <i>options</i> >	Shows information and performs various operations on Multi-Domain Server. See <i>"fwm mds" on page 947</i> .
printcert	Shows a SIC certificate's details.
<options></options>	See "fwm printcert" on page 949.
sic_reset	Resets SIC on the Management Server. See "fwm sic_reset" on page 955.
snmp_trap	Sends an SNMP Trap to the specified host.
<options></options>	See <i>"fwm snmp_trap" on page 956</i> .
unload	Unloads the policy from the specified managed Security Gateways.
< <i>options</i> >	See "fwm unload" on page 959.

Parameter	Description
ver <options></options>	Shows the Check Point version of the Management Server. See "fwm ver" on page 963.
verify <options></options>	This command is obsolete for R80 and higher. Use the "mgmt_cli" on page 985 command to verify a policy. See "fwm verify" on page 964.

fwm dbload

Description

Copies the user database and network objects information to specified managed servers with one or more **Management** Software Blades enabled.



fwm exportcert

Description

Export a SIC certificate of the specified managed object to a file.

Note:

On a Multi-Domain Server, you must run this command in the context of the applicable Domain Management Server:

mdsenv <IP Address or Name of Domain Management Server>

Syntax

```
fwm [-d] exportcert -obj <Name of Object> -cert <Name of CA> -file
<Output File> [-withroot] [-pem]
```

Parameter	Description
-d	 Runs the command in debug mode. Use only if you troubleshoot the command itself. Best Practice - If you use this parameter, then redirect the output to a file, or use the script command to save the entire CLI session. For complete debug instructions, see the description of the fwm process in sk97638.
<name of<br="">Object></name>	Specifies the name of the managed object, whose certificate you wish to export.
<name ca="" of=""></name>	Specifies the name of Certificate Authority, whose certificate you wish to export.
<output file=""></output>	Specifies the name of the output file.
-withroot	Exports the certificate's root in addition to the certificate's content.
-pem	Save the exported information in a text file. Default is to save in a binary file.

fwm fetchfile

Description

Fetches a specified OPSEC configuration file from the specified source computer.

This command supports only the fwopsec.conf or fwopsec.v4x files.

Note:

On a Multi-Domain Server, you must run this command in the context of the applicable Domain Management Server:

mdsenv <IP Address or Name of Domain Management Server>

Syntax

fwm [-d] fetchfile -r <File> [-d <Local Path>] <Source>

Parameter	Description
-d	 Runs the command in debug mode. Use only if you troubleshoot the command itself. Best Practice - If you use this parameter, then redirect the output to a file, or use the script command to save the entire CLI session.
-r <file></file>	Specifies the relative fw1 directory. This command supports only these files: conf/fwopsec.conf conf/fwopsec.v4x
-d <local Path></local 	Specifies the local directory to save the fetched file.
<source/>	 Specifies the managed remote source computer, from which to fetch the file. Note - The local and the remote source computers must have established SIC trust.

Example

```
[Expert@MGMT:0]# fwm fetchfile -r "conf/fwopsec.conf" -d /tmp 192.168.3.52
Fetching conf/fwopsec.conf from 192.168.3.52...
Done
[Expert@MGMT:0]#
```

fwm fingerprint

Description

Shows the Check Point fingerprint.

Note:

On a Multi-Domain Server, you must run this command in the context of the applicable Domain Management Server:

mdsenv <IP Address or Name of Domain Management Server>

Syntax

```
fwm [-d] fingerprint [-d]
      <IP address of Target> <SSL Port>
      localhost <SSL Port>
```

Parameter	Description
-d	 Runs the command in debug mode. Use only if you troubleshoot the command itself. Best Practice - If you use this parameter, then redirect the output to a file, or use the script command to save the entire CLI session. The debug options are: fwm -d Runs the complete debug of all fwm actions. For complete debug instructions, see the description of the fwm process in sk97638. fingerprint -d Runs the debug only for the fingerprint actions.
<ip address="" of<br="">Target></ip>	Specifies the IP address of a remote managed computer.
<ssl port=""></ssl>	Specifies the SSL port number. The default is 443.

Example 1 - Showing the fingerprint on the local Management Server

[Expert@MGMT:0]# fwm fingerprint localhost 443
#DN OID.1.2.840.113549.1.9.2=An optional company name,Email=Email
Address,CN=192.168.3.51,L=Locality Name (eg\, city)
#FINGER 11:A6:F7:1F:B9:F5:15:BC:F9:7B:5F:DC:28:FC:33:C5
##
[Expert@MGMT:0]#

Example 2 - Showing the fingerprint from a managed Security Gateway

```
[Expert@MGMT:0]# fwm fingerprint 192.168.3.52 443
#DN OID.1.2.840.113549.1.9.2=An optional company name,Email=Email
Address,CN=192.168.3.52,L=Locality Name (eg\, city)
#FINGER 5C:8E:4D:B9:B4:3A:58:F3:79:18:F1:70:99:8B:5F:2B
##
[Expert@MGMT:0]#
```

fwm getpcap

Description

Fetches the IPS packet capture data from the specified Security Gateway.

This command only works with IPS packet captures stored on the Security Gateway in the \$FWDIR/log/captures_repository/ directory.

This command does not work with other Software Blades, such as Anti-Bot and Anti-Virus that store packet captures in the *\$FWDIR/log/blob/* directory on the Security Gateway.

Note:

On a Multi-Domain Server, you must run this command in the context of the applicable Domain Management Server:

mdsenv <IP Address or Name of Domain Management Server>

Syntax

```
fwm [-d] getpcap -g <Security Gateway> -u '{<Capture UID>}' -p
<Local Path>
```

Parameter	Description
-d	 Runs the command in debug mode. Use only if you troubleshoot the command itself. Best Practice - If you use this parameter, then redirect the output to a file, or use the script command to save the entire CLI session. For complete debug instructions, see the description of the fwm process in sk97638.
-g <security Gateway></security 	Specifies the main IP address or Name of Security Gateway object as configured in SmartConsole.
-u ' { <capture UID>}'</capture 	Specifies the Unique ID of the packet capture file. To see the Unique ID of the packet capture file, open the applicable log file in SmartConsole > Logs & Events > Logs .
-p <local Path></local 	Specifies the local path to save the specified packet capture file. If you do not specify the local directory explicitly, the command saves the packet capture file in the current working directory.

Example

[Expert@MGMT:0]# fwm getpcap -g 192.168.162.1 -u '{0x4d79dc02,0x10000,0x220da8c0,0x1ffff}'
/var/log/
[Expert@MGMT:0]#

fwm ikecrypt

Description

Encrypts the password of an Endpoint VPN Client user using IKE. The resulting string must then be stored in the LDAP database.

Note:

On a Multi-Domain Server, you must run this command in the context of the applicable Domain Management Server:

mdsenv <IP Address or Name of Domain Management Server>

Syntax

fwm [-d] ikecrypt <Key> <Password>

Parameters

Parameter	Description
-d	 Runs the command in debug mode. Use only if you troubleshoot the command itself. Best Practice - If you use this parameter, then redirect the output to a file, or use the script command to save the entire CLI session. For complete debug instructions, see the description of the fwm process in sk97638.
<key></key>	Specifies the IKE Key as defined in the LDAP Account Unit properties window on the Encryption tab.
<password></password>	Specifies the password for the Endpoint VPN Client user.

```
[Expert@MGMT:0]# fwm ikecrypt MySecretKey MyPassword
OUQJHiNHCj6HJGH8ntnKQ7tg
[Expert@MGMT:0]#
```

fwm load

Description

Loads a policy on a managed Security Gateway.

 Important - This command is obsolete for R80 and higher.
 Use the API command "install-policy" to load a policy on a managed Security Gateway.
 See the <u>Check Point Management API Reference</u>.

fwm logexport

Description

Exports a Security log file (\$FWDIR/log/*.log) or Audit log file (\$FWDIR/log/*.adtlog) to an ASCII file.

Note:

On a Multi-Domain Server, you must run this command in the context of the applicable Domain Management Server:

mdsenv <IP Address or Name of Domain Management Server>

Syntax

```
fwm logexport -h
fwm [-d] logexport [{-d <Delimiter> | -s}] [-t <Table Delimiter>]
[-i <Input File>] [-o <Output File>] [{-f | -e}] [-x <Start Entry
Number>] [-y <End Entry Number>] [-z] [-n] [-p] [-a] [-u
<Unification Scheme File>] [-m {initial | semi | raw}]
```

Parameter	Description
-h	Shows the built-in usage.
-d	 Runs the command in debug mode. Use only if you troubleshoot the command itself. Best Practice - If you use this parameter, then redirect the output to a file, or use the script command to save the entire CLI session. For complete debug instructions, see the description of the fwm process in sk97638.
-d < <i>Delimiter></i> -s	 Specifies the output delimiter between fields of log entries: -d <delimiter> - Uses the specified delimiter.</delimiter> -s - Uses the ASCII character #255 (non-breaking space) as the delimiter. Note - If you do not specify the delimiter explicitly, the default is a semicolon (;).

Parameter	Description
-t <table Delimiter></table 	Specifies the output delimiter inside table field. Table field would look like: <i>ROWx:COL0,ROWx:COL1,ROWx:COL2</i> , and so on Note - If you do not specify the table delimiter explicitly, the default is a comma (,).
-i <input File></input 	Specifies the name of the input log file. Notes:
	 This command supports only Security log file (\$FWDIR/log/*.log) and Audit log file (\$FWDIR/log/*.adtlog) If you do not specify the input log file explicitly, the command processes the active Security log file \$FWDIR/log/fw.log
-o <output File></output 	Specifies the name of the output file. Note - If you do not specify the output log file explicitly, the command prints its output on the screen.
-f	After reaching the end of the currently opened log file, specifies to continue to monitor the log file indefinitely and export the new entries as well. Note - Applies only to the <i>active</i> log file: \$FWDIR/log/fw.log or \$FWDIR/log/fw.adtlog
-e	After reaching the end of the currently opened log file, continue to monitor the log file indefinitely and export the new entries as well. Note - Applies only to the <i>active</i> log file: \$FWDIR/log/fw.log or \$FWDIR/log/fw.adtlog
-x <start Entry Number></start 	Starts exporting the log entries from the specified log entry number and below, counting from the beginning of the log file.
-y <end Entry Number></end 	Starts exporting the log entries until the specified log entry number, counting from the beginning of the log file.
- z	In case of an error (for example, wrong field value), specifies to continue the export of log entries. The default behavior is to stop.
-n	Specifies not to perform DNS resolution of the IP addresses in the log file (this is the default behavior). This significantly speeds up the log processing.

Parameter	Description
-p	Specifies to not to perform resolution of the port numbers in the log file (this is the default behavior). This significantly speeds up the log processing.
-a	Exports only Account log entries.
-u <unification Scheme File></unification 	Specifies the path and name of the log unification scheme file. The default log unification scheme file is: <pre>\$FWDIR/conf/log_unification_scheme.C</pre>
-m {initial semi raw}	 Specifies the log unification mode: initial - Complete unification of log entries. The command exports one unified log entry for each ID. This is the default. If you also specify the "-f" parameter, then the output does not export any updates, but exports only entries that relate to the start of new connections. To export updates as well, use the "semi" parameter. semi - Step-by-step unification of log entries. For each log entry, exports entry that unifies this entry with all previously encountered entries with the same ID. raw - No log unification. Exports all log entries.

The output of the fwm logexport command appears in tabular format.

The first row lists the names of all log fields included in the log entries.

Each of the next rows consists of a single log entry, whose fields are sorted in the same order as the first row.

If a log entry has no information in a specific field, this field remains empty (as indicated by two successive semi-colons ";; ;").

You can control which log fields appear in the output of the command output:

Step	Instructions
1	Create the <pre>\$FWDIR/conf/logexport.ini file:</pre>
	[Expert@MGMT:0]# touch \$FWDIR/conf/logexport.ini
2	Edit the <pre>\$FWDIR/conf/logexport.ini file:</pre>
	[Expert@MGMT:0]# vi \$FWDIR/conf/logexport.ini
3	To include or exclude the log fields from the output, add these lines in the configuration file:
	[Fields_Info]
	<pre>included_fields = field1, field2, field3, <rest_of_ fields="">, field100</rest_of_></pre>
	excluded_fields = field10, field11
	Where:
	 You can specify only the included_fields parameter, only the excluded_fields parameter, or both.
	 The num field must always appear first. You cannot manipulate this field. The <rest_of_fields> is an optional reserved token that refers to a list of fields.</rest_of_fields>
	 If you specify the "-f" parameter, then the <rest_of_fields> is based on a list of fields from the \$FWDIR/conf/logexport_ default.C file.</rest_of_fields>
	 If you do not specify the "-f" parameter, then the <rest_of_fields> is based on the input log file.</rest_of_fields>
4	Save the changes in the file and exit the Vi editor.
5	Export the logs:
	<pre>fwm logexport <options></options></pre>

Example 1 - Exporting all log entries

```
[Expert@MGMT:0] # fwm logexport -i MySwitchedLog.log
Starting... There are 113 log records in the file
num;date;time;orig;type;action;alert;i/f name;i/f dir;product;LogId;ContextNum;origin
id;ContentVersion;HighLevelLogKey;SequenceNum;log sys message;ProductFamily;fg-1 client in rule
name; fg-1 client out rule name; fg-1 server in rule name; fg-1 server out rule
name;description;status;version;comment;update service;reason;Severity;failure impact
0;13Jun2018;19:47:54;CXL1_192.168.3.52;control; ;;daemon;inbound;VPN-1 & FireWall-1;-1;-
1;CN=CXL1 192.168.3.52,O=MyDomain Server.checkpoint.com.s6t98x;5;18446744073709551615;2;Log file
1;13Jun2018;19:47:54;CXL1_192.168.3.52;account;accept;;;inbound;FG;-1;-1;CN=CXL1_
192.168.3.52,O=MyDomain
Server.checkpoint.com.s6t98x;5;18446744073709551615;1;;Network;Default;Default;;;;;;;;;
. . . . . . .
35;13Jun2018;19:55:59;CXL1 192.168.3.52;account;accept;;;inbound;FG;-1;-1;CN=CXL1
192.168.3.52,O=MyDomain
Server.checkpoint.com.s6t98x;5;18446744073709551615;1;;Network;Default;Default;Host
Redirect;;;;;;;;;;
36;13Jun2018;19:56:06;CXL1 192.168.3.52;control; ;;;inbound;Security Gateway/Management;-1;-
1;CN=CXL1 192.168.3.52,O=MyDomain
Server.checkpoint.com.s6t98x;5;18446744073709551615;1;;Network;;;;;Contracts;Started;1.0;<null>
;1;;;
47;13Jun2018;19:57:02;CXL1 192.168.3.52;control; ;;;inbound;Security Gateway/Management;-1;-
1;CN=CXL1_192.168.3.52,O=MyDomain_
Server.checkpoint.com.s6t98x;5;18446744073709551615;1;;Network;;;;;;Contracts;Failed;1.0;;1;Could
not reach "https://productcoverage.checkpoint.com/ProductCoverageService". Check DNS and Proxy
configuration on the gateway.;2;Contracts may be out-of-date
. . . . . . .
[Expert@MGMT:0]#
```

Example 2 - Exporting only log entries with specified numbers

```
[Expert@MGMT:0] # fwm logexport -i MySwitchedLog.log -x 36 -y 47
Starting... There are 113 log records in the file
num;date;time;orig;type;action;alert;i/f name;i/f dir;product;LogId;ContextNum;origin
id;ContentVersion;HighLevelLogKey;SequenceNum;log_sys_message;ProductFamily;fg-1_client_in_rule_
name;fg-1 client out rule name;fg-1 server in rule name;fg-1 server out rule
name; description; status; version; comment; update service; reason; Severity; failure impact
36;13Jun2018;19:56:06;CXL1_192.168.3.52;control; ;;;inbound;Security Gateway/Management;-1;-
1;CN=CXL1 192.168.3.52,O=MyDomain
Server.checkpoint.com.s6t98x;5;18446744073709551615;1;;Network;;;;;Contracts;Started;1.0;<null>
;1;;;
37;13Jun2018;19:56:06;CXL1 192.168.3.52;account;accept;;;inbound;FG;-1;-1;CN=CXL1_
192.168.3.52,O=MyDomain
Server.checkpoint.com.s6t98x;5;18446744073709551615;2;;Network;Default;Default;Host
Redirect;;;;;;;;;;
. . . . . . .
46;13Jun2018;19:56:59;CXL1 192.168.3.52;account;accept;;;inbound;FG;-1;-1;CN=CXL1
192.168.3.52,O=MyDomain
Server.checkpoint.com.s6t98x;5;18446744073709551615;1;;Network;Default;Default;Host
Redirect;;;;;;;;;;;
47;13Jun2018;19:57:02;CXL1 192.168.3.52;control; ;;;inbound;Security Gateway/Management;-1;-
1;CN=CXL1 192.168.3.52,O=MyDomain
Server.checkpoint.com.s6t98x;5;18446744073709551615;1;;Network;;;;;;Contracts;Failed;1.0;;1;Could
not reach "https://productcoverage.checkpoint.com/ProductCoverageService". Check DNS and Proxy
configuration on the gateway.;2;Contracts may be out-of-date
[Expert@MGMT:0]#
```

fwm mds

Description

- Shows the Check Point version of the Multi-Domain Server.
- Rebuilds status tree for Global VPN Communities.

Note - On a Multi-Domain Server, you can run this command:

In the context of the MDS:

mdsenv

In the context of a Domain Management Server:

```
mdsenv <IP Address or Name of Domain
Management Server>
```

Syntax

```
fwm [-d] mds
    ver
    rebuild_global_communities_status {all | missing}
```

Parameter	Description
-d	 Runs the command in debug mode. Use only if you troubleshoot the command itself. Best Practice - If you use this parameter, then redirect the output to a file, or use the script command to save the entire CLI session. For complete debug instructions, see the description of the fwm process in sk97638.
ver	Shows the Check Point version of the Multi-Domain Server.
rebuild_global_ communities_status	 Rebuilds status tree for Global VPN Communities: all - Rebuilds status tree for all Global VPN Communities. missing - Rebuild status tree only for Global VPN Communities that do not have status trees.

```
[Expert@MDS:0]# fwm mds ver
This is Check Point Multi-Domain Security Management R82 - Build
11
[Expert@MDS:0]#
```

fwm printcert

Description

Shows a SIC certificate's details.

Note:

On a Multi-Domain Server, you must run this command in the context of the applicable Domain Management Server:

mdsenv <IP Address or Name of Domain Management Server>

Syntax

```
fwm [-d] printcert
    -obj <Name of Object> [-cert <Certificate Nick Name>] [-
verbose]
    -ca <CA Name> [-x509 <Name of File> [-p]] [-verbose]
    -f <Name of Binary Certificate File> [-verbose]
```

Item	Description
-d	 Runs the command in debug mode. Use only if you troubleshoot the command itself. Best Practice - If you use this parameter, then redirect the output to a file, or use the script command to save the entire CLI session. For complete debug instructions, see the description of the fwm process in sk97638.
-obj <name object="" of=""></name>	Specifies the name of the managed object, for which to show the SIC certificate information.
-cert < <i>Certificate</i> Nick Name>	Specifies the certificate nick name.
-ca < <i>CA Name</i> >	Specifies the name of the Certificate Authority. Note - Check Point CA Name is internal_ca.
-x509 <name file="" of=""></name>	Specifies the name of the X.509 file.
-р	Specifies to show the SIC certificate as a text file.
-f <name binary<br="" of="">Certificate File></name>	Specifies the binary SIC certificate file to show.
-verbose	Shows the information in verbose mode.

Examples

Example 1 - Showing the SIC certificate of a Management Server

```
[Expert@MGMT:0] # fwm printcert -ca internal ca
Subject: O=MGMT.checkpoint.com.s6t98x
Issuer: O=MGMT.checkpoint.com.s6t98x
Not Valid Before: Sun Apr 8 13:41:00 2018 Local Time
Not Valid After: Fri Jan 1 05:14:07 2038 Local Time
Serial No.: 1
Public Key: RSA (2048 bits)
Signature: RSA with SHA256
Key Usage:
       digitalSignature
        keyCertSign
       cRLSign
Basic Constraint:
       is CA
MD5 Fingerprint:
   7B:F9:7B:4C:BD:40:B9:1C:AB:2C:AE:CF:66:2E:E7:06
SHA-1 Fingerprints:
1. A6:43:3A:2B:1A:04:7F:A6:36:A6:2C:78:BF:22:D9:BC:F7:7E:4D:73
2. KEYS HEM GERM PIT ABUT ROVE RAW PA IQ FAWN NUT SLAM
[Expert@MGMT:0]#
```

Example 2 - Showing the SIC certificate of a Management Server in verbose mode

[Expert@MGMT:0]# fwm printcert -ca internal_ca -verbose [FWM 24304 4024166304]@MGMT[12 Jun 20:21:52] fwa db init: called [FWM 24304 4024166304]@MGMT[12 Jun 20:21:52] fwa db init: closing existing database [FWM 24304 4024166304]@MGMT[12 Jun 20:21:52] do links getver: strncmp failed. Returning -2 [FWM 24304 4024166304]@MGMT[12 Jun 20:21:52] db fetchkey: entering [FWM 24304 4024166304]@MGMT[12 Jun 20:21:52] PubKey: [FWM 24304 4024166304]@MGMT[12 Jun 20:21:52] Modulus: [FWM 24304 4024166304]@MGMT[12 Jun 20:21:52] ae b3 75 36 64 e4 1a 40 fe c2 ad 2f 9b 83 0b 45 f1 00 04 bc [FWM 24304 4024166304]@MGMT[12 Jun 20:21:52] 3f 77 77 76 dl de 8a cf 9f 32 78 8b d4 bl b4 be db 75 cc c8 [FWM 24304 4024166304]@MGMT[12 Jun 20:21:52] c2 6d ff 3e aa fe f1 2b c3 0a b0 a2 a5 e0 a8 ab 45 cd 87 32 [FWM 24304 4024166304]@MGMT[12 Jun 20:21:52] ac c6 9f a4 a9 ba 30 79 08 fa 59 4c d2 dc 3d 36 ca 17 d7 c1 [FWM 24304 4024166304]@MGMT[12 Jun 20:21:52] b2 a2 41 f5 89 0f 00 d4 2d f2 55 d2 30 a5 32 c7 46 7a 6b 32 [FWM 24304 4024166304]@MGMT[12 Jun 20:21:52] 29 0f 53 9f 35 42 91 e5 7d f7 30 6d bc b3 f2 ae f3 f0 ed 88 [FWM 24304 4024166304]@MGMT[12 Jun 20:21:52] c4 d7 7d 0c 2d f6 5f c8 ed 9f 9a 57 54 79 d0 0f 0b 2f 9c 0d [FWM 24304 4024166304]@MGMT[12 Jun 20:21:52] 94 2e f0 f4 66 62 f7 ae 2e f8 8e 90 08 ba 63 85 b6 46 2f b7 [FWM 24304 4024166304]@MGMT[12 Jun 20:21:52] a7 01 29 9a 14 58 a8 ef eb 07 17 4e 95 8b 2f 48 5f d3 18 10 [FWM 24304 4024166304]@MGMT[12 Jun 20:21:52] 3f 00 d5 03 d7 fd 45 45 ca 67 5b 34 be b8 00 ae ea 9a cd 50 [FWM 24304 4024166304]@MGMT[12 Jun 20:21:52] d6 e7 a2 81 86 78 11 d7 bf 04 9f 8b 43 3f f7 36 5f ed 31 a8 [FWM 24304 4024166304]@MGMT[12 Jun 20:21:52] a3 9d 8b 0a de 05 fb 5c 44 2e 29 e3 3e f4 dd 50 01 Of 86 9d [FWM 24304 4024166304]@MGMT[12 Jun 20:21:52] 55 16 a3 4d f8 90 2d 13 c6 c1 28 57 f8 3e 7c 59 [FWM 24304 4024166304]@MGMT[12 Jun 20:21:52] Exponent: 65537 (0x10001) [FWM 24304 4024166304]@MGMT[12 Jun 20:21:52] X509 Certificate Version 3 refCount: 1 Serial Number: 1 Issuer: O=MGMT.checkpoint.com.s6t98x Subject: O=MGMT.checkpoint.com.s6t98x Not valid before: Sun Apr 8 13:41:00 2018 Local Time Not valid after: Fri Jan 1 05:14:07 2038 Local Time Signature Algorithm: RSA with SHA-256 Public key: RSA (2048 bits) Extensions: Key Usage: digitalSignature keyCertSign cRLSign Basic Constraint (Critical): is CA [FWM 24304 4024166304]@MGMT[12 Jun 20:21:52] destroy rand mutex: destroy [FWM 24304 4024166304]@MGMT[12 Jun 20:21:52] cpKeyTaskManager::~cpKeyTaskManager: called. [Expert@MGMT:0]#

Example 3 - Showing the SIC certificate of a managed Cluster object

```
[Expert@MGMT:0] # fwm printcert -obj CXL_192.168.3.244
printing all certificates of CXL_192.168.3.244
defaultCert:
Host Certificate (level 0):
Subject: CN=CXL 192.168.3.244 VPN Certificate,O=MGMT.checkpoint.com.s6t98x
Issuer: O=MGMT.checkpoint.com.s6t98x
Not Valid Before: Sun Jun 3 19:58:19 2018 Local Time
Not Valid After: Sat Jun 3 19:58:19 2023 Local Time
Serial No.: 85021
Public Key: RSA (2048 bits)
Signature: RSA with SHA256
Subject Alternate Names:
       IP Address: 192.168.3.244
CRL distribution points:
       http://192.168.3.240:18264/ICA CRL2.crl
       CN=ICA_CRL2,O=MGMT.checkpoint.com.s6t98x
Key Usage:
       digitalSignature
        keyEncipherment
Basic Constraint:
       not CA
MD5 Fingerprint:
  B1:15:C7:A8:2A:EE:D1:75:92:9F:C7:B4:B9:BE:42:1B
SHA-1 Fingerprints:
1. BC:7A:D9:E2:CD:29:D1:9E:F0:39:5A:CD:7E:A9:0B:F9:6A:A7:2B:85
2. MIRE SANK DUSK HOOD HURD RIDE TROY QUAD LOVE WOOD GRIT WITH
                ****
[Expert@MGMT:0]#
```

Example 4 - Showing the SIC certificate of a managed Cluster object in verbose mode

[Expert@MGMT:0]# fwm printcert -obj CXL_192.168.3.244 -verbose [FWM 24665 4023814048]@MGMT[12 Jun 20:26:45] fwa db init: called [FWM 24665 4023814048]@MGMT[12 Jun 20:26:45] fwa db init: closing existing database [FWM 24665 4023814048]@MGMT[12 Jun 20:26:45] do links getver: strncmp failed. Returning -2 printing all certificates of CXL 192.168.3.244 [FWM 24665 4023814048]@MGMT[12 Jun 20:26:45] db_fetchkey: entering [FWM 24665 4023814048]@MGMT[12 Jun 20:26:45] 1 certificates [FWM 24665 4023814048]@MGMT[12 Jun 20:26:45] PubKey: [FWM 24665 4023814048]@MGMT[12 Jun 20:26:45] Modulus: [FWM 24665 4023814048]@MGMT[12 Jun 20:26:45] df 35 c3 45 ca 42 16 6e 21 9e 31 af c1 fd 20 0a 3d 5b 6f 5d [FWM 24665 4023814048]@MGMT[12 Jun 20:26:45] e0 a2 0c 0e fa fa 5e e5 91 9d 4e 73 77 fa db 86 0b 5e 5d 0c [FWM 24665 4023814048]@MGMT[12 Jun 20:26:45] ce af 4a a4 7b 30 ed b0 43 7d d8 93 c5 4b 01 f4 3d b5 d8 f4 [FWM 24665 4023814048]@MGMT[12 Jun 20:26:45] 34 b1 db ac 18 4f 11 bd d2 fb 26 7d 23 74 5c d9 00 al 58 le [FWM 24665 4023814048]@MGMT[12 Jun 20:26:45] 60 7c 83 44 fa 1e 1e 86 fa ad 98 f7 df 24 4a 21 [FWM 24665 4023814048]@MGMT[12 Jun 20:26:45] Exponent: 65537 (0x10001) [FWM 24665 4023814048]@MGMT[12 Jun 20:26:45] X509 Certificate Version 3 refCount: 1 Serial Number: 85021 Issuer: O=MGMT.checkpoint.com.s6t98x Subject: CN=CXL 192.168.3.244 VPN Certificate, O=MGMT.checkpoint.com.s6t98x Not valid before: Sun Jun 3 19:58:19 2018 Local Time Not valid after: Sat Jun 3 19:58:19 2023 Local Time Signature Algorithm: RSA with SHA-256 Public key: RSA (2048 bits) Extensions: Key Usage: digitalSignature keyEncipherment Subject Alternate names: IP: 192.168.3.244 Basic Constraint: not CA CRL distribution Points: URI: http://192.168.3.240:18264/ICA CRL2.crl DN: CN=ICA CRL2, O=MGMT.checkpoint.com.s6t98x defaultCert: [FWM 24665 4023814048]@MGMT[12 Jun 20:26:45] destroy rand mutex: destroy [FWM 24665 4023814048]@MGMT[12 Jun 20:26:45] cpKeyTaskManager::~cpKeyTaskManager: called. * * * * * [Expert@MGMT:0]#

fwm sic_reset

Description

Resets SIC on the Management Server.

For detailed procedure, see sk65764: How to reset SIC.

Warning:

 Before you run this command, take a Gaia Snapshot and a full backup of the Management Server.

This command resets SIC between the Management Server and all its managed objects.

 This operation breaks trust in all Internal CA certificates and SIC trust across the managed environment.

Therefore, we do not recommend it at all, except for real disaster recovery.

Note

On a Multi-Domain Server, you must run this command in the context of the applicable Domain Management Server:

mdsenv <IP Address or Name of Domain Management Server>

Syntax

fwm [-d] sic_reset

Parameter	Description
-d	 Runs the command in debug mode. Use only if you troubleshoot the command itself. Best Practice - If you use this parameter, then redirect the output to a file, or use the script command to save the entire CLI session. For complete debug instructions, see the description of the fwm process in sk97638.

fwm snmp_trap

Description

Sends an SNMPv1 Trap to the specified host.

Notes:

On a Multi-Domain Server, you must run this command in the context of the applicable Domain Management Server:

mdsenv <IP Address or Name of Domain Management Server>

 On a Multi-Domain Server, the SNMP Trap packet is sent from the IP address of the Leading Interface.

Syntax

```
fwm [-d] snmp_trap [-v <SNMP OID>] [-g <Generic Trap Number>] [-s
<Specific Trap Number>] [-p <Source Port>] [-c <SNMP Community>]
<Target> ["<Message>"]
```

Parameter	Description
-d	 Runs the command in debug mode. Use only if you troubleshoot the command itself. Best Practice - If you use this parameter, then redirect the output to a file, or use the script command to save the entire CLI session. For complete debug instructions, see the description of the fwm process in sk97638.
-v < <i>SNMP OID</i> >	Specifies an optional SNMP OID to bind with the message.
-g <generic trap<br="">Number></generic>	Specifies the generic trap number. One of these values:
	 0-For coldStart trap 1-For warmStart trap 2-For linkDown trap 3-For linkUp trap 4-For authenticationFailure trap 5-For egpNeighborLoss trap 6-For enterpriseSpecific trap (this is the default value)
-s <specific trap<br="">Number></specific>	Specifies the unique trap type. Valid only of generic trap value is 6 (for enterpriseSpecific). Default value is 0.
-p < <i>Source Port</i> >	Specifies the source port, from which to send the SNMP Trap packets.
-c <snmp Community></snmp 	Specifies the SNMP community.
<target></target>	Specifies the managed target host, to which to send the SNMP Trap packets. Enter an IP address of a resolvable hostname.
" <message>"</message>	Specifies the SNMP Trap text message.

Example - Sending an SNMP Trap from a Management Server and capturing the traffic on the Security Gateway

[Expert@MGMT:0] # fwm snmp_trap -g 2 -c public 192.168.3.52 "My Trap Message" [Expert@MGMT:0] # [Expert@MgGW_192.168.3.52:0] # tcpdump -s 1500 -vvvv -i eth0 udp and host 192.168.3.51 tcpdump: listening on eth0, link-type EN10MB (Ethernet), capture size 1500 bytes 22:49:43.891287 IP (tos 0x0, ttl 64, id 0, offset 0, flags [DF], proto: UDP (17), length: 103) 192.168.3.51.53450 > MyGW_192.168.3.52.snmptrap: [udp sum ok] { SNMPv1 { Trap(58) E:2620.1.1 192.168.3.240 linkDown 1486440 E:2620.1.1.11.0="My Trap Message" } } Pressed CTRL+C [Expert@MyGW_192.168.3.52:0] #

fwm unload

Description

Unloads the policy from the specified managed Security Gateways or Cluster Members.

O Warning:

- 1. The fwm unload command prevents all traffic from passing through the Security Gateway (Cluster Member), because it disables the IP Forwarding in the Linux kernel on the specified Security Gateway (Cluster Member).
- The fwm unload command removes all policies from the specified Security Gateway (Cluster Member).
 This means that the Security Gateway (Cluster Member) accepts all incoming connections destined to all active interfaces without any filtering or protection enabled.

Notes:

 On a Multi-Domain Server, you must run this command in the context of the applicable Domain Management Server:

mdsenv <IP Address or Name of Domain Management Server>

- If it is necessary to remove the current policy, but keep the Security Gateway (Cluster Member) protected, then run the "comp_init_policy" command on the Security Gateway (Cluster Member).
- To load the policies on the Security Gateway (Cluster Member), run one of these commands on the Security Gateway (Cluster Member), or reboot:
 - "fw fetch"
 - "cpstart"

Syntax

fwm [-d] unload <GW1> <GW2> ... <GWN>

Parameter	Description
-d	 Runs the command in debug mode. Use only if you troubleshoot the command itself. Best Practice - If you use this parameter, then redirect the output to a file, or use the script command to save the entire CLI session. For complete debug instructions, see the description of the fwm process in sk97638.
<gw1> <gw2> <gwn></gwn></gw2></gw1>	Specifies the managed Security Gateways by their main IP address or Object Name as configured in SmartConsole.

```
[Expert@MyGW:0] # cpstat -f policy fw
Product name: Firewall
Policy name: CXL Policy
Policy install time: Wed Oct 23 18:23:14 2019
. . . . . . . . . .
[Expert@MyGW:0]#
[Expert@MyGW:0] # sysctl -a | grep forwarding | grep -v bridge
net.ipv6.conf.bond0.forwarding = 1
net.ipv6.conf.eth1.forwarding = 1
net.ipv6.conf.eth3.forwarding = 1
net.ipv6.conf.eth2.forwarding = 1
net.ipv6.conf.eth4.forwarding = 1
net.ipv6.conf.eth5.forwarding = 1
net.ipv6.conf.eth0.forwarding = 1
net.ipv6.conf.eth6.forwarding = 1
net.ipv6.conf.default.forwarding = 1
net.ipv6.conf.all.forwarding = 1
net.ipv6.conf.lo.forwarding = 1
net.ipv4.conf.bond0.mc forwarding = 0
net.ipv4.conf.bond0.forwarding = 1
net.ipv4.conf.eth1.mc forwarding = 0
net.ipv4.conf.eth1.forwarding = 1
net.ipv4.conf.eth2.mc_forwarding = 0
net.ipv4.conf.eth2.forwarding = 1
net.ipv4.conf.eth0.mc forwarding = 0
net.ipv4.conf.eth0.forwarding = 1
net.ipv4.conf.lo.mc forwarding = 0
net.ipv4.conf.lo.forwarding = 1
net.ipv4.conf.default.mc forwarding = 0
net.ipv4.conf.default.forwarding = 1
net.ipv4.conf.all.mc forwarding = 0
net.ipv4.conf.all.forwarding = 1
[Expert@MyGW:0]#
[Expert@MGMT:0] # fwm unload MyGW
Uninstalling Policy From: MyGW
 Security Policy successfully uninstalled from MyGW...
Security Policy uninstall complete.
[Expert@MGMT:0]#
```

```
[Expert@MyGW:0] # cpstat -f policy fw
Product name: Firewall
Policy name:
Policy install time:
. . . . . . . . . .
[Expert@MyGW:0]#
[Expert@MyGW:0] # sysctl -a | grep forwarding | grep -v bridge
net.ipv6.conf.bond0.forwarding = 0
net.ipv6.conf.eth1.forwarding = 0
net.ipv6.conf.eth3.forwarding = 0
net.ipv6.conf.eth2.forwarding = 0
net.ipv6.conf.eth4.forwarding = 0
net.ipv6.conf.eth5.forwarding = 0
net.ipv6.conf.eth0.forwarding = 0
net.ipv6.conf.eth6.forwarding = 0
net.ipv6.conf.default.forwarding = 0
net.ipv6.conf.all.forwarding = 0
net.ipv6.conf.lo.forwarding = 0
net.ipv4.conf.bond0.mc forwarding = 0
net.ipv4.conf.bond0.forwarding = 0
net.ipv4.conf.eth1.mc forwarding = 0
net.ipv4.conf.eth1.forwarding = 0
net.ipv4.conf.eth2.mc forwarding = 0
net.ipv4.conf.eth2.forwarding = 0
net.ipv4.conf.eth0.mc forwarding = 0
net.ipv4.conf.eth0.forwarding = 0
net.ipv4.conf.lo.mc forwarding = 0
net.ipv4.conf.lo.forwarding = 0
net.ipv4.conf.default.mc forwarding = 0
net.ipv4.conf.default.forwarding = 0
net.ipv4.conf.all.mc_forwarding = 0
net.ipv4.conf.all.forwarding = 0
[Expert@MyGW:0]#
```

fwm ver

Description

Shows the Check Point version of the Security Management Server.

Note - On a Multi-Domain Server, you can run this command:

In the context of the MDS:

mdsenv

In the context of a Domain Management Server:

```
mdsenv <IP Address or Name of Domain
Management Server>
```

Syntax

```
fwm [-d] ver [-f <Output File>]
```

Parameters

Parameter	Description
-d	 Runs the command in debug mode. Use only if you troubleshoot the command itself. Best Practice - If you use this parameter, then redirect the output to a file, or use the script command to save the entire CLI session. For complete debug instructions, see the description of the fwm process in sk97638.
-f <output File></output 	Specifies the name of the output file, in which to save this information.

```
[Expert@MGMT:0]# fwm ver
This is Check Point Security Management Server R82 - Build 11
[Expert@MGMT:0]#
```

fwm verify

Important - This command is obsolete for R80 and higher. Use the "mgmt_cli" on page 985 command to verify a policy on a managed Security Gateway.

Description

Verifies the specified policy package without installing it.

Note

On a Multi-Domain Server, you must run this command in the context of the applicable Domain Management Server:

mdsenv <IP Address or Name of Domain Management Server>

Syntax

fwm [-d] verify <Policy Name>

Parameters

Parameter	Description
-d	 Runs the command in debug mode. Use only if you troubleshoot the command itself. Sest Practice - If you use this parameter, then redirect the output to a file, or use the script command to save the entire CLI session. For complete debug instructions, see the description of the fwm process in sk97638.
<policy Name></policy 	Specifies the name of the policy package as configured in SmartConsole.

```
[Expert@MGMT:0]# fwm verify Standard
Verifier messages:
Error: Rule 1 Hides rule 2 for Services & Applications: any .
[Expert@MGMT:0]#
```

inet_alert

Description

Notifies an Internet Service Provider (ISP) when a company's corporate network is under attack. This command forwards log messages generated by the alert daemon on your Check Point Security Gateway to an external Management Station. This external Management Station is usually located at the ISP site. The ISP can then analyze the alert and react accordingly.

This command uses the Event Logging API (ELA) protocol to send the alerts. The Management Station receiving the alert must be running the ELA Proxy.

If communication with the ELA Proxy is to be authenticated or encrypted, a key exchange must be performed between the external Management Station running the ELA Proxy at the ISP site and the Check Point Security Gateway generating the alert.

Procedure

Step	Instructions
1	Connect with SmartConsole to the applicable Security Management Server or Domain Management Server, which manages the applicable Security Gateway that should forward log messages to an external Management Station.
2	From the top left Menu, click Global properties.
3	Click on the [+] near the Log and Alert and click Alerts.
4	Clear the Send user defined alert no. 1 to SmartView Monitor.
5	Select the next option Run UserDefined script under the above.
6	Enter the applicable inet_alert syntax (see the <i>Syntax</i> section below).
7	Click OK .
8	Install the Access Control Policy on the applicable Security Gateway.

Syntax

```
inet_alert -s <IP Address> [-0] [-a <Auth Type>] [-p <Port>] [-f
<Token> <Value>] [-m <Alert Type>]
```

Notes:

- You can run this command only in the Expert mode.
- On a Multi-Domain Server, you must run this command in the context of the applicable Domain Management Server:

mdsenv <IP Address or Name of Domain Management Server>

Parameter	Description	
-s <ip Address></ip 	The IPv4 address of the ELA Proxy (usually located at the ISP site).	
-0	<pre>Prints the alert log received to stdout. Use this option when inet_alert is part of a pipe syntax (<some command=""> inet_alert).</some></pre>	
-a <auth Type></auth 	Specifies the type of connection to the ELA Proxy. One of these values:	
	 ssl_opsec - The connection is authenticated and encrypted (this is the default). auth_opsec - The connection is authenticated. clear - The connection is neither authenticated, nor encrypted. 	
-p < <i>Port</i> >	Specifies the port number on the ELA proxy. Default port is 18187.	
-f <token> <value></value></token>	A field to be added to the log, represented by a <token> <value> pair as follows:</value></token>	
	 <token> - The name of the field to be added to the log. Cannot contain spaces.</token> <value> - The field's value. Cannot contain spaces.</value> 	
	This option can be used multiple times to add multiple <token> <value> pairs to the log.</value></token>	

Parameter	Description
-m <alert Type></alert 	The alert to be triggered at the ISP site. This alert overrides the alert specified in the log message generated by the alert daemon. The response to the alert is handled according to the actions specified in the ISP Security Policy: These alerts execute the OS commands: alert - Popup alert command mail - Mail alert command snmptrap - SNMP trap alert command spoofalert - Anti-Spoof alert command
	These NetQuota and ServerQuota alerts execute the OS commands specified in the <code>\$FWDIR/conf/objects.C: file:</code> value=clientquotaalert. Parameter=clientquotaalertcmd

Exist Status

Exit Status	Description
0	Execution was successful.
102	Undetermined error.
103	Unable to allocate memory.
104	Unable to obtain log information from stdin
106	Invalid command line arguments.
107	Failed to invoke the OPSEC API.

Example

inet_alert -s 10.0.2.4 -a clear -f product cads -m alert

This command specifies to perform these actions in the event of an attack:

- Establish a clear connection with the ELA Proxy located at IP address 10.0.2.4
- Send a log message to the specified ELA Proxy. Set the product field of this log message to cads
- Trigger the OS command specified in the SmartConsole > Menu > Global properties > Log and Alert > Popup Alert Command field.

Idapcmd

Description

This is an LDAP utility that controls these features:

Feature	Description
Cache	LDAP cache operations, such as emptying the cache, as well as providing debug information.
Statistics	LDAP search statistics, such as: All user searches Pending lookups (when two or more lookups are identical) Total lookup time (the total search time for a specific lookup) Cache statistics such as hits and misses These statistics are saved in the \$FWDIR/log/ldap_pid_ <process PID>.stats file.</process
Logging	View the alert and warning logs.
 Notes: You can run this command only in the Expert mode. On a Multi-Domain Server, you must run this command in the context of the applicable Domain Management Server: 	

mdsenv <IP Address or Name of Domain Management Server>

Syntax

ldapcmd [-d <Debug Level>] -p {<Process Name> | all} <Command>

Parameter	Description
-d <debug Level></debug 	Runs the command in debug mode with the specified TDERROR debug level. Valid values are from 0 (disabled) to 5 (maximum level, recommended).
-p {< <i>Process</i> <i>Name</i> > all}	Runs on a specified Check Point process, or all supported Check Point processes.
<command/>	<pre>One of these commands: cacheclear {all UserCacheObject TemplateCacheObject TemplateExtGrpCacheObject} all - Clears cache for all objects UserCacheObject - Clears cache for user objects TemplateCacheObject - Clears cache for template objects TemplateExtGrpCacheObject - Clears cache for external template group objects cachetrace {all UserCacheObject TemplateExtGrpCacheObject TemplateExtGrpCacheObject TemplateExtGrpCacheObject TemplateExtGrpCacheObject TemplateExtGrpCacheObject TemplateExtGrpCacheObject - Traces cache for user objects userCacheObject - Traces cache for template objects UserCacheObject - Traces cache for template objects TemplateExtGrpCacheObject - Traces cache for external template group objects TemplateExtGrpCacheObject - Traces cache for external template group objects TemplateExtGrpCacheObject - Traces cache for external template group objects TemplateExtGrpCacheObject - Traces cache for external template group objects Stat {<print in="" interval="" sec=""> 0} </print></pre>

Idapcompare

Description

This is an LDAP utility that performs compare queries and prints a message whether the result returned a match or not.

This utility opens a connection to an LDAP directory server, binds, and performs the comparison specified on the command line or from a specified file.

Notes:

- You can run this command only in the Expert mode.
- On a Multi-Domain Server, you must run this command in the context of the applicable Domain Management Server:

mdsenv <IP Address or Name of Domain Management Server>

Syntax

```
ldapcompare [-d <Debug Level>] [<Options>] <DN> {<Attribute>
<Value> | <Attribute> <Base64 Value>}
```

Parameter	Description
-d <i><debug< i=""> Level></debug<></i>	Runs the command in debug mode with the specified TDERROR debug level. Valid values are from 0 (disabled) to 5 (maximum level, recommended).
<options></options>	See the tables below: Compare options Common options
< <i>DN</i> >	Specifies the Distinguished Name.
<attribute></attribute>	Specifies the assertion attribute.
<value></value>	Specifies the assertion value.
<base64 value=""></base64>	Specifies the Base64 encoding of the assertion value.

Compare options

Option	Description
-E [!] <extension> [=<extension parameter="">]</extension></extension>	Specifies the compare extensions. Note - The exclamation sign "!" indicates criticality. For example: !dontUseCopy = Do not use Copy
-M	Enables the Manage DSA IT control. Use the "-MM" option to make it critical.
-P <ldap protocol="" version=""></ldap>	Specifies the LDAP protocol version. Default version is 3.
- z	Enables the quiet mode. The command does not print anything. You can use the command return values.

Common options

Option	Description
-D <bind dn=""></bind>	Specifies the LDAP Server administrator Distinguished Name.

Idapcompare

Option	Description
-e [!] <extension> [=<extension parameter="">]</extension></extension>	Specifies the general extensions: Note - The exclamation sign "!" indicates criticality.
	<pre>[!]assert=<filter> RFC 4528; an RFC 4515 filter string [!]authzid=<authorization id=""> RFC 4370; either "dn:<dn>", or "u:<username>" [!]chaining[=<resolve behavior=""> [/<continuation behavior="">]] One of these: "chainingRequired" "referralsPreferred" "referralsRequired" "referralsRequired" "!]manageDSAit RFC 3296 [!]noop ppolicy [!]postread[=<attributes>] RFC 4527; a comma-separated list of attributes [!]preread[=<attributes>] RFC 4527; a comma-separated list of attributes [!]relax abandon SIGINT sends the abandon signal; if critical, does not wait for SIGINT. Not really controls. ignore SIGINT ignores the response; if critical, does not wait for SIGINT. Not really controls.</attributes></attributes></continuation></resolve></username></dn></authorization></filter></pre>
-h < <i>LDAP Server</i> >	Specifies the LDAP Server computer by its IP address or resolvable hostname.
-H <ldap uri=""></ldap>	Specifies the LDAP Server Uniform Resource Identifier (s).
-I	Specifies to use the SASL Interactive mode.
-n	Dry run - shows what would be done, but does not actually do it.

Idapcompare

Option	Description
-N	Specifies not to use the reverse DNS to canonicalize SASL host name.
-o <option>[=<option Parameter>]</option </option>	<pre>Specifies the general options: nettimeout={<timeout in="" sec=""> none max}</timeout></pre>
-0 <properties></properties>	Specifies the SASL security properties.
-p <ldap port="" server=""></ldap>	Specifies the LDAP Server port. Default is 389.
-Q	Specifies to use the SASL Quiet mode.
-R < <i>Realm</i> >	Specifies the SASL realm.
-U <authentication Identity></authentication 	Specifies the SASL authentication identity.
- A	Runs in verbose mode (prints the diagnostics to <i>stdout</i>).
-V	Prints version information (use the " $-\nabla\nabla$ " option only).
-w <ldap admin="" password=""></ldap>	Specifies the LDAP Server administrator password (for simple authentication).
-W	Specifies to prompt the user for the LDAP Server administrator password.
-x	Specifies to use simple authentication.
-X <authorization Identity></authorization 	Specifies the SASL authorization identity (either "dn: <dn>", or "u:<username>" option).</username></dn>
-y <file></file>	Specifies to read the LDAP Server administrator password from the <file>.</file>
-Y <sasl mechanism=""></sasl>	Specifies the SASL mechanism.
-Z	Specifies to start the TLS request. Use the " $-ZZ$ " option to require successful response.

Idapmemberconvert

Description

This is an LDAP utility that ports from the "Member" attribute values in LDAP group entries to the "MemberOf" attribute values in LDAP member (User or Template) entries.

This utility converts the LDAP server data to work in either the "MemberOf" mode, or "Both" mode. The utility searches through all specified group or template entries that hold one or more "Member" attribute values and modifies each value. The utility searches through all specified group/template entries and fetches their "Member" attribute values.

Each value is the DN of a member entry. The entry identified by this DN is added to the "MemberOf" attribute value of the group/template DN at hand. In addition, the utility delete those "Member" attribute values from the group/template, unless you run the command in the "Both" mode.

When your run the command, it creates a log file <code>ldapmemberconvert.log</code> in the current working directory. The command logs all modifications done and errors encountered in that log file.

Important - Back up the LDAP server database *before* you run this conversion utility.

Notes:

a

- You can run this command only in the Expert mode.
- On a Multi-Domain Server, you must run this command in the context of the applicable Domain Management Server:

mdsenv <IP Address or Name of Domain Management Server>

Syntax

```
ldapmemberconvert [-d <Debug Level>] -h <LDAP Server> -p <LDAP
Server Port> -D <LDAP Admin DN> -w <LDAP Admin Password> -m
<Member Attribute Name> -o <MemberOf Attribute Name> -c <Member
ObjectClass Value> [-B] [-f <File> | -g <Group DN>] [-L <LDAP
Server Timeout>] [-M <Number of Updates>] [-S <Size>] [-T <LDAP
Client Timeout>] [-Z]
```

Parameter	Description
-d < <i>Debug Level</i> >	Runs the command in debug mode with the specified TDERROR debug level. Valid values are from 0 (disabled) to 5 (maximum level, recommended).
-h < <i>LDAP Server</i> >	Specifies the LDAP Server computer by its IP address or resolvable hostname. If you do not specify the LDAP Server explicitly, the command connects to localhost.
-p <ldap server<br="">Port></ldap>	Specifies the LDAP Server port. Default is 389.
-D <ldap admin<br="">DN></ldap>	Specifies the LDAP Server administrator Distinguished Name.
-w <ldap admin<br="">Password></ldap>	Specifies the LDAP Server administrator password.
-m <member Attribute Name></member 	Specifies the LDAP attribute name when fetching and (possibly) deleting a group Member attribute value.
-o <memberof Attribute Name></memberof 	Specifies the LDAP attribute name for adding an LDAP "MemberOf" attribute value.
-c <member ObjectClass Value></member 	Specifies the LDAP "ObjectClass" attribute value that defines, which type of member to modify. You can specify multiple attribute values with this syntax: -c <member 1="" class="" object=""> -c <member object<br="">Class 2>c <member class="" n="" object=""></member></member></member>
-В	Specifies to run in "Both" mode.
-f <file></file>	Specifies the file that contains a list of Group DNs separated by a new line: <pre></pre>

Parameter	Description
-g <group dn=""></group>	Specifies the Group or Template Distinguished Name, on which to perform the conversion. You can specify multiple Group DNs with this syntax: -g <group 1="" dn=""> -g <group 2="" dn="">g <group dn="" n=""></group></group></group>
-L <ldap server<br="">Timeout></ldap>	Specifies the Server side time limit for LDAP operations, in seconds. Default is "never".
-M <number of<br="">Updates></number>	Specifies the maximum number of simultaneous member LDAP updates. Default is 20.
-S <size></size>	Specifies the Server side size limit for LDAP operations, in number of entries. Default is "none".
-T <ldap client<br="">Timeout></ldap>	Specifies the Client side timeout for LDAP operations, in milliseconds. Default is "never".
- Z	Specifies to use SSL connection.

Notes

There are two "GroupMembership" modes. You must keep these modes consistent:

- template-to-groups
- user-to-groups

For example, if you apply conversion on LDAP users to include the "MemberOf" attributes for their groups, then this conversion has to be applied on LDAP defined templates for their groups.

Troubleshooting

Symptom:

A command fails with an error message stating the connection stopped unexpectedly when you run it with the parameter -M < Number of Updates>.

Root Cause:

The LDAP server could not handle that many LDAP requests simultaneously and closed the connection.

Solution:

Run the command again with a lower value for the "-M" parameter. The default value should be adequate, but can also cause a connection failure in extreme situations. Continue to reduce the value until the command runs normally. Each time you run the command with the same set of groups, the command continues from where it left off.

Examples

Example 1

A group is defined with the DN "cn=cpGroup, ou=groups, ou=cp, c=us" and these attributes:

```
...
cn=cpGroup
uniquemember="cn=member1,ou=people,ou=cp,c=us"
uniquemember="cn=member2,ou=people,ou=cp,c=us"
...
```

For the two member entries:

```
...
cn=member1
objectclass=fw1Person
...
```

and:

```
cn=member2
objectclass=fw1Person
...
```

Run:

```
[Expert@MGMT:0]# ldapconvert -g cn=cpGroup,ou=groups,ou=cp,c=us -h MyLdapServer -d cn=admin -w secret -m uniquemember -o memberof -c fwlPerson
```

The result for the group DN is:



The result for the two member entries is:

```
...
cn=member1
objectclass=fw1Person
memberof="cn=cpGroup,ou=groups,ou=cp,c=us"
...
```

and:

```
cn=member2
objectclass=fw1Person
memberof="cn=cpGroup,ou=groups,ou=cp,c=us"
...
```

If you run the same command with the "-B" parameter, it produces the same result, but the group entry is not modified.

Example 2

If there is another member attribute value for the same group entry:

```
uniquemember="cn=template1,ou=people, ou=cp,c=us"
```

and the template is:

```
cn=member1
objectclass=fw1Template
```

Then after running the same command, the template entry stays intact, because of the parameter "-c fwlPerson", but the object class of "template1" is "fwlTemplate".

Idapmodify

Description

This is an LDAP utility that imports users to an LDAP server. The input file must be in the LDIF format.

Notes:

- You can run this command only in the Expert mode.
- On a Multi-Domain Server, you must run this command in the context of the applicable Domain Management Server:

mdsenv <IP Address or Name of Domain Management Server>

Syntax

```
ldapmodify [-d <Debug Level>] [-h <LDAP Server>] [-p <LDAP Server
Port>] [-D <LDAP Admin DN>] [-w <LDAP Admin Password>] [-a] [-b]
[-c] [-F] [-k] [-n] [-r] [-v] [-T <LDAP Client Timeout>] [-Z] [ -f
<Input File> .ldif | < <Entry>]
```

Parameter	Description
-d < <i>Debug Level</i> >	Runs the command in debug mode with the specified TDERROR debug level. Valid values are from 0 (disabled) to 5 (maximum level, recommended).
-h < <i>LDAP Server</i> >	Specifies the LDAP Server computer by its IP address or resolvable hostname. If you do not specify the LDAP Server explicitly, the command connects to localhost.
-p <ldap server<br="">Port></ldap>	Specifies the LDAP Server port. Default is 389.
-D <ldap admin<br="">DN></ldap>	Specifies the LDAP Server administrator Distinguished Name.
-w <ldap admin<br="">Password></ldap>	Specifies the LDAP Server administrator password.

Idapmodify

Parameter	Description
-a	Specifies that this is the LDAP "add" operation.
-b	Specifies to read values from files (for binary attributes).
-c	Specifies to ignore errors during continuous operation.
-F	Specifies to force changes on all records.
-k	Specifies the Kerberos bind.
-K	Specifies the Kerberos bind, part 1 only.
-n	Specifies to print the LDAP "add" operations, but do not actually perform them.
-r	Specifies to replace values, instead of adding values.
-v	Specifies to run in verbose mode.
-T <ldap client<br="">Timeout></ldap>	Specifies the Client side timeout for LDAP operations, in milliseconds. Default is "never".
-Z	Specifies to use SSL connection.
-f < <i>Input</i> <i>File</i> >.ldif	Specifies to read from the < Input File>.ldif file. The input file must be in the LDIF format.
< <entry></entry>	Specifies to read the entry from the <i>stdin</i> . The "<" character is mandatory part of the syntax. It specifies the input comes from the standard input (from the data you enter on the screen).

Idapsearch

Description

This is an LDAP utility that queries an LDAP directory and returns the results.

Notes:

- You can run this command only in the Expert mode.
- On a Multi-Domain Server, you must run this command in the context of the applicable Domain Management Server:

mdsenv <IP Address or Name of Domain Management Server>

Syntax

```
ldapsearch [-d <Debug Level>] [-h <LDAP Server>] [-p <LDAP Port>]
[-D <LDAP Admin DN>] [-w <LDAP Admin Password>] [-A] [-B] [-b
<Base DN>] [-F <Separator>] [-1 <LDAP Server Timeout>] [-s
<Scope>] [-S <Sort Attribute>] [-t] [-T <LDAP Client Timeout>] [-
u] [-z <Number of Search Entries>] [-Z] <Filter> [<Attributes>]
```

Parameter	Description
-d < <i>Debug Level</i> >	Runs the command in debug mode with the specified TDERROR debug level. Valid values are from 0 (disabled) to 5 (maximum level, recommended).
-h < <i>LDAP Server</i> >	Specifies the LDAP Server computer by its IP address or resolvable hostname. If you do not specify the LDAP Server explicitly, the command connects to localhost.
-p <ldap port=""></ldap>	Specifies the LDAP Server port. Default is 389.
-D <ldap admin<br="">DN></ldap>	Specifies the LDAP Server administrator Distinguished Name.
-w <ldap admin<br="">Password></ldap>	Specifies the LDAP Server administrator password.
-A	Specifies to retrieve attribute names only, without values.

Parameter	Description
-В	Specifies not to suppress the printing of non-ASCII values.
-b < <i>Base DN</i> >	Specifies the Base Distinguished Name (DN) for search.
-F < <i>Separator</i> >	Specifies the print separator character between attribute names and their values. The default separator is the equal sign (=).
-l <ldap server<br="">Timeout></ldap>	Specifies the Server side time limit for LDAP operations, in seconds. Default is "never".
-s <scope></scope>	Specifies the search scope. One of these: base one sub
-S <sort Attribute></sort 	Specifies to sort the results by the values of this attribute.
-t	Specifies to write values to files in the /tmp/ directory. Writes each <attribute>-<value> pair to a separate file named: /tmp/ldapsearch-<attribute>-<value> For example, for the fw1color attribute with the value a00188, the command writes to the file named: /tmp/ldapsearch-fw1color-a00188</value></attribute></value></attribute>
-T <ldap client<br="">Timeout></ldap>	Specifies the Client side timeout for LDAP operations, in milliseconds. Default is never.
-u	Specifies to show user-friendly entry names in the output. For example: shows cn=Babs Jensen, users, omi instead of cn=Babs Jensen, cn=users, cn=omi
-z <number of<br="">Search Entries></number>	Specifies the maximum number of entries to search on the LDAP Server.
- Z	Specifies to use SSL connection.
<filter></filter>	LDAP search filter compliant with RFC-1558. For example: objectclass=fw1host

Parameter	Description
<attributes></attributes>	Specifies the list of attributes to retrieve. If you do not specify attributes explicitly, then the command retrieves all attributes.

Example

[Expert@MGMT:0]# ldapsearch -p 18185 -b cn=omi objectclass=fwlhost objectclass

With this syntax, the command:

- 1. Connects to the LDAP Server to port 18185.
- 2. Connects to the LDAP Server with Base DN "cn=omi".
- 3. Queries the LDAP directory for "fwlhost" objects.
- 4. For each object found, prints the value of its "objectclass" attribute.

mgmt_cli

Description

The ${\tt mgmt_cli}$ tool works directly with the management database on your Management Server.

Syntax on Management Server or Security Gateway running on Gaia OS

mgmt_cli <Command Name> <Command Parameters> <Optional Switches>

Syntax on SmartConsole computer running on Windows OS 32-bit

Open Windows Command Prompt and run these commands:

```
cd /d "%ProgramFiles%\CheckPoint\SmartConsole\<VERSION>\PROGRAM\"
mgmt_cli.exe <Command Name> <Command Parameters> <Optional
Switches>
```

Syntax on SmartConsole computer running on Windows OS 64-bit

Open Windows Command Prompt and run these commands:

```
cd /d "%ProgramFiles
(x86)%\CheckPoint\SmartConsole\<VERSION>\PROGRAM\"
mgmt_cli.exe <Command Name> <Command Parameters> <Optional
Switches>
```

Notes

- For a complete list of the mgmt_cli options, enter the mgmt_cli (mgmt_cli.exe) command and press Enter.
- For more information, see the *Check Point Management API Reference*.

migrate

Important - This command is used to migrate the management database from R80.10 and lower versions.

For more information, see the <u>R82 Installation and Upgrade Guide</u>.

Description

Exports the management database and applicable Check Point configuration.

Imports the exported management database and applicable Check Point configuration.

Backing up and restoring in Management High Availability environment:

- To back up and restore a consistent environment, make sure to collect and restore the backups and snapshots from all servers in the High Availability environment at the same time.
- Make sure other administrators do not make changes in SmartConsole until the backup operation is completed.

For more information:

- About Gaia Backup and Gaia Snapshot, see the <u>R82 Gaia Administration</u> <u>Guide</u>.
- About Virtual Machine Snapshots, see the vendor documentation.

Notes:

- You must run this command from the Expert mode.
- If it is necessary to back up the current management database, and you do not plan to import it on a Management Server that runs a higher software version, then you can use the built-in command in the \$FWDIR/bin/upgrade_tools/ directory.
- If you plan to import the management database on a Management Server that runs a higher software version, then you must use the migrate utility from the migration tools package created specifically for that higher software version. See the Installation and Upgrade Guide for that higher software version.
- If this command completes successfully, it creates this log file: /var/log/opt/CPshrd-R82/migrate-<YYYY.MM.DD_HH.MM.SS>.log For example: /var/log/opt/CPshrd-R82/migrate-2019.06.14_11.03.46.log
- If this command fails, it creates this log file: \$CPDIR/log/migrate-<YYYY.MM.DD_HH.MM.SS>.log For example: /opt/CPshrd-R82/log/migrate-2019.06.14_11.21.39.log

Syntax

To see the built-in help:

```
[Expert@MGMT:0]# ./migrate -h
```

• To export the management database and configuration:

```
[Expert@MGMT:0]# cd $FWDIR/bin/upgrade_tools/
[Expert@MGMT:0]# yes | nohup ./migrate export [-l | -x] [-n]
[--exclude-uepm-postgres-db] [--include-uepm-msi-files] /<Full
Path>/<Name of Exported File> &
```

• To import the management database and configuration:

```
[Expert@MGMT:0]# cd $FWDIR/bin/upgrade_tools/
[Expert@MGMT:0]# yes | nohup ./migrate import [-l | -x] [-n]
[--exclude-uepm-postgres-db] [--include-uepm-msi-files] /<Full
Path>/<Name of Exported File>.tgz &
```

Parameter	Description
-h	Shows the built-in help.
yes nohup ./migrate &	 This syntax: 1. Sends the "yes" input to the interactive "migrate" command through the pipeline. 2. The "nohup" forces the "migrate" command to ignore the hangup signals from the shell. 3. The "&" forces the command to run in the background. As a result, when the CLI session closes, the command continues to run in the background. See: <u>sk133312</u> <u>https://linux.die.net/man/1/bash</u> <u>https://linux.die.net/man/1/nohup</u>
export	Exports the management database and applicable Check Point configuration.
import	Imports the management database and applicable Check Point configuration that were exported from another Management Server.

Parameter	Description
-1	Exports and imports the Check Point logs <i>without</i> log indexes in the \$FWDIR/log/ directory. important:
	 The command can export only closed logs (to which the information is not currently written). If you use this parameter, it can take the command a long time to complete (depends on the number of logs).
-x	Exports and imports the Check Point logs with their log indexes in the <pre>\$FWDIR/log/ directory.</pre> Important:
	 This parameter only supports Management Servers and Log Servers R80.10 and higher. The command can export only closed logs (to which the information is not currently written). If you use this parameter, it can take the command a long time to complete (depends on the number of logs and indexes).
-n	Runs silently (non-interactive mode) and uses the default options for each setting.
	 If you export a management database in this mode and the specified name of the exported file matches the name of an existing file, the command overwrites the existing file without prompting. If you import a management database in this mode, the
	"migrate import" command runs the "cpstop" command automatically.
exclude- uepm- postgres-db	 During the export operation, does not back up the PostgreSQL database from the Endpoint Security Management Server. During the import operation, does not restore the PostgreSQL database on the Endpoint Security Management Server.
include- uepm-msi- files	 During the export operation, backs up the MSI files from the Endpoint Security Management Server. During the import operation, restores the MSI files on the Endpoint Security Management Server.
/ <full path="">/</full>	Absolute path to the exported database file. This path must exist.

Parameter	Description
<name of<="" th=""><td> During the export operation, specifies the name of the output file.</td></name>	 During the export operation, specifies the name of the output file.
Exported	The command automatically adds the *.tgz extension. During the import operation, specifies the name of the exported file.
File>	You must manually enter the *.tgz extension in the end.

Example 1 - Export operation succeeded

```
[Expert@MGMT:0]# cd $FWDIR/bin/upgrade_tools/
[Expert@MGMT:0]# ./migrate export /var/log/Migrate_Export
You are required to close all clients to Security Management Server
or execute 'cpstop' before the Export operation begins.
Do you want to continue? (y/n) [n]? y
Copying required files...
Compressing files...
The operation completed successfully.
Location of archive with exported database: /var/log/Migrate_Export.tgz
[Expert@MGMT:0]#
[Expert@MGMT:0]# find / -name migrate-\* -type f
/var/log/opt/CPshrd-R82/migrate-2019.06.14_11.03.46.log
[Expert@MGMT:0]#
```

Example 2 - Export operation failed

```
[Expert@MGMT:0]# ./migrate export /var/log/My_Migrate_Export
Execution finished with errors. See log file '/opt/CPshrd-R82/log/migrate-2019.06.14_
11.21.39.log' for further details
[Expert@MGMT:0]#
```

migrate_server

- Important This command is used to migrate the management database from R80.20.M1, R80.20, R80.20.M2, R80.30, and higher versions.
 For more information, see:
 - sk135172 Upgrade Tools
 - The <u>R82 Installation and Upgrade Guide</u>

Description

Exports the management database and applicable Check Point configuration.

Imports the exported management database and applicable Check Point configuration.

Backing up and restoring in Management High Availability environment:

- To back up and restore a consistent environment, make sure to collect and restore the backups and snapshots from all servers in the High Availability environment at the same time.
- Make sure other administrators do not make changes in SmartConsole until the backup operation is completed.

For more information:

- About Gaia Backup and Gaia Snapshot, see the <u>R82 Gaia Administration</u> Guide.
- About Virtual Machine Snapshots, see the vendor documentation.

Notes:

- You must run this command from the Expert mode.
- If it is necessary to back up the current management database, and you do not plan to import it on a Management Server that runs a higher software version, then you can use the built-in command in the \$FWDIR/scripts/directory.
- If you plan to import the management database on a Management Server that runs a higher software version, then you must use the migrate_server utility from the migration tools package created specifically for that higher software version. See the Installation and Upgrade Guide for that higher software version.
- If this command completes successfully, it creates this log file: /var/log/opt/CPshrd-R82/migrate-<YYYY.MM.DD_HH.MM.SS>.log For example: /var/log/opt/CPshrd-R82/migrate-2022.06.14_11.03.46.log
- If this command fails, it creates this log file: \$CPDIR/log/migrate-<YYYY.MM.DD_HH.MM.SS>.log For example: /opt/CPshrd-R82/log/migrate-2024 - 2025.06.14_11.21.39.log

Important - If it is necessary to back up the current management database, and you do not plan to import it on a Management Server that runs a higher software version, then you must make sure the source Management Server and the target Management Server run the same Jumbo Hotfix Accumulator Take and all other private hotfixes.

To see all the installed software packages, you can run this command: <code>cpinfo -y all</code>

Syntax

To see the built-in help:

```
[Expert@MGMT:0]# cd $FWDIR/scripts/
[Expert@MGMT:0]# ./migrate_server -h
```

To run the Pre-Upgrade Verifier:

```
[Expert@MGMT:0]# cd $FWDIR/scripts/
[Expert@MGMT:0]# ./migrate_server verify -v R82 [-skip_
upgrade_tools_check]
```

• To export the management database and configuration:

```
[Expert@MGMT:0]# cd $FWDIR/scripts/
[Expert@MGMT:0]# ./migrate_server export -v R82 [-skip_
upgrade_tools_check] [-1 | -x] [--include-uepm-msi-files] [--
exclude-uepm-postgres-db] [--ignore_warnings] /<Full
Path>/<Name of Exported File>
```

• To import the management database and configuration:

```
[Expert@MGMT:0]# cd $FWDIR/scripts/
[Expert@MGMT:0]# ./migrate_server import -v R82 [-skip_
upgrade_tools_check] [-1 | -x] [/var/log/mdss.json] [--
include-uepm-msi-files] [--exclude-uepm-postgres-db] /<Full
Path>/<Name of Exported File>.tgz
```

To import the Domain Management Server database and configuration on a Security Management Server:

```
[Expert@MGMT:0]# cd $FWDIR/scripts/
[Expert@MGMT:0]# ./migrate_server migrate_import_domain -v R82
[-skip_upgrade_tools_check] [-1 | -x] [/var/log/mdss.json] [--
include-uepm-msi-files] [--exclude-uepm-postgres-db] /<Full
Path>/<Name of Exported File>.tgz
```

Parameter	Description
-h	Shows the built-in help.
export	Exports the management database and applicable Check Point configuration.
import	Imports the management database and applicable Check Point configuration that were exported from another Management Server. Important: This command automatically restarts Check Point services (runs the "cpstop" and "cpstart" commands). This note applies to a Multi-Domain Security Management environment, if at least one of the servers changes its IPv4 address comparing to the source server, from which you exported its database. You must do these steps before you start the upgrade and import: You must create a special JSON configuration file with the new IPv4 address(es). Syntax: Syntax: [{"name":" <name 1="" in="" object="" of="" server="" smartconsole="">", "newIpAddress4":"<new 1="" address="" ipv4="" of="" server="">"}, {"name":"<name 2="" in="" object="" of="" server="" smartconsole="">", "newIpAddress4":"<new 2="" address="" ipv4="" of="" server="">"}] Evemple:</new></name></new></name>
	<pre>Example: [{"name":"MyPrimaryMultiDomainServer","new IpAddress4":"172.30.40.51"}, {"name":"MySecondaryMultiDomainServer","ne wIpAddress4":"172.30.40.52"}] 2. You must call this file: mdss.json 3. You must put this file on all servers in this directory: /var/log/</pre>
migrate_ import_ domain	 On a Security Management Server, imports the management database and applicable Check Point configuration that were exported from a Domain Management Server. Important - This command automatically restarts Check Point services (runs the "cpstop" and "cpstart" commands).

Parameter	Description
verify	Verifies the management database and applicable Check Point configuration that were exported from another Management Server.
-v R82	Specifies the version, to which you plan to migrate / upgrade.
-skip_ upgrade_ tools_check	 Does not try to connect to Check Point Cloud to check for a more recent version of the Upgrade Tools. Best Practice - Use this parameter on the Management Server that is not connected to the Internet.
-1	 Exports and imports the Check Point logs <i>without</i> log indexes in the \$FWDIR/log/directory. Important: The command can export only closed logs (to which the information is not currently written). If you use this parameter, it can take the command a long time to complete (depends on the number of logs).
-x	 Exports and imports the Check Point logs with their log indexes in the \$FWDIR/log/ directory. Important: Before you use this parameter, it is necessary to make sure all log indexes are closed and saved. Run this command in the Expert mode and wait for the output to show "Solr stopped": \$RTDIR/scripts/stopSolr.sh This parameter only supports Management Servers and Log Servers R80.10 and higher. The command can export only closed logs (to which the information is not currently written). If you use this parameter, it can take the command a long time to complete (depends on the number of logs and indexes).

Parameter	Description
/var/log/md ss.json	Specifies the absolute path to the special JSON configuration file with new IPv4 addresses. The path and filename are mandatory. This file is mandatory during an upgrade of a Multi-Domain Security Management environment. Even if only one of the servers migrates to a new IP address, all the other servers must get this configuration file for the import process. Syntax:
	<pre>[{"name":"<name 1="" in<br="" object="" of="" server="">SmartConsole>","newIpAddress4":"<new address<br="" ipv4="">of Server 1>"}, {"name":"<name 2="" in<br="" object="" of="" server="">SmartConsole>","newIpAddress4":"<new address<br="" ipv4="">of Server 2>"}]</new></name></new></name></pre>
	Example:
	<pre>[{"name":"MyPrimaryMultiDomainServer","newIpAddress 4":"172.30.40.51"}, {"name":"MySecondaryMultiDomainServer","newIpAddres s4":"172.30.40.52"}]</pre>
include- uepm-msi- files	 During the export operation, backs up the MSI files from the Endpoint Security Management Server. During the import operation, restores the MSI files on the Endpoint Security Management Server.
exclude- uepm- postgres-db	 During the export operation, does not back up the PostgreSQL database from the Endpoint Security Management Server. During the import operation, does not restore the PostgreSQL database on the Endpoint Security Management Server.
ignore_ warnings Or -ivw	 If during an upgrade procedure, the Pre-Upgrade Verifier shows warnings, you can use this parameter to ignore warnings and continue the upgrade. Important - To prevent issues during and after upgrade, we strongly recommend to resolve all issues and not use this parameter.
exclude- licenses	 During the export operation, does not back up the licenses from the Management Server. During the import operation, does not restore the license on the Management Server.

Parameter	Description
no_ progress_ bar or -npb	Disables the progress bar in the command line.
-n	Disables the interactive mode.
/ <full Path>/<name of Exported File></name </full 	 Specifies the absolute path to the exported database file. This path must exist. During the export operation, specifies the name of the output file. The command automatically adds the *.tgz extension. During the import operation, specifies the name of the exported file. You must manually enter the *.tgz extension in the end.

Example 1 - Export operation succeeded

```
[Expert@MGMT:0]# cd $FWDIR/scripts/
[Expert@MGMT:0]# ./migrate_server export /var/log/Migrate_Export
You are required to close all clients to Security Management Server
or execute 'cpstop' before the Export operation begins.
Do you want to continue? (y/n) [n]? y
Copying required files...
Compressing files...
The operation completed successfully.
Location of archive with exported database: /var/log/Migrate_Export.tgz
[Expert@MGMT:0]#
[Expert@MGMT:0]# find / -name migrate-\* -type f
/var/log/opt/CPshrd-R82/migrate-2024 - 2025.06.14_11.03.46.log
[Expert@MGMT:0]#
```

Example 2 - Export operation failed

```
[Expert@MGMT:0]# ./migrate_server export /var/log/My_Migrate_Export
Execution finished with errors. See log file '/opt/CPshrd-R82/log/migrate-2024 - 2025.06.14_
11.21.39.log' for further details
[Expert@MGMT:0]#
```

queryDB_util

Description

Searches in the management database for objects or policy rules.

Important - This command is obsolete for R80 and higher. Use the "mgmt_cli" on page 985 command to search in the management database for objects or policy rules according to search parameters.

rs_db_tool

Description

Manages Dynamically Assigned IP address (DAIP) gateways in a DAIP database.

Notes:

- You can run this command only in the Expert mode.
- On a Multi-Domain Server, you must run this command in the context of the applicable Domain Management Server:

```
mdsenv <IP Address or Name of Domain Management Server>
```

Syntax

To add an entry to the DAIP database:

```
[Expert@MGMT:0]# rs_db_tool [-d] -operation add -name <Object
Name> -ip <IPv4 Address> -ip6 <Pv6 Address> -TTL <Time-To-
Live>
```

• To fetch a specific entry from the DAIP database:

```
[Expert@MGMT:0]# rs_db_tool [-d] -operation fetch -name
<Object Name>
```

• To delete a specific entry from the DAIP database:

```
[Expert@MGMT:0]# rs_db_tool [-d] -operation delete -name
<Object Name>
```

• To list all entries in the DAIP database:

```
[Expert@MGMT:0] # rs db tool [-d] -operation list
```

• To synchronize the DAIP database:

```
[Expert@MGMT:0] # rs_db_tool [-d] -operation sync
```

Note - You must run this command from the Expert mode.

Parameter	Description
-d	 Runs the command in debug mode. Use only if you troubleshoot the command itself. Best Practice - If you use this parameter, then redirect the output to a file, or use the script command to save the entire CLI session.
-name <object Name></object 	Specifies the name of the DAIP object.
-ip <ipv4 Address></ipv4 	Specifies the IPv4 address of the DAIP object
-ip6 <ipv6 Address></ipv6 	Specifies the IPv6 address of the DAIP object.
-TTL <time-to- Live></time-to- 	Specifies the relative time interval (in seconds), during which the entry is valid.

sam_alert

Description

For SAM v1, this utility executes Suspicious Activity Monitoring (SAM) actions according to the information received from the standard input.

For SAM v2, this utility executes Suspicious Activity Monitoring (SAM) actions with User Defined Alerts mechanism.

Important:

- You must run this command on the Management Server.
- You can run this command only in the Expert mode.
- On a Multi-Domain Server, you must run this command in the context of the applicable Domain Management Server:

mdsenv <IP Address or Name of Domain Management Server>

Notes:

- VSX Gateways and VSX Cluster Members do not support Suspicious Activity Monitoring (SAM) Rules. See <u>sk79700</u>.
- See the "fw sam" on page 892 and "fw sam_policy" on page 901 commands.

SAM v1 syntax

```
sam_alert [-v] [-o] [-s <SAM Server>] [-t <Time>] [-f <Security
Gateway>] [-C] {-n|-i|-I} {-src|-dst|-any|-srv}
```

Parameters for SAM v1

Parameter	Description
-V	Enables the verbose mode for the "fw sam" command.
-0	Specifies to print the input of this tool to the standard output (to use with pipes in a CLI syntax).
-s <sam Server></sam 	Specifies the SAM Server to be contacted. Default is "localhost".
-t <time></time>	Specifies the time (in seconds), during which to enforce the action. The default is forever.

Parameter	Description
-f <security Gateway></security 	 Specifies the Security Gateway / Cluster object, on which to run the operation. Important - If you do not specify the target Security Gateway / Cluster object explicitly, this command applies to all managed Security Gateways and Clusters.
-C	Cancels the specified operation.
-n	Specifies to notify every time a connection, which matches the specified criteria, passes through the Security Gateway / ClusterXL / Security Group.
-i	Inhibits (drops or rejects) connections that match the specified criteria.
-I	Inhibits (drops or rejects) connections that match the specified criteria and closes all existing connections that match the specified criteria.
-src	Matches the source address of connections.
-dst	Matches the destination address of connections.
-any	Matches either the source or destination address of connections.
-srv	Matches specific source, destination, protocol and port.

SAM v2 syntax

```
sam_alert -v2 [-v] [-0] [-S <SAM Server>] [-t <Time>] [-f
<Security Gateway>] [-n <Name>] [-c "<Comment">] [-0
<Originator>] [-l {r | a}] -a {d | r| n | b | q | i} [-C] {-ip
|-eth} {-src|-dst|-any|-srv}
```

Parameters for SAM v2

Parameter	Description
-v2	Specifies to use SAM v2.
-v	Enables the verbose mode for the "fw sam" command.
-0	Specifies to print the input of this tool to the standard output (to use with pipes in a CLI syntax).
-S < <i>SAM Server</i> >	Specifies the SAM server to be contacted. Default is "localhost".
-t <time></time>	Specifies the time (in seconds), during which to enforce the action. The default is forever.
-f <security Gateway></security 	 Specifies the Security Gateway / Cluster object, on which to run the operation. Important - If you do not specify the target Security Gateway / Cluster object explicitly, this command applies to all managed Security Gateways and Clusters.
-n < <i>Name</i> >	Specifies the name for the SAM rule. Default is empty.
-c " <comment>"</comment>	Specifies the comment for the SAM rule. Default is empty. You must enclose the text in the double quotes or single quotes.
-o <originator></originator>	Specifies the originator for the SAM rule. Default is "sam_alert".

Parameter	Description
-l {r a}	 Specifies the log type for connections that match the specified criteria: r - Regular a - Alert Default is None.
-a {d r n b q i}	Specifies the action to apply on connections that match the specified criteria: d - Drop r - Reject n - Notify b - Bypass q - Quarantine i - Inspect
-C	Specifies to close all existing connections that match the criteria.
-ip	Specifies to use IP addresses as criteria parameters.
-eth	Specifies to use MAC addresses as criteria parameters.
-src	Matches the source address of connections.
-dst	Matches the destination address of connections.
-any	Matches either the source or destination address of connections.
-srv	Matches specific source, destination, protocol and port.

Example

See <u>sk110873</u>: How to configure Security Gateway to detect and prevent port scan.

stattest

Description

Check Point AMON client to query SNMP OIDs.

You can use this command as an alternative to the standard SNMP commands for debug purposes - to make sure the applicable SNMP OIDs provide the requested information.



- You can run this command only in the Expert mode.
- On a Multi-Domain Server, you must run this command in the context of the applicable Domain Management Server:

mdsenv <IP Address or Name of Domain Management Server>

Syntax to query a Regular OID

• On a Management Server / Security Gateway / Cluster Member:

Notes:

- These Regular OIDs are specified in the SNMP MIB files.
- For Check Point MIB files, see sk90470.

Syntax to query a Statistical OID

On a Management Server / Security Gateway / Cluster Member:

Notes:

- These Statistical OIDs take some time to "initialize".
- For example, to calculate an average, it is necessary to collect enough samples.
- Check Point statistical OIDs are registered in the \$CPDIR/conf/statistical_ oid.conf file.

Parameter	Description
-d	 Runs the command in debug mode. Use only if you troubleshoot the command itself. Best Practice - If you use this parameter, then redirect the output to a file, or use the script command to save the entire CLI session.
-h <host></host>	Specifies the remote Check Point host to query by its IP address or resolvable hostname.
-p < <i>Port</i> >	Specifies the port number, on which the AMON server listens. Default port is 18192.
-x <proxy server=""></proxy>	 Specifies the Proxy Server by its IP address or resolvable hostname. Note - Use only when you query a remote host.
-l <polling interval=""></polling>	 Specifies the time in seconds between queries. Note - Use only when you query a Statistical OID.
-r <polling duration=""></polling>	 Specifies the time in seconds, during which to run consecutive queries. Note - Use only when you query a Statistical OID.
-t <timeout></timeout>	Specifies the session timeout in milliseconds.
<regular_oid_1> <regular_oid_2> <regular_oid_n></regular_oid_n></regular_oid_2></regular_oid_1>	 Specifies the Regular OIDs to query. Notes: OID must not start with period. Separate the OIDs with spaces. You can specify up to 100 OIDs.

Parameter	Description
<statistical_oid_1> <statistical_oid_2> <statistical_oid_n></statistical_oid_n></statistical_oid_2></statistical_oid_1>	 Specifies the Statistical OIDs to query. Notes: OID must not start with period. Separate the OIDs with spaces. You can specify up to 100 OIDs.

Example - Query a Regular OID

Query the CPU Idle utilization at the OID 1.3.6.1.4.1.2620.1.6.7.2.3 (procIdleTime).

[Expert@HostName]# stattest get 1.3.6.1.4.1.2620.1.6.7.4.2

Example - Query a Statistical OID

Query the CPU Idle utilization at the OID 1.3.6.1.4.1.2620.1.6.7.2.3 (procIdleTime).

Information is collected with intervals of 5 seconds during 5 seconds

[Expert@HostName]# stattest get -1 5 -r 5 1.3.6.1.4.1.2620.1.6.7.2.3

threshold_config

Description

You can configure a variety of different SNMP thresholds that generate SNMP traps, or alerts.

You can use these thresholds to monitor many system components automatically without requesting information from each object or device.

You configure these SNMP Monitoring Thresholds only on the Security Management Server, Multi-Domain Server, or Domain Management Server.

During policy installation, the managed a Security Gateway and Clusters receive and apply these thresholds as part of their policy.

For more information, see sk90860: How to configure SNMP on Gaia OS.

Procedure

Step	Instructions
1	Connect to the command line on the Management Server.
2	Log in to the Expert mode.
3	On a Multi-Domain Server, switch to the context of the applicable Domain Management Server:
	[Expert@HostName:0]# mdsenv <name address="" domain<br="" ip="" of="" or="">Management Server></name>
4	Go to the Threshold Engine Configuration menu: <pre>[Expert@HostName:0]# threshold_config</pre>

Step	Instructions
5	Select the applicable options and configure the applicable settings (see the Threshold Engine Configuration Options table below).
	Threshold Engine Configuration Options:
	<pre>(1) Show policy name (2) Set policy name (3) Save policy (4) Save policy to file (5) Load policy from file (6) Configure global alert settings (7) Configure alert destinations (8) View thresholds overview (9) Configure thresholds (e) Exit (m) Main Menu Enter your choice (1-9) :</pre>
6	Exit from the Threshold Engine Configuration menu.
7	Stop the CPD daemon: [Expert@HostName:0] # cpwd_admin stop -name CPD -path "\$CPDIR/bin/cpd_admin" -command "cpd_admin stop"
	See "cpwd_admin stop" on page 847.
8	Start the CPD daemon: [Expert@HostName:0] # cpwd_admin start -name CPD -path "\$CPDIR/bin/cpd" -command "cpd"
	See "cpwd_admin start" on page 844.
9	Wait for 10-20 seconds.
10	<pre>Verify that CPD daemon started successfully: [Expert@HostName:0] # cpwd_admin list egrep "STAT CPD" See "cpwd_admin list" on page 840.</pre>
11	In SmartConsole, install the Access Control Policy on Security Gateways and Clusters.

Threshold Engine Configuration Options

Menu item	Description
(1) Show policy name	Shows the name of the current configured threshold policy.
(2) Set policy name	Configures the name for the threshold policy. If you do not specify it explicitly, then the default name is "Default Profile".
(3) Save policy	Saves the changes in the current threshold policy.
(4) Save policy to file	Exports the configured threshold policy to a file. If you do not specify the path explicitly, the file is saved in the current working directory.
(5) Load policy from file	Imports a threshold policy from a file. If you do not specify the path explicitly, the file is imported from the current working directory.
(6) Configure global alert settings	 Configures global settings: How frequently alerts are sent (configured delay must be greater than 30 seconds) How many alerts are sent
(7) Configure alert destinations	Configures the SNMP Network Management System (NMS), to which the managed Security Gateways and Cluster Members send their SNMP alerts.
	Configure Alert Destinations Options: (1) View alert destinations (2) Add SNMP NMS (3) Remove SNMP NMS (4) Edit SNMP NMS
(8) View thresholds overview	 Shows a list of all available thresholds and their current settings. These include: Name Category (see the next option " (9) ") State (disabled or enabled) Threshold (threshold point, if applicable) Description

Menu item	Description
(9) Configure thresholds	Shows the list of threshold categories to configure. Thresholds Categories (1) Hardware (2) High Availability (3) Local Logging Mode Status (4) Log Server Connectivity (5) Networking (6) Resources See the Thresholds Categories table below.

Thresholds Categories

Category	Sub-Categories
(1) Hardware	Hardware Thresholds:
	 (1) RAID volume state (2) RAID disk state (3) RAID disk flags (4) Temperature sensor reading (5) Fan speed sensor reading (6) Voltage sensor reading
(2) High Availability	High Availability Thresholds: (1) Cluster member state changed (2) Cluster block state (3) Cluster state (4) Cluster problem status (5) Cluster interface status
(3) Local Logging Mode Status	Local Logging Mode Status Thresholds: (1) Local Logging Mode
(4) Log Server Connectivity	Log Server Connectivity Thresholds: (1) Connection with log server (2) Connection with all log servers

Category	Sub-Categories
(5) Networking	Networking Thresholds: (1) Interface Admin Status (2) Interface removed (3) Interface Operational Link Status (4) New connections rate (5) Concurrent connections rate (6) Bytes Throughput (7) Accepted Packet Rate (8) Drop caused by excessive traffic
(6) Resources	Resources Thresholds: (1) Swap Memory Utilization (2) Real Memory Utilization (3) Partition free space (4) Core Utilization (5) Core interrupts rate

Notes:

- If you run the threshold_config command *locally* on a Security Gateway or Cluster Members to configure the SNMP Monitoring Thresholds, then each policy installation erases these *local* SNMP threshold settings and reverts them to the *global* SNMP threshold settings configured on the Management Server that manages this Security Gateway or Cluster.
- On a Security Gateway and Cluster Members, you can save the local Threshold Engine Configuration settings to a file and load it locally later.
- The Threshold Engine Configuration is stored in the \$FWDIR/conf/thresholds.conf file.
- In a Multi-Domain Security Management environment:
 - You can configure the SNMP thresholds in the context of Multi-Domain Server (MDS) and in the context of each individual Domain Management Server.
 - Thresholds that you configure in the context of the Multi-Domain Server are for the Multi-Domain Server only.
 - Thresholds that you configure in the context of a Domain Management Server are for that Domain Management Server and its managed Security Gateway and Clusters.
 - If an SNMP threshold applies both to the Multi-Domain Server and a Domain Management Server, then configure the SNMP threshold both in the context of the Multi-Domain Server and in the context of the Domain Management Server.

However, in this scenario you can only get alerts from the Multi-Domain Server, if the monitored object exceeds the threshold. Example:

If you configure the CPU threshold, then when the monitored value exceeds the configured threshold, it applies to both the Multi-Domain Server and the Domain Management Server. However, only the Multi-Domain Server generates SNMP alerts.

Glossary

Α

Active Security Management Server

The Management Server in Management High Availability that is currently configured as Active.

Anti-Bot

Check Point Software Blade on a Security Gateway that blocks botnet behavior and communication to Command and Control (C&C) centers. Acronyms: AB, ABOT.

Anti-Spam

Check Point Software Blade on a Security Gateway that provides comprehensive protection for email inspection. Synonym: Anti-Spam & Email Security. Acronyms: AS, ASPAM.

Anti-Virus

Check Point Software Blade on a Security Gateway that uses real-time virus signatures and anomaly-based protections from ThreatCloud to detect and block malware at the Security Gateway before users are affected. Acronym: AV.

Application Control

Check Point Software Blade on a Security Gateway that allows granular control over specific web-enabled applications by using deep packet inspection. Acronym: APPI.

Audit Log

Log that contains administrator actions on a Management Server (login and logout, creation or modification of an object, installation of a policy, and so on).

В

Bridge Mode

Security Gateway or Virtual System that works as a Layer 2 bridge device for easy deployment in an existing topology.

Cluster

С

Two or more Security Gateways that work together in a redundant configuration - High Availability, or Load Sharing.

Cluster Member

Security Gateway that is part of a cluster.

Compliance

Check Point Software Blade on a Management Server to view and apply the Security Best Practices to the managed Security Gateways. This Software Blade includes a library of Check Point-defined Security Best Practices to use as a baseline for good Security Gateway and Policy configuration.

Content Awareness

Check Point Software Blade on a Security Gateway that provides data visibility and enforcement. Acronym: CTNT.

CoreXL

Performance-enhancing technology for Security Gateways on multi-core processing platforms. Multiple Check Point Firewall instances are running in parallel on multiple CPU cores.

CoreXL Firewall Instance

On a Security Gateway with CoreXL enabled, the Firewall kernel is copied multiple times. Each replicated copy, or firewall instance, runs on one processing CPU core. These firewall instances handle traffic at the same time, and each firewall instance is a complete and independent firewall inspection kernel. Synonym: CoreXL FW Instance.

CoreXL SND

Secure Network Distributer. Part of CoreXL that is responsible for: Processing incoming traffic from the network interfaces; Securely accelerating authorized packets (if SecureXL is enabled); Distributing non-accelerated packets between Firewall kernel instances (SND maintains global dispatching table, which maps connections that were assigned to CoreXL Firewall instances). Traffic distribution between CoreXL Firewall instances is statically based on Source IP addresses, Destination IP addresses, and the IP 'Protocol' type. The CoreXL SND does not really "touch" packets. The decision to stick to a particular FWK daemon is done at the first packet of connection on a very high level, before anything else. Depending on the SecureXL settings, and in most of the cases, the SecureXL can be offloading decryption calculations. However, in some other cases, such as with Route-Based VPN, it is done by FWK daemon.

CPUSE

Check Point Upgrade Service Engine for Gaia Operating System. With CPUSE, you can automatically update Check Point products for the Gaia OS, and the Gaia OS itself.

D

DAIP Gateway

Dynamically Assigned IP (DAIP) Security Gateway is a Security Gateway, on which the IP address of the external interface is assigned dynamically by the ISP.

Data Loss Prevention

Check Point Software Blade on a Security Gateway that detects and prevents the unauthorized transmission of confidential information outside the organization. Acronym: DLP.

Data Type

Classification of data in a Check Point Security Policy for the Content Awareness Software Blade.

Distributed Deployment

Configuration in which the Check Point Security Gateway and the Security Management Server products are installed on different computers.

Dynamic Object

Special object type, whose IP address is not known in advance. The Security Gateway resolves the IP address of this object in real time.

Endpoint Policy Management

Check Point Software Blade on a Management Server to manage an on-premises Harmony Endpoint Security environment.

Expert Mode

The name of the elevated command line shell that gives full system root permissions in the Check Point Gaia operating system.

G

Ε

Gaia

Check Point security operating system that combines the strengths of both SecurePlatform and IPSO operating systems.

Gaia Clish

The name of the default command line shell in Check Point Gaia operating system. This is a restricted shell (role-based administration controls the number of commands available in the shell).

Gaia Portal

Web interface for the Check Point Gaia operating system.

Η

Hotfix

Software package installed on top of the current software version to fix a wrong or undesired behavior, and to add a new behavior.

HTTPS Inspection

Feature on a Security Gateway that inspects traffic encrypted by the Secure Sockets Layer (SSL) protocol for malware or suspicious patterns. Synonym: SSL Inspection. Acronyms: HTTPSI, HTTPSI.

ICA

L

Internal Certificate Authority. A component on Check Point Management Server that issues certificates for authentication.

Identity Awareness

Check Point Software Blade on a Security Gateway that enforces network access and audits data based on network location, the identity of the user, and the identity of the computer. Acronym: IDA.

Identity Logging

Check Point Software Blade on a Management Server to view Identity Logs from the managed Security Gateways with enabled Identity Awareness Software Blade.

Inline Layer

Set of rules used in another rule in Security Policy.

Internal Network

Computers and resources protected by the Firewall and accessed by authenticated users.

IPS

Check Point Software Blade on a Security Gateway that inspects and analyzes packets and data for numerous types of risks (Intrusion Prevention System).

IPsec VPN

Check Point Software Blade on a Security Gateway that provides a Site to Site VPN and Remote Access VPN access.

J

Jumbo Hotfix Accumulator

Collection of hotfixes combined into a single package. Acronyms: JHA, JHF, JHFA.

Κ

Kerberos

An authentication server for Microsoft Windows Active Directory Federation Services (ADFS).

L

Log Server

Dedicated Check Point server that runs Check Point software to store and process logs.

Logging & Status

Check Point Software Blade on a Management Server to view Security Logs from the managed Security Gateways.

Μ

Management High Availability

Deployment and configuration mode of two Check Point Management Servers, in which they automatically synchronize the management databases with each other. In this mode, one Management Server is Active, and the other is Standby. Acronyms: Management HA, MGMT HA.

Management Interface

(1) Interface on a Gaia Security Gateway or Cluster member, through which Management Server connects to the Security Gateway or Cluster member. (2) Interface on Gaia computer, through which users connect to Gaia Portal or CLI.

Management Server

Check Point Single-Domain Security Management Server or a Multi-Domain Security Management Server.

Manual NAT Rules

Manual configuration of NAT rules by the administrator of the Check Point Management Server.

Mobile Access

Check Point Software Blade on a Security Gateway that provides a Remote Access VPN access for managed and unmanaged clients. Acronym: MAB.

Multi-Domain Log Server

Dedicated Check Point server that runs Check Point software to store and process logs in a Multi-Domain Security Management environment. The Multi-Domain Log Server consists of Domain Log Servers that store and process logs from Security Gateways that are managed by the corresponding Domain Management Servers. Acronym: MDLS.

Multi-Domain Server

Dedicated Check Point server that runs Check Point software to host virtual Security Management Servers called Domain Management Servers. Synonym: Multi-Domain Security Management Server. Acronym: MDS.

Ν

Network Object

Logical object that represents different parts of corporate topology - computers, IP addresses, traffic protocols, and so on. Administrators use these objects in Security Policies.

Network Policy Management

Check Point Software Blade on a Management Server to manage an on-premises environment with an Access Control and Threat Prevention policies.

0

Open Server

Physical computer manufactured and distributed by a company, other than Check Point.

Ρ

Package Repository

Collection of software packages that were uploaded to the Management Server. You can easily install these packages in SmartConsole on the managed Security Gateways.

Permission Profile

Predefined group of SmartConsole access permissions assigned to Domains and administrators. With this feature you can configure complex permissions for many administrators with one definition.

Policy Layer

Layer (set of rules) in a Security Policy.

Policy Package

Collection of different types of Security Policies, such as Access Control, Threat Prevention, QoS, and Desktop Security. After installation, Security Gateways enforce all Policies in the Policy Package.

Primary Security Management Server

The Security Management Server in Management High Availability that you install as Primary.

Provisioning

Check Point Software Blade on a Management Server that manages large-scale deployments of Check Point Security Gateways using configuration profiles. Synonyms: SmartProvisioning, SmartLSM, Large-Scale Management, LSM.

Q

QoS

Check Point Software Blade on a Security Gateway that provides policy-based traffic bandwidth management to prioritize business-critical traffic and guarantee bandwidth and control latency.

R

Rule

Set of traffic parameters and other conditions in a Rule Base (Security Policy) that cause specified actions to be taken for a communication session.

Rule Base

All rules configured in a given Security Policy. Synonym: Rulebase.

Secondary Security Management Server

The Security Management Server in Management High Availability that you install as Secondary.

SecureXL

S

Check Point product on a Security Gateway that accelerates IPv4 and IPv6 traffic that passes through a Security Gateway.

Security Gateway

Dedicated Check Point server that runs Check Point software to inspect traffic and enforce Security Policies for connected network resources.

Security Management Server

Dedicated Check Point server that runs Check Point software to manage the objects and policies in a Check Point environment within a single management Domain. Synonym: Single-Domain Security Management Server.

Security Policy

Collection of rules that control network traffic and enforce organization guidelines for data protection and access to resources with packet inspection.

SIC

Secure Internal Communication. The Check Point proprietary mechanism with which Check Point computers that run Check Point software authenticate each other over SSL, for secure communication. This authentication is based on the certificates issued by the ICA on a Check Point Management Server.

SmartConsole

Check Point GUI application used to manage a Check Point environment - configure Security Policies, configure devices, monitor products and events, install updates, and so on.

SmartDashboard

Legacy Check Point GUI client used to create and manage the security settings in versions R77.30 and lower. In versions R80.X and higher is still used to configure specific legacy settings.

SmartProvisioning

Check Point Software Blade on a Management Server (the actual name is "Provisioning") that manages large-scale deployments of Check Point Security Gateways using configuration profiles. Synonyms: Large-Scale Management, SmartLSM, LSM.

SmartUpdate

Legacy Check Point GUI client used to manage licenses and contracts in a Check Point environment.

Software Blade

Specific security solution (module): (1) On a Security Gateway, each Software Blade inspects specific characteristics of the traffic (2) On a Management Server, each Software Blade enables different management capabilities.

Standalone

Configuration in which the Security Gateway and the Security Management Server products are installed and configured on the same server.

Standby Security Management Server

The Security Management Server in Management High Availability that is currently configured as Standby.

Т

Threat Emulation

Check Point Software Blade on a Security Gateway that monitors the behavior of files in a sandbox to determine whether or not they are malicious. Acronym: TE.

Threat Extraction

Check Point Software Blade on a Security Gateway that removes malicious content from files. Acronym: TEX.

U

Updatable Object

Network object that represents an external service, such as Microsoft 365, AWS, Geo locations, and more.

URL Filtering

Check Point Software Blade on a Security Gateway that allows granular control over which web sites can be accessed by a given group of users, computers or networks. Acronym: URLF.

User Database

Check Point internal database that contains all users defined and managed in SmartConsole.

User Directory

Check Point Software Blade on a Management Server that integrates LDAP and other external user management servers with Check Point products and security solutions.

User Group

Named group of users with related responsibilities.

User Template

Property set that defines a type of user on which a security policy will be enforced.

V

VSX

Virtual System Extension. Check Point virtual networking solution, hosted on a computer or cluster with virtual abstractions of Check Point Security Gateways and other network devices. These Virtual Devices provide the same functionality as their physical counterparts.

VSX Gateway

Physical server that hosts VSX virtual networks, including all Virtual Devices that provide the functionality of physical network devices. It holds at least one Virtual System, which is called VS0.

Ζ

Zero Phishing

Check Point Software Blade on a Security Gateway (R81.20 and higher) that provides real-time phishing prevention based on URLs. Acronym: ZPH.